

# **Table of Contents**

Preface	1
Document Conventions	2
Typographic Conventions	2
Pull-quote Conventions	4
Notes and Warnings	5
Provide feedback to the authors!	6
1. Introduction	7
2. Pre-Requisites	8
3. Hardware Setup	10
4. Downloading and Installing	11
4.1. Binary Download and Installation	11
4.2. Directory Structure	11
4.3. Setup from Source	12
5. Post Installation Configuration	14
6. Uninstalling	
Appendix A: Java Development Kit (): Installing, Configuring and Running	16
Appendix B: Setting the JBOSS_HOME Environment Variable	19
Annendix C. Revision History	2.2

# **Preface**

## **Document Conventions**

This manual uses several conventions to highlight certain words and phrases and draw attention to specific pieces of information.

In PDF and paper editions, this manual uses typefaces drawn from the Liberation Fonts set. The Liberation Fonts set is also used in HTML editions if the set is installed on your system. If not, alternative but equivalent typefaces are displayed. Note: Red Hat Enterprise Linux 5 and later includes the Liberation Fonts set by default.

## **Typographic Conventions**

Four typographic conventions are used to call attention to specific words and phrases. These conventions, and the circumstances they apply to, are as follows.

#### Mono-spaced Bold

Used to highlight system input, including shell commands, file names and paths. Also used to highlight key caps and key-combinations. For example:

To see the contents of the file <code>my\_next\_bestselling\_novel</code> in your current working directory, enter the <code>cat my\_next\_bestselling\_novel</code> command at the shell prompt and press <code>Enter</code> to execute the command.

The above includes a file name, a shell command and a key cap, all presented in Mono-spaced Bold and all distinguishable thanks to context.

Key-combinations can be distinguished from key caps by the hyphen connecting each part of a key-combination. For example:

Press Enter to execute the command.

Press to switch to the first virtual terminal. Press to return to your X-Windows session.

The first sentence highlights the particular key cap to press. The second highlights two sets of three key caps, each set pressed simultaneously.

If source code is discussed, class names, methods, functions, variable names and returned values mentioned within a paragraph will be presented as above, in Mono-spaced Bold. For example:

File-related classes include filesystem for file systems, file for files, and dir for directories. Each class has its own associated set of permissions.

#### Proportional Bold

This denotes words or phrases encountered on a system, including application names; dialogue box text; labelled buttons; check-box and radio button labels; menu titles and sub-menu titles. For example:

Choose **System > Preferences > Mouse** from the main menu bar to launch Mouse Preferences. In the Buttons tab, click the Left-handed mouse check box and click **[ Close ]** to switch the primary mouse button from the left to the right (making the mouse suitable for use in the left hand).

To insert a special character into a <code>gedit</code> file, choose <code>Applications > Accessories > Character Map</code> from the main menu bar. Next, choose <code>Search > Find | ]</code> from the <code>Character Map</code> menu bar | type the name of the character in the <code>Search field</code> and <code>click [Next</code>. The character you sought will be highlighted in the Character Table. Double-click this highlighted character to place it in the Text to copy field and then click the <code>[Copy]</code> button. Now switch back to your document and choose <code>Edit > Paste</code> from the <code>gedit</code> menu bar.

The above text includes application names; system-wide menu names and items; application-specific menu names; and buttons and text found within a GUI interface, all presented in Proportional Bold and all distinguishable by context.

Note the menu:>[] shorthand used to indicate traversal through a menu and its sub-menus. This is to avoid the difficult-to-follow 'Select from the **Preferences** | ] sub-menu in the menu:System[ menu of the main menu bar' approach.

#### Mono-spaced Bold Italic or Proportional Bold Italic

Whether Mono-spaced Bold or Proportional Bold, the addition of Italics indicates replaceable or variable text. Italics denotes text you do not input literally or displayed text that changes depending on circumstance. For example:

To connect to a remote machine using ssh, type ssh username@domain.name at a shell prompt. If the remote machine is *example.com* and your username on that machine is john, type ssh john@example.com.

The mount -o remount file-system command remounts the named file system. For example, to remount the */home* file system, the command is mount -o remount /home.

To see the version of a currently installed package, use the rpm -q package command. It will return a result as follows: package-version-release.

Note the words in bold italics above — username, domain.name, file-system, package,

version and release. Each word is a placeholder, either for text you enter when issuing a command or for text displayed by the system.

Aside from standard usage for presenting the title of a work, italics denotes the first use of a new and important term. For example:

When the Apache HTTP Server accepts requests, it dispatches child processes or threads to handle them. This group of child processes or threads is known as a *server-pool*. Under Apache HTTP Server 2.0, the responsibility for creating and maintaining these server-pools has been abstracted to a group of modules called *Multi-Processing Modules (MPMs)*. Unlike other modules, only one module from the MPM group can be loaded by the Apache HTTP Server.

## **Pull-quote Conventions**

Two, commonly multi-line, data types are set off visually from the surrounding text.

Output sent to a terminal is set in Mono-spaced Roman and presented thus:

```
books Desktop documentation drafts mss photos stuff svn
books_tests Desktop1 downloads images notes scripts svgs
```

Source-code listings are also set in Mono-spaced Roman but are presented and highlighted as follows:

```
package org.jboss.book.jca.ex1;
import javax.naming.InitialContext;
public class ExClient
{
  public static void main(String args[])
      throws Exception
  {
     InitialContext iniCtx = new InitialContext();
     Object 0
                    ref = iniCtx.lookup("EchoBean");
     EchoHome
                    home = (EchoHome) ref;
                    echo = home.create();
     Echo
     System.out.println("Created Echo");
     System.out.println("Echo.echo('Hello') = " + echo.echo("Hello"));
  }
}
```

## **Notes and Warnings**

Finally, we use three visual styles to draw attention to information that might otherwise be overlooked.

#### Note



A note is a tip or shortcut or alternative approach to the task at hand. Ignoring a note should have no negative consequences, but you might miss out on a trick that makes your life easier.

## *Important*



Important boxes detail things that are easily missed: configuration changes that only apply to the current session, or services that need restarting before an update will apply. Ignoring Important boxes won't cause data loss but may cause irritation and frustration.

# A

## Warning

A Warning should not be ignored. Ignoring warnings will most likely cause data loss.

## Provide feedback to the authors!

If you find a typographical error in this manual, or if you have thought of a way to make this manual better, we would love to hear from you! Please submit a report in the the {this-issue.tracker.ur}, against the product Restcomm GMLC``, or contact the authors.

When submitting a bug report, be sure to mention the manual's identifier: Restcomm GMLC

If you have a suggestion for improving the documentation, try to be as specific as possible when describing it. If you have found an error, please include the section number and some of the surrounding text so we can find it easily.

## **Chapter 1. Introduction**

Restcomm GMLC is an Open Source Java based GMLC Gateway Platform that routes GMLC messages from the signaling network to service applications and the other way around. It enables operators to offer real-time interactions to mobile subscribers and deliver interactive content to their mobile phones.

Restcomm GMLC acts as an intermediary platform linking the service applications to the GSM network in a session oriented communication. The platform is easy-to-install and easy-to-deploy allowing you to have the Gateway set up and configured very quickly.

Restcomm GMLC supports TDM hardware offered by major vendors in the market, namely Intel family boards (Dialogic) and Zaptel/Dahdi (Digium, Sangoma). TeleStax also has in-house SS7 cards also known as RestComm SS7 Cards. RestComm SS7 cards have MTP2/3 support on-board and therefore the processing load on the server hosting the Restcomm GMLC platform will be low when you use these SS7 cards.

Restcomm GMLC is based on the robust and proven Restcomm JAIN SLEE 1.1 Server and Restcomm jSS7 Stack. Restcomm JAIN SLEE Server is a highly scalable event-driven application server with a robust component model and fault tolerant execution environment. It provides a set of connectors to a variety of networks elements: SS7 MAP, TCAP, INAP, ISUP, SMPP, XMPP, SIP, MGCP, HTTP, XDM, XCAP, Diameter and many others. It is fully compliant with JSR 240 (JSLEE 1.1). Restcomm jSS7 is a software based implementation of the SS7 protocol. It provides implementation for Level 2 and above in the SS7 protocol Stack. Restcomm jSS7 Stack User Guide is bundled within and you can refer to the guide for more details on the Stack.

The Restcomm GMLC Gateway makes use of HTTP protocol between the gateway and the third-party applications (or Value Added Service Modules). Restcomm GMLC Gateway receives the GMLC request from the subscriber's handset/device via the GSM Signaling network and then translates these requests to HTTP depending on the rules configured in the Gateway to route to a corresponding Value Added Service (VAS) or third-party application. The HTTP callback mechanism allows the third-party Application to be agnostic to Operating System, Programming Language and Framework.

This guide will assist you in installing Restcomm GMLC . For more details on configuring and using the platform, please refer to the Restcomm GMLC User Guide.

# **Chapter 2. Pre-Requisites**

Restcomm GMLC 's core requirement is Java. The following table details the Hardware, Operating System and Software requirements for a clean installation of Restcomm GMLC .

Table 1. Installation Pre-Requisites

Component	Requirement	Notes
System Requirements	Intel Pentium 1 GHz or faster for simple applications. Hard disk space of at least 20MB. RAM of at least 1.5 GB	Higher the RAM and processing power, better is the throughput
TDM Hardware	For legacy SS7 links, you must have dahdi or dialogic cards installed along with their native libraries.	
Operating System	The platform can be installed on any OS that supports Java and SCTP. But native libraries for SS7 cards are compiled only for Linux at the moment and therefore supported only on Linux Operating System.	The libraries will be compiled for Windows in future releases.
Java	You must have a working Java Runtime Environment (JRE) or Java Development Kit (JDK) installed on your system and it must be version 7 or higher. M3UA uses Java SCTP which is available only from JDK 7 onwards.	
Firewall Access	You must ensure that you have appropriate firewall permissions to allow access to IP:8080. This is required to access the management consoles.	
SCTP libraries	If you intend to use SIGTRAN (M3UA), you must have the lksctp library installed. The Linux Kernel Stream Control Transmission Protocol (lksctp) library provides SCTP implementation.	For more details on downloading and installing lksctp, please refer to http://lksctp.sourceforge.net/



You must ensure that the JAVA\_HOME and JBOSS\_HOME Environment variables are set properly for the user account(s) that will run the server. For more details on setting these variables, please refer to the sections Java Development Kit (): Installing, Configuring and Running and Setting the JBOSS\_HOME Environment Variable.

# Chapter 3. Hardware Setup

For legacy SS7 links, you must have relevant SS7 cards installed along with their native libraries.

Restcomm GMLC supports dahdi based SS7 cards like diguim and sangoma as well as dialogic cards. Since dahdi based SS7 crads do not have MTP2/MTP3 support on board they rely on external software to provide these services. But dialogic based SS7 cards have on board support for MTP2/MTP3.

This guide does not provide installation instructions for SS7 hardware. You must refer to respective vendor documentation for installing and configuring the hardware cards. The following external links point to information that will assist you in setting up the hardware.

• Sangoma: http://wiki.sangoma.com/

• Diguim: http://www.digium.com/en/products/digital/

• Dialogic: http://www.dialogic.com/

# Chapter 4. Downloading and Installing

Installing Restcomm GMLC is easy and quick with the binary download. You can either download the binary release or download the source code and set up from source.

## 4.1. Binary Download and Installation

The binary release is available for download at {this-release-binary-url}

Procedure: Binary Download and Installation

- 1. Download the zip file <filename> to any folder of your choice.
- 2. Extract the contents of the zip file.

```
Downloads]$ unzip <filename>
```

3. Verify the newly created directory and ensure the contents are as explained below.

## 4.2. Directory Structure

When you download the binary release, you will notice that the top level directory is named restcomm-gmlc-<version> and immediately below this are five sub-directories as explained below:

- docs: Contains all relevant documentation in respective subfolders for JSLEE, jSS7, Management-HQ and GMLC.
- jboss-5.1.0.GA: The core server with two profiles "default" and "simulator". The "default" profile is a clean profile where you will have to start from scratch and configure the entire SS7 Stack and GMLC Gateway. The "simulator" profile is a pre-configured profile to work with jss7-simulator. Refer to the Admin Guide for instructions on how to start the server in either of the profiles.
- resources: Contains SLEE MAP, JDBC, http-client, http-servlet and SIP RA jars.
- tools: Contains SLEE tools and jss7-simulator.

```
|- restcomm-gmlc-<version>
        - docs
                |+ jss7
                + slee
                + GMLC
                |+ management-hg
        |- jboss-5.1.0.GA
                |+ bin
                          //contains start up and shutdown scripts for the Server and
the start up script for Shell.
                |+ client
                l+ common
                l+ docs
                |+ lib
                - server
                    |+ default //clean profile to set up from scratch
                                     //pre-configured profile to work with the jss7-
                    |+ simulator
simulator
        |- resources
                |+ http-client
                + map
        |- tools
                |+ eclipslee
                |+ jopr-plugin
                |+ remote-slee-connection
                + snmp
                |+ restcomm-jss7-simulator
                |+ twiddle
```

## 4.3. Setup from Source

Restcomm GMLC is an open source project and you have the freedom to build from source. Building from source means you can stay on top with the latest features. Whilst aspects of Restcomm GMLC are quite complicated, you may find ways to become contributors.

Restcomm GMLC works with JDK1.7 or above. In addition you must have the following tools installed.

- Git Client: Instructions for using GIT, including install, can be found at http://git-scm.com/book
- Maven 3.2.X : Instructions for using Maven, including install, can be found at http://maven.apache.org/
- Ant 1.9.X: Instructions for using Ant, including install, can be found at http://ant.apache.org

## 4.3.1. Release Source Code Building

1. Downloading the source code

Use GIT to checkout a specific release source, the base URL is &THIS.TRUNK\_SOURCE\_CODE\_URL;, then add the specific release version.

```
[usr]$ git clone https://userid@bitbucket.org/telestax/restcomm-gmlc.git
[usr]$ cd restcomm-gmlc
[usr]$ git checkout <version>
```

## 2. Building the source code

Now that we have the source the next step is to build and install the source. Restcomm GMLC uses Maven 2 to build the system. You must ensure that JAVA\_HOME environment variable is set properly prior to building the source.

```
[usr]$ mvn clean install
```

## 4.3.2. Development Trunk Source Building

Similar process as for Release Source Code Building, the only change is don't switch to specific tag.

# **Chapter 5. Post Installation Configuration**

You must perform post-installation configuration of the Gateway according to instructions in the Restcomm GMLC Admin Guide. Before using in Production, you must remember to fine-tune Memory and Database settings for better performance.

Once you have installed Restcomm GMLC to suit your needs, you can go ahead and configure the SS7 Stack and the Gateway to meet your requirements. The Restcomm jSS7 Stack User Guide in the restcomm-gmlc-<version>/docs/jss7/ folder will assist you in configuring and managing the SS7 Stack. Only when you have completely configured the SS7 Stack to meet your requirements, you must go ahead with configuring the GMLC Gateway. The Restcomm GMLC Admin Guide in the restcomm-gmlc-<version>/docs/GMLC/ folder will assist you in configuring and managing the GMLC Gateway. To configure and manage both the Stack and the Gateway you can make use of the Command Line Interface (CLI) tool or the GUI that comes with the platform.



Failure to configure memory, database, logging and other settings as per the instructions in the Admin Guide may result in poor performance of the Gateway.

# **Chapter 6. Uninstalling**

If you wish to remove Restcomm GMLC you can do so by deleting the installation directory.

# Appendix A: Java Development Kit (): Installing, Configuring and Running

The [app] Platform is written in Java; therefore, before running any server, you must have a working Java Runtime Environment () or Java Development Kit () installed on your system. In addition, the JRE or JDK you are using to run [app] must be version 5 or higher [1: At this point in time, it is possible to run most servers, such as the JAIN SLEE, using a Java 6 JRE or JDK. Be aware, however, that presently the XML Document Management Server does not run on Java 6. We suggest checking the web site, forums or discussion pages if you need to inquire about the status of running the XML Document Management Server with Java 6.].

## Should I Install the JRE or JDK?

Although you can run servers using the Java Runtime Environment, we assume that most users are developers interested in developing Java-based, [app]-driven solutions. Therefore, in this guide we take the tact of showing how to install the full Java Development Kit.

## Should I Install the 32-Bit or the 64-Bit JDK, and Does It Matter?

Briefly stated: if you are running on a 64-Bit Linux or Windows platform, you should consider installing and running the 64-bit JDK over the 32-bit one. Here are some heuristics for determining whether you would rather run the 64-bit Java Virtual Machine (JVM) over its 32-bit cousin for your application:

- Wider datapath: the pipe between RAM and CPU is doubled, which improves the performance of memory-bound applications when using a 64-bit JVM.
- 64-bit memory addressing gives virtually unlimited (1 exabyte) heap allocation. However large heaps affect garbage collection.
- Applications that run with more than 1.5 GB of RAM (including free space for garbage collection optimization) should utilize the 64-bit JVM.
- Applications that run on a 32-bit JVM and do not require more than minimal heap sizes will gain nothing from a 64-bit JVM. Barring memory issues, 64-bit hardware with the same relative clock speed and architecture is not likely to run Java applications faster than their 32-bit cousin.

Note that the following instructions detail how to download and install the 32-bit JDK, although the steps are nearly identical for installing the 64-bit version.

#### **Downloading**

You can download the Sun JDK 5.0 (Java 2 Development Kit) from Sun's website: <a href="http://java.sun.com/javase/downloads/index\_jdk5.jsp">http://java.sun.com/javase/downloads/index\_jdk5.jsp</a>. Click on the Download link next to "JDK 5.0 Update <x>`" (where [replaceable]<x>` is the latest minor version release number). On the next page, select your language and platform (both architecture—whether 32- or 64-bit—and operating system), read and agree to the Java Development Kit 5.0 License Agreement, and proceed to the download page.

The Sun website will present two download alternatives to you: one is an RPM inside a self-extracting file (for example,  $jdk-1\_5\_0\_16$ -linux-i586-rpm.bin), and the other is merely a self-extracting file (e.g.  $jdk-1\_5\_0\_16$ -linux-i586.bin). If you are installing the JDK on Red Hat Enterprise

Linux, Fedora, or another RPM-based Linux system, we suggest that you download the self-extracting file containing the RPM package, which will set up and use the SysV service scripts in addition to installing the JDK. We also suggest installing the self-extracting RPM file if you will be running [app]`in a production environment.

#### *Installing*

The following procedures detail how to install the Java Development Kit on both Linux and Windows.

Procedure: Installing the JDK on Linux

1. Regardless of which file you downloaded, you can install it on Linux by simply making sure the file is executable and then running it:

```
~]$ chmod +x "jdk-1_5_0_<minor_version>-linux-<architecture>-rpm.bin"
~]$ ./"jdk-1_5_0_<minor_version>-linux-<architecture>-rpm.bin"
```

You Installed Using the Non-RPM Installer, but Want the SysV Service Scripts



If you download the non-RPM self-extracting file (and installed it), and you are running on an RPM-based system, you can still set up the SysV service scripts by downloading and installing one of the -compat packages from the JPackage project. Remember to download the -compat package which corresponds correctly to the minor release number of the JDK you installed. The compat packages are available

link:ftp://jpackage.hmdc.harvard.edu/JPackage/1.7/generic/RPMS.non-free/.



You do not need to install a **-compat** package in addition to the JDK if you installed the self-extracting RPM file! The **-compat** package merely performs the same SysV service script set up that the RPM version of the JDK installer does.

Procedure: Installing the JDK on Windows

1. Using Explorer, simply double-click the downloaded self-extracting installer and follow the instructions to install the JDK.

## Configuring

Configuring your system for the JDK consists in two tasks: setting the JAVA\_HOME environment variable, and ensuring that the system is using the proper JDK (or JRE) using the alternatives command. Setting JAVA\_HOME usually overrides the values for java, javac and java\_sdk\_1.5.0 in alternatives, but we will set them all just to be safe and consistent.

Setting the JAVA\_HOME Environment Variable on Generic Linux

After installing the JDK, you must ensure that the JAVA\_HOME environment variable exists and points to the location of your JDK installation.

Setting java, javac and java\_sdk\_1.5.0 Using the alternatives command

As the root user, call /usr/sbin/alternatives with the --config java option to select between

JDKs and JREs installed on your system:

Setting the JAVA\_HOME Environment Variable on Windows

For information on how to set environment variables in Windows, refer to http://support.microsoft.com/kb/931715.

#### **Testing**

Finally, to make sure that you are using the correct JDK or Java version (5 or higher), and that the java executable is in your PATH, run the `java -version` command in the terminal from your home directory:

```
~]$ java -version
java version "1.5.0_16"
Java(TM) 2 Runtime Environment, Standard Edition (build 1.5.0_16-b03)
Java HotSpot(TM) Client VM (build 1.5.0_16-b03, mixed mode, sharing)
```

## Uninstalling

There is usually no reason (other than space concerns) to remove a particular JDK from your system, given that you can switch between JDKs and JREs easily using alternatives, and/or by setting JAVA\_HOME.

#### Uninstalling the JDK on Linux

On RPM-based systems, you can uninstall the JDK using the `yum remove <jdk\_rpm\_name> `command.

#### Uninstalling the JDK on Windows

On Windows systems, check the JDK entry in the Start menu for an uninstall command, or use Add/Remove Programs.

# Appendix B: Setting the JBOSS\_HOME Environment Variable

The [app]` Platform` () is built on top of the [app]. You do not need to set the JBOSS\_HOME environment variable to run any of the [app]` Platform` servers *unless* JBOSS\_HOME is *already* set.

The best way to know for sure whether JBOSS\_HOME was set previously or not is to perform a simple check which may save you time and frustration.

Checking to See If JBOSS\_HOME is Set on Unix

At the command line, echo \$JBOSS\_HOME to see if it is currently defined in your environment:

~]\$ echo \$JBOSS HOME

The [app]` Platform` and most &THIS.PLATFORM; servers are built on top of the ([app]). When the [app]` Platform` or &THIS.PLATFORM; servers are built *from source*, then JBOSS\_HOME *must* be set, because the &THIS.PLATFORM; files are installed into (or "over top of" if you prefer) a clean installation, and the build process assumes that the location pointed to by the JBOSS\_HOME environment variable at the time of building is the [app] installation into which you want it to install the &THIS.PLATFORM; files.

This guide does not detail building the [app]` Platform` or any &THIS.PLATFORM; servers from source. It is nevertheless useful to understand the role played by JBoss AS and JBOSS\_HOME in the &THIS.PLATFORM; ecosystem.

The immediately-following section considers whether you need to set <code>JBOSS\_HOME</code> at all and, if so, when. The subsequent sections detail how to set <code>JBOSS\_HOME</code> on Unix and Windows



Even if you fall into the category below of *not needing* to set <code>JBOSS\_HOME</code>, you may want to for various reasons anyway. Also, even if you are instructed that you do *not need* to set <code>JBOSS\_HOME</code>, it is good practice nonetheless to check and make sure that <code>JBOSS\_HOME</code> actually <code>isn't</code> set or defined on your system for some reason. This can save you both time and frustration.

You DO NOT NEED to set JBOSS\_HOME if...

- ...you have installed the [app]` Platform` binary distribution.
- ...you have installed a &THIS.PLATFORM; server binary distribution which bundles [app]``.

You MUST set JBOSS\_HOME if...

- ...you are installing the [app]` Platform` or any of the &THIS.PLATFORM; servers from source.
- ...you are installing the [app]` Platform` binary distribution, or one of the &THIS.PLATFORM; server binary distributions, which *do not* bundle [app]``.

Naturally, if you installed the [app]` Platform` or one of the &THIS.PLATFORM; server binary

releases which *do not* bundle `, yet requires it to run, then you should install before setting [var]`JBOSS\_HOME or proceeding with anything else.

Setting the JBOSS HOME Environment Variable on Unix

The JBOSS\_HOME environment variable must point to the directory which contains all of the files for the [app]` Platform` or individual &THIS.PLATFORM; server that you installed. As another hint, this topmost directory contains a *bin* subdirectory.

Setting JBOSS\_HOME in your personal ~/.bashrc startup script carries the advantage of retaining effect over reboots. Each time you log in, the environment variable is sure to be set for you, as a user. On Unix, it is possible to set JBOSS\_HOME as a system-wide environment variable, by defining it in /etc/bashrc, but this method is neither recommended nor detailed in these instructions.

Procedure: To Set JBOSS\_HOME on Unix...

1. Open the ~/.bashrc startup script, which is a hidden file in your home directory, in a text editor, and insert the following line on its own line while substituting for the actual install location on your system:

```
export JBOSS_HOME="/home/<username>/<path>/<to>/<install_directory>"
```

- 2. Save and close the .bashrc startup script.
- 3. You should source the .bashrc script to force your change to take effect, so that JBOSS\_HOME becomes set for the current session [2: Note that any other terminals which were opened prior to your having altered .bashrc will need to source ~/.bashrc as well should they require access to JBOSS\_HOME.].

```
~]$ source ~/.bashrc
```

4. Finally, ensure that JBOSS\_HOME is set in the current session, and actually points to the correct location:



The command line usage below is based upon a binary installation of the [app]` Platform`. In this sample output, JBOSS\_HOME has been set correctly to the topmost\_directory of the installation. Note that if you are installing one of the standalone [app] servers (with JBoss AS bundled!), then JBOSS\_HOME would point to the topmost\_directory of your server installation.

```
~]$ echo $JBOSS_HOME
/home/silas/<path>/<to>/<install_directory>
```

Setting the JBOSS\_HOME Environment Variable on Windows

The JBOSS\_HOME environment variable must point to the directory which contains all of the files for the &THIS.PLATFORM;Platform or individual &THIS.PLATFORM;server that you installed. As another hint, this topmost directory contains a *bin* subdirectory.

For information on how to set environment http://support.microsoft.com/kb/931715.	variables	in	recent	versions	of	Windows,	refer	to

# **Appendix C: Revision History**