
# Overview of main concepts

# Physical limits: how fast can a serial computer be?

1 Tflop/s, 1 Tbyte sequential machine



- Consider the 1 Tflop/s sequential machine:
  - Data must travel some distance, r, to get from memory to CPU.
  - Go get 1 data element per cycle, this means  $10^{12}$  times per second at the speed of light,  $c = 3x10^8$  m/s. Thus  $r < c/10^{12} = 0.3$  mm.
- Now put 1 Tbyte of storage in a 0.3 mm 0.3 mm areas

in fact 
$$0.3^2 \text{ mm}^2/10^{12} = 9 \cdot 10^{-2} \cdot 10^{-6} \cdot \text{m}^2/10^{12} = 9 \cdot 10^{-20} \cdot \text{m}^2 = (3 \cdot 10^{-10})^2 \cdot \text{m}^2 = 3^2 \cdot \text{A}^2 \rightarrow$$

- Each byte occupies less than 3 square Angstroms, or the size of a small atom! (1 Angstrom =  $10^{-10}$  m = 0.1 nanometer)

### No choice but parallelism !!!

## **Mail**Online




Home | News | U.S. | Sport | TV&Showbiz | Australia | Femail | Health | Science | Money | Video | Travel | Fashion Finder

Latest Headlines | Science | Pictures | Discounts

# IBM stores one bit of data on a SINGLE atom: Breakthrough may lead to credit card-sized devices capable of holding the entire iTunes library of music

- Prototype device uses world's smallest ever magnet using one atom of holmium
- Stores 1,000 times more information in the same space as existing technology
- · Could lead to creation of radically smaller hard drives with vastly greater storage
- Entire 35 million song iTunes library could be saved to a pocket sized drive

By TIM COLLINS FOR MAILONLINE PUBLISHED: 14:35 GMT, 9 March 2017 | UPDATED: 14:35 GMT, 9 March 2017

















Imagine one day being able to carry vast libraries of data, currently stored in rooms full of servers, in your pocket.

That's the dream of a team of IBM scientists who have built what they say is the







Most



'Unnatural structures' on the me evidence of an alien base that N hiding, claim conspiracy...



Raising Ramses: Archaeologists I year-old statue of Egyptian Pharac considered 'one of the most...



Will Apple release a trio of new WEEK? New 10.5-inch and 12.9-Pro models set for...



Beware of 'time travel' texts from 2 Experts warn strange messages c scam



NASA tests radical electric prop system that could take man to N single tank of fuel



Samsung's Galaxy S8 will be a FL consumers wait for the iPhone 8. I

### **Automatic parallelism in modern machines**


- Bit level parallelism: for floating point operations, etc.
- Instruction level parallelism (ILP): execution of multiple instructions per clock cycle
- Memory system parallelism: overlap of memory operations with the computation
- OS parallelism: multiple tasks run in parallel (eg, threads)

#### There are obviously limits to these!

Hence, to achieve high performance, the programmer needs to identify, schedule and coordinate the parallel tasks and data and

**Become a Parallel Computing programmer!** 

## Microprocessor Transistors and Parallelism



### More Exotic Solutions on the Horizon

#### GPUs - Graphics Processing Units (e.g., NVidia)

- Parallel processor attached to main processor
- Originally special purpose, getting more general

#### FPGAs – Field Programmable Gate Arrays

- Inefficient use of chip area
- More efficient than multicore now, maybe not later
- Wire routing heuristics still troublesome

#### Dataflow and tiled processor architectures

- Have considerable experience with dataflow from 1980's
- Are we ready to return to functional programming languages?


#### Cell

- Software controlled memory uses bandwidth efficiently
- Programming model not yet mature

#### Quantum computing

- Use of quantum-mechanical phenomena
- Qubits
- Theoretical or physical computation

## **Memory Hierarchy**




## Processors vs. memory access

```
Clock cycle ~ 120 nanoseconds
  DRAM access time ~ 140 nanoseconds
      > 1:1 ratio ⋈
In 1996
  Clock cycle ~ 4 nanoseconds
   DRAM access time \sim 60 nanoseconds
      >> 20:1 ratio ⊗⊗
In 2002
   Clock cycle ~ 0.6 nanoseconds
   DRAM access time ~ 50 nanoseconds
      > 100::1 ratio ⊗⊗⊗
```

In 1986


From 2003, in fact, first Dual Core processor .....(by Power PC, not Intel!)

## Processor-DRAM Gap (latency)



## What is Parallel Computing?


- Parallel Processes
  - Dived a job in more tasks
  - Assign these task to many processes which work simultaneously
  - Coordinate, control and monitor these processes
- Everyday example
  - Wall construction



## Simplistic definition of Parallel Computing

In the more simple sense, Parallel Computing is the simultaneous use of multiple computation resources to solve a computational problem:

- 1 Use of multiple CPUs
- 2 A problem is broken into discrete parts that can be solved concurrently
- 3 Each part is further broken down into a series of instructions
- 4 The instructions of each part are performed simultaneously on different CPUs





## What is Parallel Computing

- Unfortunately, it is not enough to give a "shovel" (program) to each "worker" (processor)!
- Steps in the parallelization of a job (in first approximation):
  - 1. Decide on the pattern of interconnection between the "processor" and "memory"
  - 2. Identify and implement system software for the hardware
  - 3. Identify data structures and algorithms for our problem
  - 4. Splitting of algorithms and data structures into sub-problems
  - 5. Identify "communications" that will be needed between the sub-problems
  - 6. Assign the sub-problems to "processors" and memory modules.

We will deal with points 3-6!

# Supercomputers, CPUs, Nodes, Processors, Sockets





IBM BG/Q Compute Chip with 18 cores (PU) and 16 L2 Cache units (L2)

## **Scalability**



## The main reasons for Parallel Computing

- Increase the size and complexity of problems that can be solved
  - Bigger problems may not be solvable on sequential computers in a reasonable time
    - Decompose in smaller problems (weak scaling)
  - Big problems may not be contained in a sequential computer's memory
    - Distribute the problem on many computers memories (strong scaling)
- Reduce the time to solve a problem
- Solve bigger problems, more quickly


# **Scalabilty**

#### •Strong scaling:

- The total problem size N stays fixed as more processors P are added.
- Goal is to run the same problem size faster
- Perfect scaling means problem is solved in 1/P time (compared to serial)

#### •Weak scaling:

- The problem size per processor stays fixed as more processors are added.
- Goal is to run larger problem in same amount of time
- Perfect scaling means problem PxN runs in same time as single processor run



#### Hardware factors play a significant role in scalability:

- -Memory-cpu bus bandwidth on an SMP machine
- -Communications network bandwidth
- -Amount of memory available on any given machine or set of machines
- -Processor clock speed

# Why do fast (parallel) machines run slow?

#### Latency

Waiting for access to memory or other parts of the system

#### **Overhead**

Extra work that has to be done to manage program concurrency and parallel resources the real work you want to perform

#### **Starvation**

Not enough work to do due to insufficient parallelism or poor load balancing among distributed resources

#### **Contention**


Delays due to fighting over what task gets to use a shared resource next. Network bandwidth is a major constraint.

## Supercomputers

Check this out www.top500.org

... after checking this ...
http://en.wikipedia.org/wiki/Teraflops\_
Research\_Chip

### Who uses parallel computing?



## What is a Benchmark?

- Comparison of different systems in solving "something hard" as "dense systems of linear equations"
- The comparison involves different computers
- Famous Benchmarks :
  - LINPACK: Linear equation resolver
  - Typical floating-point operations and use of data structures (vector/array)

## **Performance**

- The measurement of the performance of a certain parallel machine makes sense for:
  - The magnitude of the "bigger" problems (ie the size of the problem that "make sense")
  - The performances reflect the largest problem that can be executed on a given machine
- R<sub>max</sub> The performance in Tflops of the largest problem that runs on the machine
- N<sub>max</sub> The size of the largest problem that runs on the machine
- N<sub>1/2</sub> the size where half Rmax is obtained
- R<sub>peak</sub> Theoretical peak performance (in Tflops) of the machine

#### **TOP 7 - November 2020**

Rank	System	Cores	Rmax (TFlop/s)	Rpeak (TFlop/s)	Power (kW)
1	Supercomputer Fugaku - Supercomputer Fugaku, A64FX 48C 2.2GHz, Tofu interconnect D, Fujitsu RIKEN Center for Computational Science Japan	7,630,848	442,010.0	537,212.0	29,899
2	Summit - IBM Power System AC922, IBM POWER9 22C 3.07GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM DOE/SC/Oak Ridge National Laboratory United States	2,414,592	148,600.0	200,794.9	10,096
3	Sierra - IBM Power System AC922, IBM POWER9 22C 3.1GHz, NVIDIA Volta GV100, Dual-rail Mellanox EDR Infiniband, IBM / NVIDIA / Mellanox DOE/NNSA/LLNL United States	1,572,480	94,640.0	125,712.0	7,438
4	Sunway TaihuLight - Sunway MPP, Sunway SW26010 260C 1.45GHz, Sunway, NRCPC National Supercomputing Center in Wuxi China	10,649,600	93,014.6	125,435.9	15,371
5	Selene - NVIDIA DGX A100, AMD EPYC 7742 64C 2.25GHz, NVIDIA A100, Mellanox HDR Infiniband, Nvidia NVIDIA Corporation United States	555,520	63,460.0	79,215.0	2,646
6	<b>Tianhe-2A</b> - TH-IVB-FEP Cluster, Intel Xeon E5-2692v2 12C 2.2GHz, TH Express-2, Matrix-2000, NUDT National Super Computer Center in Guangzhou China	4,981,760	61,444.5	100,678.7	18,482
7	JUWELS Booster Module - Bull Sequana XH2000 , AMD EPYC 7402 24C 2.8GHz, NVIDIA A100, Mellanox HDR InfiniBand/ParTec ParaStation ClusterSuite, Atos	449,280	44,120.0	70,980.0	1,764

#### **Task**

A discrete logic section of computational work. A task is typically a program or "piece" of the program that is executed by a processor

#### **Parallel Task**

A task that can be executed by multiple processors in a "safe" (i.e., provides correct results)

#### **Serial Execution**

Execution of a program sequentially, one instruction at a time. In the simplest sense, this is what happens using a machine with a processor. However, virtually all parallel tasks have sections of a parallel program to be executed in a serial fashion

#### **Parallel Execution**

Execution of a program consists of several tasks with each task that is "able" to carry out the same or different instructions at the same time

#### **Shared Memory**

From a <u>hardware point of view</u>, it describes an architecture where each processor has direct access (usually via bus) to a common physical memory.

From a <u>software point of view</u>, it describes a model where parallel tasks have the same "picture" of memory, and can access and address the same logical memory locations, regardless of where it is located

#### **Distributed Memory**

From a <u>hardware point of view</u>, it refers to a memory access based on network, for a not in common physical memory .

From a <u>software point of view</u>, the task can only " see " from a logical point of view the local memory of the machine, and can use communications to access the memory of other machines where other tasks are running

#### **Communications**

Parallel tasks typically need to exchange data. There are several ways to achieve this, for example through a shared memory bus, or via a network. However, the exchange of data is reported as effective *communication*, regardless of the method used

**Synchronization** 

The coordination of parallel tasks in real-time, often associated with communications. It is often implemented by establishing a sync point in an application where a task can not continue until another task (or more) achieve the same (or logically equivalent) point. Synchronization usually involves the expectation of at least one task, and can therefore cause an increase in the "wall - clock" of parallel applications

#### **Parallel Overhead**

Amount of time taken to coordinate parallel tasks, in contrast to useful work. The determining factors are:

- 1.Task start-up time
- 2. Synchronizations
- 3. Data Communications
- 4. Software overhead imposed by parallel compilers, libraries, tools, operating systems, etc.
- 5. Task termination time

#### **Granularity**

In parallel computing, granularity is a qualitative measure of the relationship between computation and communication.


**Coarse**: relatively large portions of computational work are done between communication


**Fine**: relatively small portions of computational work are done between communication

## Granularity

Computing / Communication Ratio

Fine-grain Parallelism: Coarse-grain Parallelism:





#### **Massive Parallelism**


Refers to hardware that includes a given parallel system consisting of many physical processors. "Many" refers to date in systems with more than 10,000 processors (i.e., GPGPU)

#### **Scalability**

Refers to the ability of parallel systems (hardware and / or software) to allow a **proportional increase** in the speed-up with the increase of processors. Factors that contribute to scalability include:

- Hardware especially the memory bandwidth-cpu bandwidths and network communications
- The used algorithm!
- The parallel overhead
- Characteristics of your specific application and coding

## Overview of parallel architectures




# Classification of Parallel Computers

- Purely functional, by Flynn:
  - SIMD, SIMD, MISD, MIMD


- Structural
  - Memory based
    - Shared memory, distributed memory
  - Based on the interconnection network
    - Bus, crossbar, direct and indirect networks

## Flynn's Classification

 Michael Flynn introduced in 1966 the following taxonomy, where "interesting" parallel computer classes are MIMD (Multiple Instruction stream-Multiple Data Stream) and SIMD (Single Instruction stream-Multiple Data Stream)




## Potentialities of the 4 models



## **SIMD**


- Synchronous operations
  - At each clock step all processors execute the same instruction on different data
- Array processors (Connection machine, MasPAR MP, etc)
- Pipeline vector computer (Cray 1 & 2)
- SIMD machines are suitable for solving data-parallel problems, where the same instruction is applied to distinct partitions:
  - Ex: Matrix sum: A + B = C
  - If A [2][2] and B[2][2] are distributed to 4 processors, in parallel we have:
    - A11 + B11 = C11 A12 + B12 = C12
    - A21 + B21 = C21 A22 + B22 = C22



GPGPU!!!

# MIMD Multiprocessor, Multicomputer

- Each processor operates in asynchronous mode under the program control and on different data
- Shared memory MIMD computers are known as multiprocessor ore tightly coupled machines (ex: all current multi-core computers, etc)
- Network based MIMD computers are known as multicomputer or loosely coupled machines (es: Transputers, CRAY T3E, Beowulf clusters, etc)



# Structural classification based on memory

• In a parallel system, **2 typical memory configurations** are possible:


#### Shared-memory

- A single memory is present, where all processing elements (PE) can access
- 2. Message exchanges between PEs occurs by writes in this memory
- 3. If the number of PEs is high, memory can become a **bottleneck**

#### Distributed memory

- 1. Each PE has its local memory
- Communication occur by means of message exchanges (Message Passing)

## **Generic Parallel Architecture**




Where is memory physically located?

# Shared memory vs Message passing


- In both SIMD and MIMD machines, cooperation is achieved by means of data exchange
- This can occur by:
  - Using Shared memory (SM) and shared variables
  - Using Distributed memory (DM) and message passing
- In the case of SM, we have a single address space, where all processors can access data
  - Problems linked to scalability, partially solved by cache usage
  - Cooperation suitable only for few processors (2-32 MIMD multiprocessors)
- In the case of **DM**, we have a **private addressing to each processor**, so message passing is necessary for communication
  - Typical modality for many MIMD computers and workstation based clusters
  - If necessary, a single address space can be **emulated** by a suitable software (e.g. Virtual Shared Memory)

## **Shared Memory Multiprocessors**

- Load/Store operations access directly all memory locations of the system memory
  - Simple mechanism for communication and sharing
    - Transparent respect to location
    - Same operations available from uni-processors
- Central memory or distributed «near» processors
- Cost of Uniform Memory Access (UMA) or Non Uniform Memory Access (NUMA)



## **Typical Workstation Cluster**



# Structural classification on interconection basis

- Typical interconnection network include:
  - Single Shared bus
  - Multiple bus
  - Crossbar
  - Ring
  - Hypercube
  - tree

## Programming languages adopted in High Performance Computing

### Message Passing Interface (MPI)

 Explicit sharing of variables from one processor to another, so that each process can manage a memory segment of the program

#### OpenMP

Manages the distribution of process and data in SMP machines,
 communications occur by means of shared memory

#### High Performance Fortran

 Creates a single virtual shared memory segment between processors: the programmer chooses how to distribute data in memory

### CUDA/ OpenCL

De-facto programming languages for GPGPU based sytems