11/25/24, 11:15 AM Check Answers

12.3.8 Lab: Create a Guest Network for BYOD

Candidate: Richard Habib ()
Time Spent: 00:27

Score: 0%
Task Summary
Required Actions
× Create a guest access service Show Details
★ Create a guest WLAN Show Details
× Request a guest pass
★ Connect to Guest_BYOD from Gst-Lap

Explanation



Complete this lab as follows:

- 1. Open the Ruckus ZoneDirector.
 - a. In the Google Chrome URL field, enter 192.168.0.6 and press Enter.
 - b. Maximize Google Chrome.
 - c. Log in using the following information:
 - Admin Name: WirelessAdmin (case sensitive).
 - Password: Adminsonly! (case sensitive).
 - d. Select Login.
- 2. Set up Guest Access Services.
 - a. Select the **Configure** tab.
 - b. From the left menu, select **Guest Access**.
 - c. Under Guest Access Service, select Create New.
 - d. In the Name field, use Guest_BYOD.
 - e. For Authentication, make sure **Use guest pass authentication** is selected.
 - f. For Terms of Use, select Show terms of use.
 - g. For Redirection, make sure **Redirect to the URL that the user intends to visit** is selected.
 - h. Expand Restricted Subnet Access.
 - i. Verify that **192.168.0.0/16** is listed.
 - j. Select **OK**.
- 3. Create a guest WLAN.
 - a. From the left menu, select WLANs.
 - b. Under WLANs, select Create New.
 - c. In the Name field, use Guest.

11/25/24, 11:15 AM Check Answers

- d. In the ESSID field, use **Guest_BYOD**.
- e. For Type, select Guest Access.
- f. Confirm the following settings are set:
 - Authentication Options: Open
 - Encryption Options: None
 - Guest Access Service: Guest BYOD
- g. For Wireless Client Isolation, select **Isolate wireless client traffic from other clients on the same AP**.
- h. Select **OK**.
- i. Close the Google Chrome browser.
- 4. Request a guest password.
 - a. Open a new Google Chrome browser window.
 - b. Maximize the window for better viewing.
 - c. In the URL field, enter 192.168.0.6/guestpass and press Enter.
 - d. Log in using the following information:
 - Admin Name: BYODAdmin (case sensitive).
 - Password: @dmin1s (case sensitive).
 - e. Select Log In.
 - f. In the Full Name field, enter any full name.
 - g. In the *Key* field, highlight the *key* and press Ctrl + C to copy the key.
 - h. Select Next.
- 5. Access the wireless Guest Access service from the guest laptop in the lobby.
 - a. From the top left, select **Floor 1**.
 - b. Under Lobby, select **Gst-Lap**.
 - c. In the Notification area, select the *wireless network* icon.
 - d. Select **Guest BYOD**.
 - e. Select **Connect**.
 - f. Select **Yes** to allow the device to be discoverable.
 - g. After checking network requirements, the browser opens to the Guest Access login page.
 - h. In the Guest Pass field, press Ctrl + V to paste the key copied from the Key field.
 - i. Select Log In.