11/28/24, 2:32 PM Check Answers

13.2.8 Lab: Configure a Remote Access VPN

Candidate: Richard Habib ()
Time Spent: 01:13

Score: 0%

Task Summary

Required Actions

- X Create a new certificate authority certificate Show Details
- X Create a new server certificate named CorpNet
- ★ Configure the VPN server Show Details
- X Configure the firewall rules Show Details
- X Set the OpenVPN server to Remote Access (User Auth)
- X Configure the following standard VPN users Show Details

Explanation



While completing this lab, use the following information:

• Create and configure the following standard remote VPN users:

Username	Password	Full Name
blindley	L3tM31nNow	Brian Lindley
jphillips	L3tM31nToo	Jacob Phillips

Complete this lab as follows:

- 1. Sign in to the pfSense management console.
 - a. In the Username field, enter admin.
 - b. In the Password field, enter **P@ssw0rd** (zero).
 - c. Select **SIGN IN** or press **Enter**.
- 2. Start the VPN wizard and select the authentication backend type.
 - a. From the pfSense menu bar, select VPN > OpenVPN.
 - b. From the breadcrumb, select Wizards.
 - c. Under Select an Authentication Backend Type, make sure Local User Access is selected.
 - d. Select Next.
- 3. Create a new certificate authority certificate.

- a. For Descriptive Name, enter CorpNet-CA.
- b. For Country Code, enter GB.
- c. For State, enter Cambridgeshire.
- d. For City, enter Woodwalton.
- e. For Organization, enter CorpNet.
- f. Select Add new CA.
- 4. Create a new server certificate.
 - a. For Descriptive Name, enter CorpNet.
 - b. Verify that all of the previous changes (Country Code, State/Providence, and City) are the same.
 - 3. Use all other default settings.
 - d. Select Create new Certificate.
- 5. Configure the VPN server.
 - a. Under General OpenVPN Server Information:
 - Use the Interface drop-down menu to select WAN.
 - Verify that the Protocol is set to UDP on IPv4 only.
 - For Description, enter CorpNet-VPN.
 - b. Under Tunnel Settings:
 - For Tunnel Network, enter 198.28.20.0/24.
 - For Local Network, enter 198.28.56.18/24.
 - For Concurrent Connections, enter 4.
 - c. Under Client Settings, in DNS Server1, enter 198.28.56.1.
 - d. Select Next.
- 6. Configure the firewall rules.
 - a. Under *Traffic from clients to server*, select **Firewall Rule**.
 - b. Under *Traffic from clients through VPN*, select **OpenVPN rule**.
 - c. Select **Next**.
 - d. Select Finish.
- 7. Set the OpenVPN server just created to **Remote Access (User Auth)**.
 - a. For the WAN interface, select the Edit Server icon (pencil).
 - b. For Server mode, use the drop-down and select **Remote Access (User Auth)**.
 - c. Scroll to the bottom and select **Save**.
- 8. Configure the following Standard VPN users.
 - a. From the pfSense menu bar, select **System > User Manager**.
 - b. Select **Add**.
 - c. Configure the User Properties as follows:
 - Username: *Username*Password: *Password*Full name: *Fullname*
 - d. Scroll to the bottom and select **Save**.
 - e. Repeat steps 8b-8d to create the remaining VPN users.