

Week-2

1. a) Create and attach an EBS volume to an EC2 instance, and
b) scale the instance by increasing CPU and RAM by changing the instance type.
2. Attach and permanently mount an EBS volume to a Linux EC2 instance to ensure data persistence across reboots.
3. Create a snapshot of the attached EBS volume and use it to create and attach a new volume to an EC2 instance in another AWS region.

1. a) Create and attach an EBS volume to an EC2 instance, and
b) scale the instance by increasing CPU and RAM by changing the instance type.

a) Creating and attaching an EBS volume to an EC2 instance

Step 1: Create a New EBS Volume

Open the EC2 Dashboard.

From the left-hand menu, select Volumes under Elastic Block Store (EBS).

Click Create Volume.

Choose:

Volume type (gp3/gp2)

Size of the volume

Availability Zone (must be the same as the EC2 instance)

Click Create Volume.

The screenshot displays the AWS Management Console interface for an EBS volume. The left-hand navigation pane shows the 'Elastic Block Store' section expanded, with 'Volumes' selected. The main content area shows the details for volume 'vol-0caa9fd3076a042e5'. The volume is of type 'gp2', 20 GiB in size, and is in the 'Available' state. It is located in the 'us-east-1a' Availability Zone. The volume was created on 'Fri Jan 23 2026 12:11:01 GMT+0530 (India Standard Time)'. The 'Status check' is 'Okay'. The 'Multi-Attach enabled' option is 'No'. The 'Operator' is 'false'. The 'Encryption' section shows 'Not encrypted'. The 'KMS key ID' is 'None'. The 'KMS key alias' is 'None'. The 'KMS key ARN' is 'None'. The 'Source' section shows 'None'. The 'Outposts ARN' is 'None'. The 'Attached resources' section shows 'None'. The 'Fast snapshot restored' option is 'No'. The 'AWS Compute Optimizer finding' shows a warning: 'This user is not authorized to call AWS Compute Optimizer. | Retry'. The 'Volume state' is 'Available'. The 'IOPS' is '100'. The 'Throughput' is 'None'. The 'Actions' button is visible in the top right corner.

vol-0caa9fd3076a042e5			
Details			
Volume ID vol-0caa9fd3076a042e5	Size 20 GiB	Type gp2	Status check Okay
AWS Compute Optimizer finding This user is not authorized to call AWS Compute Optimizer. Retry	Volume state Available	IOPS 100	Throughput -
Fast snapshot restored No	Availability Zone us-east-1a (us-east-1a)	Created Fri Jan 23 2026 12:11:01 GMT+0530 (India Standard Time)	Multi-Attach enabled No
Attached resources -	Outposts ARN -	Managed false	Operator -
Source			
Snapshot ID -	Source volume ID -		
Encryption			
Encryption Not encrypted	KMS key ID -	KMS key alias -	KMS key ARN -

Volumes (2) Info

Last updated less than a minute ago

Recycle Bin Actions Create volume

Saved filter sets Choose filter set Search

Name	Volume ID	Type	Size	IOPS	Throughput	Snapshot ID	Source volume ID	Created
	vol-015137dea25cbc674	gp3	8 GiB	3000	125	snap-0ff2a61a...	-	2026/
	vol-0caa9fd3076a042e5	gp2	20 GiB	100	-	-	-	2026/

Step 2: Attach the EBS Volume to the Existing EC2 Instance

In the Volumes section, select the newly created volume.

Click Actions → Attach Volume.

Select the target EC2 instance from the list.

Specify the device name (example: /dev/xvdf).

Click Attach.

Basic details

Volume ID
vol-0caa9fd3076a042e5

Availability Zone
use1-az4 (us-east-1a)

Instance Info
i-02724092d6bc14354 (ec2) (running)

Only instances in the same Availability Zone as the selected volume are displayed.

Device name Info
/dev/sdf

Recommended device names for Linux: /dev/sda1 for root volume, /dev/sd[f-p] for data volumes.

ⓘ Newer Linux kernels may rename your devices to /dev/xvdf through /dev/xvdp internally, even when the device name entered here (and shown in the details) is /dev/sdf through /dev/sdp.

Cancel Attach volume

Step 3: Verify the Volume on the EC2 Instance

Connect to the EC2 instance using SSH.

Check the attached disks:

lsblk

Identify the new volume (e.g., /dev/xvdf).

```
aws
Search [Alt+S]
United States (N. Virginia) Account ID: 0558-4918-2216
voclabs/user4599926=viswambharpapalli@gmail...

The list of available updates is more than a week old.
To check for new updates run: sudo apt update

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

ubuntu@ip-172-31-28-104:~$ sudo su
root@ip-172-31-28-104:/home/ubuntu# lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0        7:0      0   27.6M 1 loop /snap/amazon-ssm-agent/11797
loop1        7:1      0    74M 1 loop /snap/core22/2163
loop2        7:2      0   50.9M 1 loop /snap/snapd/25577
nvme0n1      259:0    0     8G 0 disk 
--nvme0n1p1  259:1    0    7G 0 part /
--nvme0n1p4  259:2    0    4M 0 part 
--nvme0n1p5  259:3    0   106M 0 part /boot/efi
--nvme0n1p6  259:4    0   913M 0 part /boot
nvme1n1      259:5    0    20G 0 disk
```

Note: Ensure that the EBS volume and the EC2 instance belong to the **same Availability Zone**, as cross-AZ attachment is not supported.

b) Procedure: increasing/decreasing of CPU and RAM

Step 1. - Navigate to the EC2 dashboard.

Step 2. - Stop the EC2 instance associated with the EBS volume.

Step 3. - Click "Actions" and then—instance settings—change the instance type "Modify Volume".

Step 4. - Increase/ decrease the size or change the volume type to a higher performance specification.

Step 5. - Click "Modify" to apply the changes.

Step 6: Now the start the machine you see with increase /decrease of size and performance

aws
Search [Alt+S]
United States (N. Virginia) Account ID: 0558-4918-2216
voclabs/user4599926=viswambharpapalli@gmail...

EC2 > Volumes > vol-0caa9fd3076a042e5 > Modify volume

Modify volume info

Modify the type, size, and performance of an EBS volume.

Volume details


Volume ID
vol-0caa9fd3076a042e5

Volume type Info
General Purpose SSD (gp2)

Size (GiB) Info
21
Min: 1 GiB, Max: 16384 GiB.

IOPS Info
100/3000
Baseline of 3 IOPS per GiB with a minimum of 100 IOPS, burstable to 3000 IOPS.

Cancel Modify



2. Attach and permanently mount an EBS volume to a Linux EC2 instance to ensure data persistence across reboots.

Step 1: Create an EBS Volume

1. Log in to **AWS Management Console**
2. Go to **EC2 → Volumes**
3. Click **Create Volume**
4. Choose:
 - **Volume Type:** gp3 (recommended)
 - **Size:** (e.g., 20 GB)
 - **Availability Zone:** Same AZ as EC2 instance
5. Click **Create Volume**

Step 2: Attach the EBS Volume to EC2

1. Select the newly created **EBS volume**
2. Click **Actions → Attach Volume**
3. Choose:

- **Instance:** Select your Linux EC2 instance
- **Device name:** /dev/xvdf

4. Click **Attach**

Step 3: Connect to the EC2 Instance

Connect using SSH:

```
ssh -i key.pem ec2-user@<public-ip>
```

Step 4: Verify the Attached Disk

Check all available disks:

lsblk

You will see:

- Root volume: /dev/xvda
- New volume: /dev/xvdf (no partition yet)

Check filesystem:

lsblk -fs

```
To check for new updates run: sudo apt update

Last login: Fri Jan 23 06:49:39 2026 from 18.206.107.28
ubuntu@ip-172-31-28-104:~$ sudo su
root@ip-172-31-28-104:/home/ubuntu# lsblk -fs
NAME        FSTYPE     FSVER LABEL          UUID                                FSAVAIL FSUSE% MOUNTPOINTS
loop0       squashfs   4.0                                     0      100% /snap/amazon-ssm-agent/11797
loop1       squashfs   4.0                                     0      100% /snap/snapd/25577
loop2       squashfs   4.0                                     0      100% /snap/core22/2163
nvme0n1
nvme0n1p1   ext4       1.0    cloudimg-rootfs f6fbc198-289f-487b-9a4c-c22e821c6c98 4.9G    27% /
└─nvme0n1
nvme0n1p14
└─nvme0n1
nvme0n1p15  vfat       FAT32  UEFI            872E-BD64                        98.2M    6% /boot/efi
└─nvme0n1
nvme0n1p16  ext4       1.0    BOOT            d066b928-2f3b-4fe5-9761-6d12299a7d53 729.8M   10% /boot
└─nvme0n1
root@ip-172-31-28-104:/home/ubuntu#
```

Step 5: Create a Partition

Create a partition on the new volume:

`fdisk /dev/xvdf`

```
root@ip-172-31-28-104:/home/ubuntu# fdisk /dev/nvme1n1

Welcome to fdisk (util-linux 2.39.3).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table.
Created a new DOS (MBR) disklabel with disk identifier 0xbc8e34fa.


Command (m for help): m

Help:

DOS (MBR)
a toggle a bootable flag
b edit nested BSD disklabel
c toggle the dos compatibility flag
```

Inside fdisk:

- Press m → Help menu
- Press n → New partition
- Press p → Primary partition
- Press Enter → Default partition number
- Press Enter → Default first sector
- Press Enter → Default last sector (use full disk)
- Press w → Write changes and exit



```
Account ID: 0558-4918-2216
voclabs/user4599926=viswambharparepalli@gmail...

w write table to disk and exit
q quit without saving changes

Create a new label
g create a new empty GPT partition table
G create a new empty SGI (IRIX) partition table
o create a new empty MBR (DOS) partition table
s create a new empty Sun partition table

Command (m for help): n
Partition type
  p primary (0 primary, 0 extended, 4 free)
  e extended (container for logical partitions)
Select (default p): p
Partition number (1-4, default 1): 1
First sector (2048-44040191, default 2048): 2048
Last sector, +/-sectors or +/-size[K,M,G,T,P] (2048-44040191, default 44040191): 44040191

Created a new partition 1 of type 'Linux' and of size 21 GiB.

Command (m for help): w
The partition table has been altered.
Calling ioctl() to re-read partition table.
Syncing disks.

root@ip-172-31-28-104:/home/ubuntu#
```

Notify kernel:

partprobe

Step 6: Verify the New Partition

lsblk -fs

You should now see:

/dev/xvdf1

```
root@ip-172-31-28-104:/home/ubuntu# lsblk
NAME                MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0                 7:0      0  27.6M  1 loop /snap/amazon-ssm-agent/11797
loop1                 7:1      0  50.9M  1 loop /snap/snapd/25577
loop2                 7:2      0   74M   1 loop /snap/core22/2163
nvme1n1              259:0     0    21G  0 disk
└─nvme1n1p1          259:7     0    21G  0 part
nvme0n1              259:1     0     8G  0 disk
├─nvme0n1p1          259:2     0     7G  0 part /
├─nvme0n1p14          259:3     0     4M  0 part
├─nvme0n1p15          259:4     0   106M  0 part /boot/efi
└─nvme0n1p16          259:5     0   913M  0 part /boot
root@ip-172-31-28-104:/home/ubuntu#
```

Step 7: Format the Partition

Format with XFS filesystem:

mkfs.xfs /dev/xvdf1

```
root@ip-172-31-28-104:/home/ubuntu# mkfs.xfs /dev/nvme1n1p1
meta-data=/dev/nvme1n1p1    isize=512    agcount=16, agsize=344048 blks
               =                        sectsz=512    attr=2, projid32bit=1
               =                        crc=1        finobt=1, sparse=1, rmapbt=1
               =                        reflink=1     bigtime=1 inobtcount=1 nrext64=0
data        =                        bsize=4096    blocks=5504768, imaxpct=25
               =                        sunit=1      swidth=1 blks
naming      =version 2          bsize=4096    ascii-ci=0, ftype=1
log         =internal log      bsize=4096    blocks=16384, version=2
               =                        sectsz=512    sunit=1 blks, lazy-count=1
realtime    =none                extsz=4096    blocks=0, rtextents=0
root@ip-172-31-28-104:/home/ubuntu#
```

Verify:

lsblk -fs

```
aws [Alt+S] United States (N. Virginia) Account ID: 0558-4918-2216 voclabs/user4599926=viswambharparepalli@gmail....

root@ip-172-31-28-104:/home/ubuntu# mkfs.xfs /dev/nvme1n1p1
meta-data=/dev/nvme1n1p1 isize=512    agcount=16, agsize=344048 blks
           =               sectsz=512   attr=2, projid32bit=1
           =               crc=1        finobt=1, sparse=1, imapbt=1
data      =               reflink=1    bigtime=1 inobtcount=1 nrext64=0
           =               bsize=4096   blocks=5504768, imaxpct=25
           =               sunit=1      swidth=1 blks
naming    =version 2              bsize=4096   ascii-ci=0, ftype=1
log       =internal log          bsize=4096   blocks=16384, version=2
           =               sectsz=512   sunit=1 blks, lazy-count=1
realtime  =none                  extsz=4096   blocks=0, rtextents=0

root@ip-172-31-28-104:/home/ubuntu# lsblk -fs
NAME        FSTYPE FSVER LABEL        UUID                                FSAVAIL FSUSE% MOUNTPOINTS
loop0       squashfs 4.0                                0      100% /snap/amazon-ssm-agent/11797
loop1       squashfs 4.0                                0      100% /snap/snapd/25577
loop2       squashfs 4.0                                0      100% /snap/snapd/2163
nvme0n1p1   ext4      1.0  cloudimg-rootfs f6fbc198-289f-487b-9a4c-c22e821c6c98 4.9G    27% /
└─nvme0n1
   nvme0n1p14
   └─nvme0n1
      nvme0n1p15 vfat     FAT32  UEFI            872E-BD64                98.2M    6% /boot/efi
      └─nvme0n1
         nvme0n1p16 ext4      1.0  BOOT            d066b928-2f3b-4fe5-9761-6d12299a7d53 729.8M   10% /boot
         └─nvme0n1
            nvme1n1p1 xfs       cfdc8826-3bde-464c-a19c-4db434e334a8

root@ip-172-31-28-104:/home/ubuntu#
```

Step 8: Create a Mount Directory

```
mkdir /mnt/archana
```

Step 9: Mount the Volume

```
mount /dev/xvdf1 /mnt/archana
```

Verify:

```
df -h
```

```
aws [Alt+S] United States (N. Virginia) Account ID: 0558-4918-2216 voclabs/user4599926=viswambharparepalli@gmail....

loop0       squashfs 4.0                                0      100% /snap/amazon-ssm-agent/11797
loop1       squashfs 4.0                                0      100% /snap/snapd/25577
loop2       squashfs 4.0                                0      100% /snap/snapd/2163
nvme0n1p1   ext4      1.0  cloudimg-rootfs f6fbc198-289f-487b-9a4c-c22e821c6c98 4.9G    27% /
└─nvme0n1
   nvme0n1p14
   └─nvme0n1
      nvme0n1p15 vfat     FAT32  UEFI            872E-BD64                98.2M    6% /boot/efi
      └─nvme0n1
         nvme0n1p16 ext4      1.0  BOOT            d066b928-2f3b-4fe5-9761-6d12299a7d53 729.8M   10% /boot
         └─nvme0n1
            nvme1n1p1 xfs       cfdc8826-3bde-464c-a19c-4db434e334a8
            └─nvme1n1

root@ip-172-31-28-104:/home/ubuntu# mkdir /mnt/vish
root@ip-172-31-28-104:/home/ubuntu# mount /dev/nvme1n1p1 /mnt/vish
root@ip-172-31-28-104:/home/ubuntu# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/root        6.8G  1.8G  4.9G   27% /
tmpfs           458M    0  458M    0% /dev/shm
tmpfs          183M  892K  182M    1% /run
tmpfs           5.0M    0   5.0M    0% /run/lock
efivarfs        128K  4.1K  119K    4% /sys/firmware/efi/efivars
/dev/nvme0n1p16 881M   89M  730M   11% /boot
/dev/nvme0n1p15 105M   6.2M   99M    6% /boot/efi
tmpfs           92M   12K   92M    1% /run/user/1000
/dev/nvme1n1p1  21G  444M   21G    3% /mnt/vish

root@ip-172-31-28-104:/home/ubuntu#
```

Step 10: Make the Mount Persistent

Get the UUID of the volume:

```
blkid /dev/xvdf1
```


```
cloudimg-rootfs 92M 12K 92M 1% /run/user/1000
/dev/nvme1n1p1 21G 444M 21G 3% /mnt/vish
root@ip-172-31-28-104:/home/ubuntu# blkid /dev/nvme1n1p1
/dev/nvme1n1p1: UUID="cfd8826-3bde-464c-a19c-4db434e334a8" BLOCK_SIZE="512" TYPE="xfs" PARTUUID="bc8e34fa-01"
root@ip-172-31-28-104:/home/ubuntu#
```

Edit fstab:

```
nano /etc/fstab
```

Add this line at the end:

```
UUID=<UUID-value> /mnt/archana xfs defaults,nofail 0 0
```

The screenshot shows the AWS Management Console interface at the top, with the account ID 0558-4918-2216 and the user voelabs/user4599926-vishwambharparepalli@gmail.com. Below the console, a terminal window displays the GNU nano 7.2 editor editing the file /etc/fstab. The content of the file is as follows:

```
cloudimg-rootfs / ext4 discard,commit=30,errors=remount-ro 0 1
LABEL=BOOT /boot ext4 defaults 0 2
LABEL=UEFI /boot/efi vfat umask=0077 0 1
UUID=cfd8826-3bde-464c-a19c-4db434e334a8 /mnt/vish xfs defaults,nofail 0 0
```

The nano editor's status bar at the bottom shows various keyboard shortcuts for editing, such as Ctrl+H for Help, Ctrl+W for Write Out, and Ctrl+O for Open.

Save and exit.

Test fstab:

```
mount -a
```

```
root@ip-172-31-28-104:/home/ubuntu# mount -a
root@ip-172-31-28-104:/home/ubuntu#
```

Step 11: Verify Persistence

1. Reboot the instance:

```
reboot
```

2. Reconnect and check:

```
df -h
```

```
aws
Search [Alt+S]
United States (N. Virginia) Account ID: 0558-4918-2216
vociabs/user4599926-viswambharpapalli@gmail...

Expanded Security Maintenance for Applications is not enabled.
0 updates can be applied immediately.
Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

The list of available updates is more than a week old.
To check for new updates run: sudo apt update

Last login: Fri Jan 23 06:58:18 2026 from 18.206.107.29
ubuntu@ip-172-31-28-104:~$ sudo su
root@ip-172-31-28-104:/home/ubuntu#
root@ip-172-31-28-104:/home/ubuntu# df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/root        6.8G  1.9G  4.9G  27% /
tmpfs            458M    0  458M   0% /dev/shm
tmpfs           183M  912K  182M   1% /run
tmpfs            5.0M    0   5.0M   0% /run/lock
efivarfs         128K  4.1K  119K   4% /sys/firmware/efi/efivars
/dev/nvme0n1p6   881M   89M   730M  11% /boot
/dev/nvme0n1p5  105M   6.2M   99M    6% /boot/efi
/dev/nvme1n1p1   21G  444M   21G    3% /mnt/vish
tmpfs            92M   12K   92M    1% /run/user/1000
root@ip-172-31-28-104:/home/ubuntu#
```

→ Volume should be mounted automatically.

Step 12: Detach and Reattach Volume (Data Recovery Scenario)

Detach:

1. EC2 → Volumes → Select volume
2. Actions → Detach volume

Attach to another EC2 instance:

1. Attach to new instance (same AZ)
2. Login to new instance
3. Create mount directory:

```
mkdir /mnt/archana
```

4. Mount the volume:

```
mount /dev/xvdf1 /mnt/archana
```

All previous data will be available

```
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/copyright.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

To run a command as administrator (user "root"), use "sudo <command>".
See "man sudo_root" for details.

ubuntu@ip-172-31-27-105:~$ sudo su
root@ip-172-31-27-105:/home/ubuntu# mkdir /cmt/ish
mkdir: cannot create directory '/cmt/ish': No such file or directory
root@ip-172-31-27-105:/home/ubuntu# mkdir /mnt/vish
root@ip-172-31-27-105:/home/ubuntu# mount /dev/nvme1n1p1 /mnt/vish
root@ip-172-31-27-105:/home/ubuntu# lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0        7:0      0   27.6M  1 loop /snap/amazon-ssm-agent/11797
loop1        7:1      0    94M  1 loop /snap/core22/2163
loop2        7:2      0   50.9M  1 loop /snap/snapd/25577
nvme0n1      259:0    0     8G  0 disk 
├─nvme0n1p1  259:1    0     7G  0 part /
├─nvme0n1p4  259:2    0     4M  0 part 
├─nvme0n1p5  259:3    0   106M  0 part /boot/efi
├─nvme0n1p6  259:4    0   913M  0 part /boot
└─nvme1n1    259:5    0    21G  0 disk 
   nvme1n1p1 259:6    0    21G  0 part /mnt/vish
root@ip-172-31-27-105:/home/ubuntu#
```

Summary Flow

Create Volume → Attach → lsblk → fdisk → mkfs → mkdir → mount → fstab → reboot

3. Create a snapshot of the attached EBS volume and use it to create and attach a new volume to an EC2 instance in another AWS region.

Attaching Volumes across regions of EC2 using the snapshot

To create a snapshot of an EBS volume and attach it to an instance in another region in AWS, you'll need to follow these steps:

Step 1. Create a Snapshot:

- Sign in to the AWS Management Console.
- Navigate to the EC2 Dashboard.
- Click on "Volumes" in the left-hand navigation pane.
- Select the EBS volume you want to create a snapshot of.
- Click on the "Actions" dropdown menu above the volume list and select "Create Snapshot."
- Provide a name and description for the snapshot.
- Click on the "Create Snapshot" button to initiate the snapshot creation process.

aws Search [Alt+S] United States (N. Virginia) Account ID: 0558-4918-2216 voclabs/user4599926=viswambharpaparelli@gmail...

EC2 > Volumes > vol-0ba5eb8ee6e94a9ee > Create snapshot

Create a point-in-time snapshot to back up the data on an Amazon EBS volume to Amazon S3.

Source volume

Volume ID
vol-0ba5eb8ee6e94a9ee

Availability Zone
use1-az4 (us-east-1a)

Snapshot details

Description
Add a description for your snapshot
20gb volume attach
255 characters maximum.

Encryption [Info](#)
Not encrypted

Tags [Info](#)
A tag is a label that you assign to an AWS resource. Each tag consists of a key and an optional value. You can use tags to search and filter your resources or track your AWS costs.
No tags associated with the resource.
[Add tag](#)

Step 2. Copy the Snapshot to Another Region:

- Once the snapshot is created, go to the "Snapshots" section in the EC2 Dashboard.
- Select the snapshot you just created.
- Click on the "Actions" dropdown menu above the snapshot list and select "Copy Snapshot."
- Choose the destination region where you want to copy the snapshot.
- Click on the "Copy Snapshot" button to initiate the copy process. This may take some time depending on the size of the snapshot and the network speed.

aws Search [Alt+S] United States (N. Virginia) Account ID: 0558-4918-2216 voclabs/user4599926=viswambharpaparelli@gmail...

EC2 > Snapshots

Snapshots (1/2) [Info](#) Last updated less than a minute ago [Recycle Bin](#) [Actions](#) [Create snapshot](#)

Owned by me	Name	Snapshot ID	Full snapshot size	Volume size	Description
☐		snap-0882e7073f2a0fd36	8 GiB	8 GiB	my snap
☒		snap-032d63c51e62279bf	0 B	20 GiB	20gb volume

Snapshot ID: snap-032d63c51e62279bf

Details

Snapshot ID
snap-032d63c51e62279bf

Owner
055849182216

Description
20gb volume attach

Full snapshot size
0 B


Started
Sat Jan 24 2026 10:30:47 GMT+0530 (India Standard Time)

Progress
100%

Product codes
-

Snapshot status
Completed

Fast snapshot restore
-




Step 3. Monitor the Snapshot Copy Progress:

- You can monitor the progress of the snapshot copy by navigating to the "Snapshots" section in the EC2 Dashboard of the source region.
- Look for the snapshot you copied and check its status. It will change from "pending" to "completed" once the copy process is finished.

Step 4. Switch to the Destination Region:

- Use the region selector in the top-right corner of the AWS Management Console to switch to the destination region where you copied the snapshot.



Step 5. Create a Volume from the Snapshot:

- In the EC2 Dashboard of the destination region, go to the "Snapshots" section.
- Find the snapshot you copied from the source region.
- Click on the snapshot, then click on the "Actions" dropdown menu and select "Create Volume."
- Configure the volume settings, such as volume type, size, and availability zone.
- Click on the "Create Volume" button to create the volume from the snapshot.

The screenshot displays the AWS Management Console interface. At the top, the navigation bar shows the AWS logo, a search bar, and account information. The left sidebar contains the 'EC2' menu with options like Dashboard, Global View, Events, Instances, Instance Types, Launch Templates, Spot Requests, Savings Plans, Reserved Instances, Dedicated Hosts, Capacity Reservations, and Capacity Manager. The main content area shows the 'Snapshots' page for the 'snap-032d63c51e62279bf' snapshot. The 'Actions' dropdown menu is open, showing options like 'Create volume from snapshot', 'Copy snapshot', 'Launch copy duration calculator', 'Delete snapshot', 'Manage tags', 'Snapshot settings', and 'Archiving'. The 'Create volume from snapshot' option is highlighted. Below the snapshot list, the details for 'snap-032d63c51e62279bf' are shown, including its size (0 B), progress (100%), and status (Completed). The 'Create volume' page is also visible, showing options for encryption, tags, and a summary.

Step 6. Create the ec2 instance & Attach the Volume to an Instance:

- Once the volume is created, navigate to the "Volumes" section in the EC2 Dashboard.
- Find the newly created volume and select it.
- Click on the "Actions" dropdown menu and select "Attach Volume."
- the EC2 instance to which you want to attach the volume and specify the device name.
- Click on the "Attach" button to attach the volume to the instance.

Attach volume Info

Attach a volume to an instance to use it as you would a regular physical hard disk drive.

Basic details

Volume ID
vol-0ba5eb8ee6e94a9ee

Availability Zone
use1-az4 (us-east-1a)

Instance Info
Search Instance ID or name tag
i-086f80360a7f290b1 (eb3) (running)

[Cancel](#) [Attach volume](#)

Elastic Block Store

- Volumes
- Snapshots
- Lifecycle Manager

Network & Security

- Security Groups
- Elastic IPs
- Placement Groups
- Key Pairs
- Network Interfaces

Load Balancing

- Load Balancers
- Target Groups
- Trust Stores

Auto Scaling

- Auto Scaling Groups

[Settings](#)

Successfully attached volume vol-0ba5eb8ee6e94a9ee to instance i-086f80360a7f290b1. Last updated less than a minute ago. [Recycle Bin](#) [Actions](#) [Create volume](#)

Volumes (2) Info

Saved filter sets Choose filter set Search

☐	Name	Volume ID	Type	Size	IOPS	Throughput	Snapshot ID	Source volume ID	Created
☐		vol-0f00534825f03ec30	gp3	8 GiB	3000	125	snap-0ff2a61a...	-	2026/
☐		vol-0ba5eb8ee6e94a9ee	gp3	20 GiB	3000	125	-	-	2026/

Fault tolerance for all volumes in this Region

Snapshot summary
Recently backed up volumes / Total # volumes
1 / 2

Last updated on Sat, Jan 24, 2026, 10:44:00 AM (GMT+05:30)

Data Lifecycle Manager default policy for EBS Snapshots status
Failed to fetch default policy status

We have created a snapshot of an EBS volume, copied it to another region, created a volume from the snapshot, and attached it to an instance in the destination region.

VIVA QUESTIONS

1. Your database server crashed. Data must be recovered fast. What do you do?
Restore from the latest EBS snapshot or AMI, attach the recovered volume to a new EC2, and bring the service up. Speed comes from having automated backups.

2. EC2 is deleted accidentally — how do you recover data?
Launch a new EC2 and attach EBS volumes restored from snapshots. If no snapshots exist, data is gone.

3. Root volume deleted with EC2. How do you prevent this next time?

Disable “Delete on Termination” for the root EBS volume and enable regular snapshots.

4. Disk is full in production EC2. What will you do?

Extend the EBS volume, grow the filesystem, then clean logs/temp files. Long term: add monitoring and alerts.

5. You want to migrate EC2 to another AWS region

Create an AMI or EBS snapshot, copy it to the target region, then launch a new EC2 there.

6. What happens to EBS when EC2 is stopped?

Nothing — EBS stays intact and keeps all data. Only compute stops.

7. What happens to EBS when EC2 is terminated?

Root volume is deleted by default. Extra attached volumes stay unless explicitly set to delete.

8. Application requires 20,000 IOPS. Which volume will you choose?

Provisioned IOPS SSD (io2 or io1). gp3 may work, but io2 is safer for sustained high IOPS.

9. Can one EBS volume attach to multiple EC2s?

Normally no. Only special “Multi-Attach” volumes support this, and only for specific workloads.

10. You deleted an EBS volume by mistake. How can you get it back?

Restore from snapshot. No snapshot = permanent loss.

11. What happens if a snapshot used by a volume is deleted?

AWS protects dependencies — you can’t delete a snapshot that’s actively in use by a volume.

12. Where are EBS snapshots stored?

In AWS S3 (managed internally by AWS). They’re regional and highly durable.