
Table of Contents

UserStory_01	User Authentication (Sign In & Sign Out)
UserStory_02	Navigation & Global Header
UserStory_03	Product Catalogue Browsing
UserStory_04	Product Filtering by Vendor and Category
UserStory_05	Product Sorting
UserStory_06	Favourites (Wishlist)
UserStory_07	Shopping Cart Management
UserStory_08	Checkout – Shipping Information
UserStory_09	Order Confirmation
UserStory_10	Location-Based Product Offers

UserStory_01 · User Authentication (Sign In & Sign Out)

Card

As a **registered user**, I want to sign in to the BrowserStack Demo Store using my credentials and sign out when done so that I can access protected features such as checkout and favourites securely.

Conversation

- The Sign In page is accessible via the 'Sign In' button located in the top-right navigation header.
- Username field behaviour:
 - Rendered as a React Select dropdown; the user must click the field and select a username from the available list.
 - Valid demo usernames include: demouser, image_not_loading_user, existing_orders_user, fav_user, locked_user.
 - The field is mandatory; the form cannot be submitted without a selection.
- Password field behaviour:
 - Rendered as a React Select dropdown; the user selects a password from the list.
 - The default valid password for all users is: testingisfun99.
 - The field is mandatory; the form cannot be submitted without a selection.
- Login button (id: login-btn) triggers authentication when clicked.
- Successful login behaviour:
 - The system redirects the user to the product listing page.
 - The navigation header replaces the 'Sign In' button with the authenticated username and a 'Logout' button.
- Failed login – Invalid Password scenario:
 - An inline error message 'Invalid Password' is displayed on the Sign In page.
 - The user remains on the Sign In page; no redirect occurs.
- Locked user scenario:
 - If the user 'locked_user' attempts to log in with the correct password, the system displays a 'Your account has been locked.' error message.
 - Access to the application is denied for locked accounts.
- Sign Out behaviour:
 - The 'Logout' button (id: logout) is visible in the header only when a user is authenticated.
 - Clicking 'Logout' ends the session, clears authentication state, and displays the 'Sign In' button in the header.
 - After logout, protected pages (checkout, favourites) redirect the user back to Sign In.
- Accessing the Sign In page while already authenticated should redirect to the product listing page.
- Both Username and Password dropdowns must be completed before the Login button is enabled for submission.

Confirmation (Acceptance Criteria)

AC1 — Successful Login with Valid Credentials

Given the user is on the Sign In page
When the user selects 'demouser' from the Username dropdown
And the user selects 'testingisfun99' from the Password dropdown
And the user clicks the Login button
Then the system redirects the user to the product listing page
And the header displays the username 'demouser' and a 'Logout' button

AC2 — Login Failure with Invalid Password

Given the user is on the Sign In page
When the user selects 'demouser' from the Username dropdown
And the user selects an invalid password from the Password dropdown
And the user clicks the Login button
Then an inline error message 'Invalid Password' is displayed
And the user remains on the Sign In page

AC3 — Locked User Cannot Authenticate

Given the user is on the Sign In page
When the user selects 'locked_user' from the Username dropdown
And the user selects 'testingisfun99' from the Password dropdown
And the user clicks the Login button
Then the system displays an error message indicating the account is locked
And the user is not redirected to the product listing page

AC4 — Form Submission Blocked Without Both Fields

Given the user is on the Sign In page
When the user has not selected a value in the Username dropdown
And the user clicks the Login button
Then no authentication attempt is made
And the Login button does not navigate away from the Sign In page

AC5 — Successful Logout

Given the user is authenticated and on the product listing page
When the user clicks the 'Logout' button in the navigation header
Then the session is terminated
And the header displays the 'Sign In' button instead of the username
And navigating to the checkout page redirects the user to the Sign In page

AC6 — Authenticated User Cannot Access Sign In Page

Given the user is already authenticated

When the user navigates directly to the Sign In URL

Then the system redirects the user to the product listing page

UserStory_02 · Navigation & Global Header

Card

As a **site visitor**, I want to use the global navigation header to access key areas of the store so that I can navigate efficiently between the product catalogue, cart, and authentication at all times.

Conversation

- The header is persistent across all pages of the application.
- The header contains the following elements:
 - Store logo / brand name on the left — clicking it navigates to the product listing page.
 - 'Sign In' link (id: signin) — displayed only when no user is authenticated.
 - Authenticated username label and 'Logout' button (id: logout) — displayed only when a user is logged in.
 - Shopping cart icon with an item count badge — reflects the current number of items in the cart.
- Cart icon behaviour:
 - The count badge is updated in real time when items are added or removed.
 - Clicking the cart icon opens the cart side-drawer / panel.
 - When the cart is empty, the badge is either hidden or displays zero.
- The header renders correctly on all supported viewport sizes.
- The header does not obscure content on page scroll.
- No duplicate navigation elements should be present in the same header state.

Confirmation (Acceptance Criteria)

AC1 — Logo Navigates to Product Listing

Given the user is on any page of the application
When the user clicks the store logo in the header
Then the user is navigated to the product listing page

AC2 — Sign In Link Visible for Unauthenticated Users

Given no user is authenticated
When the user views the header
Then the 'Sign In' link is visible
And the username and 'Logout' button are not displayed

AC3 — Authenticated State Reflected in Header

Given the user has successfully logged in
When the user views the header

Then the authenticated username is displayed in the header
And the 'Logout' button is displayed
And the 'Sign In' link is not visible

AC4 — Cart Badge Updates on Item Addition

Given the user is on the product listing page
When the user adds a product to the cart
Then the cart icon badge in the header increments by one

AC5 — Cart Icon Opens Cart Panel

Given the user is on any page
When the user clicks the shopping cart icon in the header
Then the cart side-drawer opens
And the contents of the cart are displayed

UserStory_03 · Product Catalogue Browsing

Card

As a **site visitor**, I want to browse the full list of available smartphone products on the home page so that I can discover products and decide which ones I want to add to my cart.

Conversation

- The product listing page is the default landing page at the root URL.
- Each product card displays:
 - Product image.
 - Product name.
 - Price (formatted as a currency value).
 - 'Add to Cart' button.
 - Favourite (heart) icon for wishlisting.
- Products are displayed in a responsive grid layout.
- The system loads all products on initial page load with no pagination; all available products are visible.
- Image loading behaviour:
 - For the user 'image_not_loading_user', product images intentionally fail to load (broken image state).
 - For all other users, product images load correctly.
- Products span multiple vendors including Apple, Samsung, Google, OnePlus, and others.
- The 'Add to Cart' button is available on each product card without requiring the user to navigate to a product detail page.
- The user does not need to be authenticated to browse products.

Confirmation (Acceptance Criteria)

AC1 — Product Listing Displayed on Home Page

Given the user navigates to the root URL

When the page loads

Then a grid of product cards is displayed

And each card shows a product image, name, price, and an 'Add to Cart' button

AC2 — Unauthenticated User Can Browse Products

Given no user is authenticated

When the user navigates to the home page

Then all product cards are visible

And the user can browse without being redirected to Sign In

AC3 — Product Images Load for Standard Users

Given the user is authenticated as 'demouser'
When the product listing page loads
Then all product images are rendered successfully

AC4 — Broken Images for Specific Demo User

Given the user is authenticated as 'image_not_loading_user'
When the product listing page loads
Then product images do not load
And broken image placeholders are shown in place of product images

AC5 — Each Product Card Contains Required Elements

Given the product listing page has loaded
When the user inspects any product card
Then the card displays the product name, price, and an Add to Cart button
And a favourite icon is present on each card

UserStory_04 · Product Filtering by Vendor and Category

Card

As a **shopper**, I want to filter products by brand (vendor) and device category from the sidebar so that I can narrow down the product catalogue to find items that match my preferences quickly.

Conversation

- A filter sidebar is present on the left side of the product listing page.
- Two filter groups are available:
 - Brand / Vendor filter — includes options such as Apple, Samsung, Google, OnePlus, HTC, Nokia, and others.
 - Category / Handset filter — includes options such as iPhone, Galaxy, Pixel, Oneplus, and others.
- Each filter option is represented as a checkbox.
- Multiple filters can be selected simultaneously within the same filter group and across groups.
- Filter application behaviour:
 - Filters are applied immediately upon checkbox selection — no 'Apply' button is required.
 - The product grid updates in real time to show only products matching the selected criteria.
 - Multiple filter selections within the same group act as an OR condition (show products matching any selected option).
- Clearing filters:
 - Unchecking all filter checkboxes restores the full product listing.
 - Filters persist while navigating within the current session but reset on page reload.
- If no products match the selected filter combination, the product grid displays no products (empty state).
- Filter state is reflected immediately in the product grid without a page reload.
- Filter is independent of sort order — applied filters and sort order can coexist.

Confirmation (Acceptance Criteria)

AC1 — Vendor Filter Reduces Product Grid

Given the user is on the product listing page with all products visible
When the user selects the 'Apple' vendor filter checkbox
Then only Apple products are displayed in the product grid
And non-Apple products are hidden

AC2 — Multiple Vendor Filters Applied Simultaneously

Given the user is on the product listing page
When the user selects both 'Samsung' and 'Google' vendor checkboxes
Then only Samsung and Google products are displayed in the product grid

AC3 — Category Filter Works Independently

Given the user is on the product listing page
When the user selects the 'iPhone' category filter
Then only products in the iPhone category are displayed

AC4 — Deselecting All Filters Restores Full Listing

Given the user has applied one or more filters
When the user unchecks all selected filter checkboxes
Then all products are displayed in the product grid

AC5 — Filter Updates Without Page Reload

Given the user is on the product listing page
When the user selects or deselects any filter checkbox
Then the product grid updates immediately without a full page reload

AC6 — Empty State When No Products Match Filters

Given the user has applied a combination of filters that match no products
When the product grid renders
Then no product cards are displayed
And an empty state or message is shown indicating no results

AC7 — Filter and Sort Coexist

Given the user has selected the 'Samsung' vendor filter
When the user also applies the 'Lowest to Highest' sort order
Then only Samsung products are shown, sorted by price ascending

UserStory_05 · Product Sorting

Card

As a **shopper**, I want to sort the product listing by price or other available criteria so that I can organise the product catalogue to quickly locate products within my budget or preference.

Conversation

- A sort dropdown is present on the product listing page, located above or adjacent to the product grid.
- The available sort options are:
 - Lowest to Highest — sorts products by price in ascending order.
 - Highest to Lowest — sorts products by price in descending order.
- Selecting a sort option immediately re-orders the product grid without a page reload.
- Sort is applied on top of any active filters — filtered results are sorted, not the full catalogue.
- The default sort order (when no option is selected) is the natural order of products as returned by the data source.
- The selected sort option remains active while the user browses the listing page until changed or the page is reloaded.
- Sort operates independently of filter selections; changing the sort does not clear any active filters.

Confirmation (Acceptance Criteria)

AC1 — Sort Lowest to Highest Orders by Price Ascending

Given the user is on the product listing page
When the user selects 'Lowest to Highest' from the sort dropdown
Then products are re-ordered with the lowest-priced product displayed first
And prices increase progressively from left-to-right and top-to-bottom

AC2 — Sort Highest to Lowest Orders by Price Descending

Given the user is on the product listing page
When the user selects 'Highest to Lowest' from the sort dropdown
Then products are re-ordered with the highest-priced product displayed first

AC3 — Sort Updates Without Page Reload

Given the user is on the product listing page
When the user changes the sort option
Then the product grid re-orders immediately without a full page reload

AC4 — Sort Applied to Filtered Results

Given the user has applied the 'Google' vendor filter
When the user selects 'Lowest to Highest' sort
Then only Google products are displayed, ordered by price ascending

AC5 — Changing Sort Does Not Clear Filters

Given the user has the 'Apple' filter active and 'Lowest to Highest' sort applied
When the user changes the sort to 'Highest to Lowest'
Then only Apple products are displayed
And they are now ordered by price descending

UserStory_06 · Favourites (Wishlist)

Card

As a **authenticated user**, I want to mark products as favourites from the product listing page and view them in my favourites list so that I can save products I am interested in for easy reference without immediately adding them to the cart.

Conversation

- Each product card on the listing page contains a heart / favourite icon.
- Favouriting behaviour:
 - Clicking the heart icon on a product marks it as a favourite.
 - The heart icon toggles its visual state (filled/highlighted) to indicate the product is favourited.
 - Clicking the icon again removes the product from favourites (toggle behaviour).
- Authentication requirement:
 - Attempting to favourite a product while unauthenticated should redirect the user to the Sign In page.
 - After signing in, the user is returned to the product listing page.
- Favourites page:
 - Accessible from the navigation or directly via URL.
 - Displays all products that have been marked as favourites for the current session.
 - If no products are favourited, an empty state message is displayed.
- The 'fav_user' demo account has pre-existing favourited products for testing.
- Favourites persist for the duration of the authenticated session.

Confirmation (Acceptance Criteria)

AC1 — Authenticated User Can Favourite a Product

Given the user is authenticated and on the product listing page
When the user clicks the heart icon on a product card
Then the icon changes to a filled/highlighted state
And the product is added to the user's favourites

AC2 — Unauthenticated User Redirected on Favourite Attempt

Given the user is not authenticated
When the user clicks the heart icon on a product card
Then the user is redirected to the Sign In page

AC3 — Favourite Can Be Removed by Re-clicking

Given the user has a product marked as a favourite

When the user clicks the filled heart icon on that product card
Then the icon returns to its unfilled state
And the product is removed from the user's favourites

AC4 — Favourites Page Displays Favourited Products

Given the user has one or more favourited products
When the user navigates to the Favourites page
Then all favourited products are displayed

AC5 — Empty Favourites State

Given the user has no products marked as favourites
When the user navigates to the Favourites page
Then an empty state message is displayed indicating no favourites exist

AC6 — Pre-existing Favourites for fav_user

Given the user logs in as 'fav_user'
When the user navigates to the Favourites page
Then pre-existing favourited products are displayed

UserStory_07 · Shopping Cart Management

Card

*As a **shopper**, I want to add products to my shopping cart, review the cart contents, and remove items before checkout so that I can collect the products I intend to purchase and review my selection before committing to payment.*

Conversation

- Products are added to the cart by clicking the 'Add to Cart' button on any product card.
- The cart is implemented as a side-drawer / slide-in panel that opens from the right side of the screen.
- Cart panel contents:
 - List of added products, each showing product name, price, and quantity.
 - A remove / delete button per line item to remove that product from the cart.
 - Subtotal or total price calculated from the items in the cart.
 - A 'Checkout' button that initiates the checkout flow.
- Adding items:
 - Each click of 'Add to Cart' adds one unit of the product to the cart.
 - The cart badge count in the header increments accordingly.
- Removing items:
 - Clicking the remove button on a line item deletes that product from the cart.
 - The cart total and badge count update immediately after removal.
- Empty cart state:
 - If all items are removed, the cart displays an empty state message (e.g., 'Add some products in the bag :)').
 - The 'Checkout' button is not available or is disabled when the cart is empty.
- The cart panel can be closed without navigating away from the current page.
- Proceeding to checkout from the cart when the user is unauthenticated redirects the user to the Sign In page.

Confirmation (Acceptance Criteria)

AC1 — Product Added to Cart Successfully

Given the user is on the product listing page

When the user clicks the 'Add to Cart' button on a product card

Then the cart side-drawer opens

And the product appears as a line item in the cart

And the header cart badge count increments by one

AC2 — Cart Displays Correct Total

Given the user has added multiple products to the cart

When the user views the cart panel
Then the total price reflects the sum of all added product prices

AC3 — Product Removed from Cart

Given the user has at least one product in the cart
When the user clicks the remove button on a line item
Then that product is removed from the cart
And the cart total and badge count update to reflect the removal

AC4 — Empty Cart State

Given the user removes all items from the cart
When no items remain in the cart
Then an empty state message is displayed
And the Checkout button is absent or disabled

AC5 — Unauthenticated User Redirected at Checkout

Given the user is not authenticated and has items in the cart
When the user clicks the 'Checkout' button in the cart panel
Then the user is redirected to the Sign In page

AC6 — Cart Persists Across Navigation

Given the user has items in the cart
When the user navigates to another page within the application
Then the cart contents remain unchanged
And the header badge count continues to reflect the correct item count

UserStory_08 · Checkout – Shipping Information

Card

*As a **authenticated shopper**, I want to complete the checkout form by entering my shipping details and submitting my order so that I can finalise my purchase by providing delivery information.*

Conversation

- The checkout page is accessible only to authenticated users; unauthenticated users are redirected to Sign In.
- Checkout is initiated by clicking the 'Checkout' button in the cart panel when the cart contains at least one item.
- The checkout form contains the following required fields:
 - First Name (id: firstNameInput) — free-text input, mandatory.
 - Last Name (id: lastNameInput) — free-text input, mandatory.
 - Address Line 1 (id: addressLine1Input) — free-text input, mandatory.
 - Province / State (id: provinceInput) — free-text input, mandatory.
 - Post Code / Zip Code (id: postCodeInput) — free-text input, mandatory.
- Validation rules:
 - All five fields are mandatory; the form cannot be submitted unless all fields contain a value.
 - Submitting with any empty mandatory field should prevent navigation and indicate the missing field(s).
- Submission:
 - The 'Submit' / Continue button (id: checkout-shipping-continue) triggers form validation and order processing.
 - On successful validation and submission, the user is navigated to the Order Confirmation page.
- The checkout page displays an order summary (items and total) alongside the shipping form.
- The user cannot reach the checkout page with an empty cart; they are redirected back to the product listing page.

Confirmation (Acceptance Criteria)

AC1 — Checkout Page Accessible Only When Authenticated

Given the user is not authenticated
When the user navigates directly to the checkout URL
Then the system redirects the user to the Sign In page

AC2 — Successful Form Submission Navigates to Confirmation

Given the user is authenticated and has items in the cart
When the user completes all required checkout fields with valid data
And the user clicks the Submit / Continue button

Then the system processes the order
And the user is navigated to the Order Confirmation page

AC3 — Submission Blocked When Required Fields Are Empty

Given the user is on the checkout page
When the user leaves one or more required fields empty
And the user clicks the Submit button
Then form submission is prevented
And an indication of the missing field(s) is presented to the user

AC4 — All Required Fields Are Present on Checkout Form

Given the user navigates to the checkout page
When the page loads
Then the form displays fields for First Name, Last Name, Address Line 1, Province, and Post Code

AC5 — Order Summary Displayed on Checkout Page

Given the user has items in the cart and navigates to the checkout page
When the checkout page loads
Then an order summary showing cart items and total is displayed alongside the form

AC6 — Empty Cart Prevents Access to Checkout

Given the user is authenticated but the cart is empty
When the user attempts to access the checkout page
Then the system does not allow checkout to proceed
And the user is redirected to the product listing page

UserStory_09 · Order Confirmation

Card

*As a **authenticated shopper**, I want to view an order confirmation page after successfully submitting my checkout so that I receive assurance that my order has been placed and can access a record of my purchase.*

Conversation

- The Order Confirmation page is displayed immediately after a successful checkout form submission.
- The confirmation page contains a confirmation message (element id: confirmation-message) indicating the order was successfully placed.
- A receipt download link or button is available (id: downloadOrder or similar), allowing the user to download/view their order receipt.
- The confirmation page includes:
 - Order confirmation message.
 - Summary of the purchased item(s).
 - Option to download a receipt or order document.
- The confirmation page should not be directly accessible without completing a valid checkout (i.e., it is a result of a successful submission flow).
- Existing orders:
 - The 'existing_orders_user' demo account has pre-existing orders visible upon login.
 - These pre-existing orders are accessible from the user's order history, not from the checkout flow.
- The shopping cart is cleared after a successful order submission.
- The header cart badge should reset to zero after the order is confirmed.

Confirmation (Acceptance Criteria)

AC1 — Confirmation Message Displayed After Successful Checkout

Given the user has completed the checkout form with valid data
When the user submits the checkout form
Then the Order Confirmation page is displayed
And a confirmation message is visible on the page

AC2 — Receipt Download Available on Confirmation Page

Given the user is on the Order Confirmation page
When the page loads
Then a receipt download link or button is available
And clicking it initiates a download or opens the order receipt

AC3 — Cart Is Cleared After Order Confirmation

Given the user has completed a successful checkout
When the Order Confirmation page is displayed
Then the shopping cart is empty
And the header cart badge count reflects zero items

AC4 — Existing Orders Visible for existing_orders_user

Given the user logs in as 'existing_orders_user'
When the user accesses the orders history
Then pre-existing orders are visible

AC5 — Confirmation Page Not Directly Accessible Without Checkout

Given the user has not completed a checkout
When the user navigates directly to the Order Confirmation URL
Then the system does not display an order confirmation
And the user is redirected or shown an appropriate page

UserStory_10 · Location-Based Product Offers

Card

As a **authenticated shopper**, I want to view promotional offers that are applicable based on my geographic location so that I can access region-specific deals and promotions relevant to my area.

Conversation

- The application supports a location-based offers feature that displays offers relevant to the user's GPS/geolocation.
- Offers are bundled within the application's data and mapped to specific geographic regions (e.g., Singapore, Mumbai).
- The application detects or receives the user's location in order to determine applicable offers.
- When a supported geographic location is detected, the matching offers for that region are displayed to the authenticated user.
- If no location-specific offers exist for the user's region, a default or empty offers state is shown.
- The offers feature is available only to authenticated users.
- Offers data is pre-bundled in the application (no external API dependency for demo purposes).
- The offers page or panel must render without errors when offers are available and when no offers apply.

Confirmation (Acceptance Criteria)

AC1 — Offers Displayed for Matching Location

Given the user is authenticated
And the user's GPS location is set to Singapore
When the user views the offers section
Then offers applicable to Singapore are displayed

AC2 — Offers Displayed for Mumbai Location

Given the user is authenticated
And the user's GPS location is set to Mumbai
When the user views the offers section
Then offers applicable to Mumbai are displayed

AC3 — No Offers for Unsupported Location

Given the user is authenticated
And the user's location does not match any supported region
When the user views the offers section
Then an empty state or 'no offers available' message is displayed

And no errors are thrown

AC4 — Unauthenticated User Cannot Access Offers

Given the user is not authenticated

When the user attempts to access the offers page

Then the user is redirected to the Sign In page

AC5 — Offers Page Renders Without Errors

Given any geographic location context

When the authenticated user navigates to the offers section

Then the page loads without any JavaScript errors or broken states

And the content renders correctly regardless of whether offers are present