CS 447/647

Pluggable Authentication Modules


Goals

What is the purpose of PAM?

What are the four PAM control types?

How are PAM variables passed into libpam-script scripts?

What is the data structure used by PAM modules?



Pluggable Authentication Modules (PAM)

- Provides an interface for authentication
 - login(1) utility calls the PAM libraries
 - Iterates over a stack composed of modules
- Configurations in /etc/pam.d/*
- "You can choose to have no security or absolute security (no access permitted)."
 - Errs toward the latter
- Configuration errors will lock you out.

Pluggable Authentication Modules (PAM)

- Four separate types of (management) module-type
 - Authentication
 - Account
 - Session
 - Password
- man pam.conf

Authentication

- Instructs application to prompt for username and password
 - Verifies access credentials
 - pam_unix.so checks /etc/passwd and /etc/shadow

Account

- Non-authentication based account management
- Restrict/permit access to a service based on
 - Time of day
 - Resources available
 - Location of a user

Session

- "Does things" before/after a user can be given service
 - Logging
 - Mounting filesystems

Password

Used for changing and manipulating passwords.

Example

```
module-type control-flag module-path [arguments]
```

Add:

```
auth optional pam_warn.so
```

To:

```
/etc/pam.d/common-auth
```

Exit and log back-in

```
tail -n20 /var/log/auth.log
```

Absolute security

```
#
 default; deny access
#
                  required
                                  pam_deny.so
other
        auth
other
                  required
                                  pam_deny.so
        account
        password required
                                  pam_deny.so
other
                  required
        session
                                  pam_deny.so
other
```

```
_/_( <sup>"</sup> )_/_
```

```
#
# default; any access
#
```

```
other auth required pam_permit.so other account required pam_permit.so other password required pam_permit.so other session required pam_permit.so
```

#This module is very dangerous. It should be used with extreme caution. man 8 pam_permit

Modules

pam_access - Provides access management

pam_unix - Authenticate against /etc files

pam_env - Control environmental variables

pam_systemd - Registers sessions in systemd hierarchy

pam_ldap - LDAP authentication

pam_sss - SSS authentication

pam_permit - Always allows access

pam listfile - Allows you to authenticate based on lines in a file

module-type control-flag module-path [arguments]

module-type

auth - Identify user and grant permissions

account - enforces restrictions

session - tasks before login password - changing a password

control-flag

include - Includes another file

optional - Only important if the only module required - Failure eventually causes stack to fail requisite - Same as required but stack fails

immediately

sufficient - Exits upon success but does not override

module-path (/lib/x86_64-linux-gnu/security)

pam_unix.so - Unix file authentication Local
pam_ldap.so - LDAP authentication Network

pam_krb5.so - Kerberos Authentication
Network

pam sss.so - SSSD authentication

Network

auth [success=ok new_authtok_reqd=ok ignore=ignore user_unknown=bad default=die] pam_securetty.so auth requisite pam_nologin.so session [success=ok ignore=ignore module_unknown=ignore default=bad] pam_selinux.so close session required pam_loginuid.so session [success=ok ignore=ignore module_unknown=ignore default=bad] pam_selinux.so open

session required pam_env.so readenv=1 session required pam_env.so readenv=1 envfile=/etc/default/locale

pam_faildelay.so delay=3000000

session required pam_limits.so
session optional pam_lastlog.so
session optional pam_motd.so motd=/run/motd.dynamic
session optional pam_motd.so noupdate

pam_group.so

session optional pam_mail.so standard session optional pam_keyinit.so force revoke

@include common-account @include common-session <u>@include common</u>-password

@include common-auth

optional

auth

auth

Syntax [value1=action1 value2=action2 ...]

```
Values
                          Actions
                           ignore - will not contribute to return
SUCCESS
                          bad
                                 - module failed
open err
                          die
symbol err
                                 - same as bad but immediately exits
                          ok
service err
                                 - PAM SUCCESS
                          done
                                 - Terminate the stack and return
system err
buf err
                                 - Same as OK but skips N modules
                          N
                                 - clear all memory and start with
perm denied
                          reset
abort
                          next
default
                                   module
. . .
```

Handling authentication

```
apt install libpam-script libpam-mkhomedir
pam-auth-update #Friendly
vim|emacs|nano /etc/pam.d/common-auth
```

libpam-script

- Invoke scripts within the PAM stack
 - Authentication
 - Passwd changes
 - Session opening
 - Session closing
- Scripts stored in /usr/share/libpam-script

libpam-script scripts

- pam_script_auth Authentication
- pam_script_acct Account
- pam_script_passwd Password changes
- pam_script_ses_open Session open
- pam_script_ses_close Session close

pam_script_auth

```
/usr/share/libpam-script/pam script auth
#!/usr/bin/env python3
import os
import sys
print("PAM Script Start")
for k, v in os.environ.items():
  print("{0}, {1}".format(k, v))
print("PAM Script End")
sys.exit(0)
```

PAM

/run/pwchk

uid: greater than 0

pam_script_auth

user:password



/etc/pam.d/nginx_pwchk

auth optional pam_warn.so
auth [success=1 default=ignore] pam_script.so
dir=/usr/local/pam
auth requisite pam_deny.so
auth required pam permit.so



uid: 0

pwchk.py

/etc/pam.d/login #or

auth optional pam_warn.so
auth [success=1 default=ignore] pam_unix.so
auth requisite pam_deny.so
auth required pam_permit.so



True or False

socket 0666 rw-rw-rw