

# Chapter 6

# The Link Layer

# and LANs

A note on the use of these PowerPoint slides:


We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we'd like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

For a revision history, see the slide note for this page.

Thanks and enjoy! JFK/KWR

All material copyright 1996-2020  
J.F Kurose and K.W. Ross, All Rights Reserved



*Computer Networking: A  
Top-Down Approach*  
8<sup>th</sup> edition  
Jim Kurose, Keith Ross  
Pearson, 2020

# Link layer and LANs: our goals

- understand principles behind link layer services:
  - error detection, correction
  - sharing a broadcast channel: multiple access
  - link layer addressing
  - local area networks: Ethernet, VLANs
- datacenter networks
- instantiation, implementation of various link layer technologies



# Link layer, LANs: roadmap


- introduction
  - error detection, correction
  - multiple access protocols
  - LANs
    - addressing, ARP
    - Ethernet
    - switches
    - VLANs
  - link virtualization: MPLS
  - data center networking
- 
- a day in the life of a web request

# Link layer: introduction

terminology:

- hosts and routers: nodes
- communication channels that connect adjacent nodes along communication path: links
  - wired
  - wireless
  - LANs
- layer-2 packet: *frame*, encapsulates datagram

*link layer* has responsibility of transferring datagram from one node to *physically adjacent* node over a link



# Link layer: context


- datagram transferred by different link protocols over different links:
  - e.g., WiFi on first link, Ethernet on next link
- each link protocol provides different services
  - e.g., may or may not provide reliable data transfer over link

## transportation analogy:

- trip from Princeton to Lausanne
  - limo: Princeton to JFK
  - plane: JFK to Geneva
  - train: Geneva to Lausanne
- tourist = **datagram**
- transport segment = **communication link**
- transportation mode = **link-layer protocol**
- travel agent = **routing algorithm**


# Link layer: services

- **framing, link access:**
  - encapsulate datagram into frame, adding header, trailer
  - channel access if shared medium
  - “MAC” addresses in frame headers identify source, destination (different from IP address!)
- **reliable delivery between adjacent nodes**
  - we already know how to do this!
  - seldom used on low bit-error links
  - wireless links: high error rates
    - Q: why both link-level and end-end reliability?




# Link layer: services (more)

- **flow control:**
  - pacing between adjacent sending and receiving nodes
- **error detection:**
  - errors caused by signal attenuation, noise.
  - receiver detects errors, signals retransmission, or drops frame
- **error correction:**
  - receiver identifies *and corrects* bit error(s) without retransmission
- **half-duplex and full-duplex:**
  - with half duplex, nodes at both ends of link can transmit, but not at same time




# Where is the link layer implemented?

- in each-and-every host
- link layer implemented in *network interface card* (NIC) or on a chip
  - Ethernet, WiFi card or chip
  - implements link, physical layer
- attaches into host's system buses
- combination of hardware, software, firmware



# Interfaces communicating



sending side:

- encapsulates datagram in frame
- adds error checking bits, reliable data transfer, flow control, etc.

receiving side:

- looks for errors, reliable data transfer, flow control, etc.
- extracts datagram, passes to upper layer at receiving side

# Link layer, LANs: roadmap

- introduction
- **error detection, correction**
- multiple access protocols
- LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANs
- link virtualization: MPLS
- data center networking




- a day in the life of a web request

# Error detection

EDC: error detection and correction bits (e.g., redundancy)

D: data protected by error checking, may include header fields




Error detection not 100% reliable!

- protocol may miss some errors, but rarely
- larger EDC field yields better detection and correction

# Parity checking

## single bit parity:


- detect single bit errors



Even parity: set parity bit so there is an even number of 1's

## two-dimensional bit parity:

- detect *and correct* single bit errors



no errors:	1 0 1 0 1   1
	1 1 1 1 0   0
	0 1 1 1 0   1
	1 0 1 0 1   0

detected and correctable single-bit error:

1 0 1 0 1   1
1 0 1 1 0   0
0 1 1 1 0   1
1 0 1 0 1   0

parity error

parity error

\* Check out the online interactive exercises for more examples: [http://gaia.cs.umass.edu/kurose\\_ross/interactive/](http://gaia.cs.umass.edu/kurose_ross/interactive/)

# Internet checksum (review)

**Goal:** detect errors (*i.e.*, flipped bits) in transmitted segment

sender:

- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- **checksum:** addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
  - not equal - error detected
  - equal - no error detected. *But maybe errors nonetheless?* More later ....

# Cyclic Redundancy Check (CRC)

- more powerful error-detection coding
- **D**: data bits (given, think of these as a binary number)
- **G**: bit pattern (generator), of  $r+1$  bits (given)



goal: choose  $r$  CRC bits, **R**, such that  $\langle D, R \rangle$  exactly divisible by **G** ( $\text{mod } 2$ )

- receiver knows **G**, divides  $\langle D, R \rangle$  by **G**. If non-zero remainder: error detected!
- can detect all burst errors less than  $r+1$  bits
- widely used in practice (Ethernet, 802.11 WiFi)

# Cyclic Redundancy Check (CRC): example

We want:

$$D \cdot 2^r \text{ XOR } R = nG$$


or equivalently:

$$D \cdot 2^r = nG \text{ XOR } R$$

or equivalently:

if we divide  $D \cdot 2^r$  by  $G$ , want remainder  $R$  to satisfy:

$$R = \text{remainder} \left[ \frac{D \cdot 2^r}{G} \right]$$



\* Check out the online interactive exercises for more examples: [http://gaia.cs.umass.edu/kurose\\_ross/interactive/](http://gaia.cs.umass.edu/kurose_ross/interactive/)

# Link layer, LANs: roadmap

- introduction
- error detection, correction
- **multiple access protocols**
- LANs
  - addressing, ARP
  - Ethernet
  - switches
  - VLANs
- link virtualization: MPLS
- data center networking



- a day in the life of a web request

# Multiple access links, protocols

two types of “links”:

- point-to-point
  - point-to-point link between Ethernet switch, host
  - PPP for dial-up access
- broadcast (shared wire or medium)
  - old-fashioned Ethernet
  - upstream HFC in cable-based access network
  - 802.11 wireless LAN, 4G/4G satellite




shared wire (e.g.,  
cabled Ethernet)



shared radio: 4G/5G



shared radio: WiFi



shared radio: satellite



humans at a cocktail party  
(shared air, acoustical)

# Multiple access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
  - *collision* if node receives two or more signals at the same time

## multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
  - no out-of-band channel for coordination

# An ideal multiple access protocol

*given:* multiple access channel (MAC) of rate  $R$  bps

*desiderata:*

1. when one node wants to transmit, it can send at rate  $R$ .
2. when  $M$  nodes want to transmit, each can send at average rate  $R/M$
3. fully decentralized:
  - no special node to coordinate transmissions
  - no synchronization of clocks, slots
4. simple

# MAC protocols: taxonomy


three broad classes:

- **channel partitioning**
  - divide channel into smaller “pieces” (time slots, frequency, code)
  - allocate piece to node for exclusive use
- ***random access***
  - channel not divided, allow collisions
  - “recover” from collisions
- **“taking turns”**
  - nodes take turns, but nodes with more to send can take longer turns

# Channel partitioning MAC protocols: TDMA

## TDMA: time division multiple access


- access to channel in “rounds”
- each station gets fixed length slot (length = packet transmission time) in each round
- unused slots go idle
- example: 6-station LAN, 1,3,4 have packets to send, slots 2,5,6 idle



# Channel partitioning MAC protocols: FDMA

## FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have packet to send, frequency bands 2,5,6 idle



# Random access protocols

- when node has packet to send
  - transmit at full channel data rate  $R$ .
  - no *a priori* coordination among nodes
- two or more transmitting nodes: “collision”
- **random access MAC protocol** specifies:
  - how to detect collisions
  - how to recover from collisions (e.g., via delayed retransmissions)
- examples of random access MAC protocols:
  - ALOHA, slotted ALOHA
  - CSMA, CSMA/CD, CSMA/CA

# Slotted ALOHA

## assumptions:


- all frames same size
- time divided into equal size slots (time to transmit 1 frame)
- nodes start to transmit only slot beginning
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

## operation:

- when node obtains fresh frame, transmits in next slot
  - *if no collision*: node can send new frame in next slot
  - *if collision*: node retransmits frame in each subsequent slot with probability  $p$  until success

randomization – *why?*

# Slotted ALOHA



## Pros:

- single active node can continuously transmit at full rate of channel
- highly decentralized: only slots in nodes need to be in sync
- simple

## Cons:

- collisions, wasting slots
- idle slots
- nodes may be able to detect collision in less than time to transmit packet
- clock synchronization


# Slotted ALOHA: efficiency

**efficiency:** long-run fraction of successful slots (many nodes, all with many frames to send)

- *suppose:*  $N$  nodes with many frames to send, each transmits in slot with probability  $p$ 
  - prob that given node has success in a slot =  $p(1-p)^{N-1}$
  - prob that *any* node has a success =  $Np(1-p)^{N-1}$
  - max efficiency: find  $p^*$  that maximizes  $Np(1-p)^{N-1}$
  - for many nodes, take limit of  $Np^*(1-p^*)^{N-1}$  as  $N$  goes to infinity, gives:  
*max efficiency =  $1/e = .37$*
- *at best:* channel used for useful transmissions 37% of time!

# Pure ALOHA

- unslotted Aloha: simpler, no synchronization
  - when frame first arrives: transmit immediately
- collision probability increases with no synchronization:
  - frame sent at  $t_0$  collides with other frames sent in  $[t_0-1, t_0+1]$



- pure Aloha efficiency: 18% !

# CSMA (carrier sense multiple access)

simple **CSMA**: listen before transmit:


- if channel sensed idle: transmit entire frame
- if channel sensed busy: defer transmission
- human analogy: don't interrupt others!

**CSMA/CD**: CSMA with *collision detection*

- collisions *detected* within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection easy in wired, difficult with wireless
- human analogy: the polite conversationalist


# CSMA: collisions

- collisions *can* still occur with carrier sensing:
  - propagation delay means two nodes may not hear each other's just-started transmission
- **collision:** entire packet transmission time wasted
  - distance & propagation delay play role in determining collision probability



# CSMA/CD:

- CSMA/CS reduces the amount of time wasted in collisions
  - transmission aborted on collision detection



# Ethernet CSMA/CD algorithm

1. NIC receives datagram from network layer, creates frame
2. If NIC senses channel:
  - if **idle**: start frame transmission.
  - if **busy**: wait until channel idle, then transmit
3. If NIC transmits entire frame without collision, NIC is done with frame !
4. If NIC detects another transmission while sending: abort, send jam signal
5. After aborting, NIC enters *binary (exponential) backoff*:
  - after  $m$ th collision, NIC chooses  $K$  at random from  $\{0,1,2, \dots, 2^m-1\}$ . NIC waits  $K \cdot 512$  bit times, returns to Step 2
  - more collisions: longer backoff interval

# CSMA/CD efficiency

- $T_{prop}$  = max prop delay between 2 nodes in LAN
- $t_{trans}$  = time to transmit max-size frame

$$efficiency = \frac{1}{1 + 5t_{prop}/t_{trans}}$$

- efficiency goes to 1
  - as  $t_{prop}$  goes to 0
  - as  $t_{trans}$  goes to infinity
- better performance than ALOHA: and simple, cheap, decentralized!

# “Taking turns” MAC protocols

## channel partitioning MAC protocols:

- share channel *efficiently* and *fairly* at high load
- inefficient at low load: delay in channel access,  $1/N$  bandwidth allocated even if only 1 active node!

## random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead


## “taking turns” protocols

- look for best of both worlds!

# “Taking turns” MAC protocols

## polling:


- master node “invites” other nodes to transmit in turn
- typically used with “dumb” devices
- concerns:
  - polling overhead
  - latency
  - single point of failure (master)




# “Taking turns” MAC protocols

## token passing:

- control *token* passed from one node to next sequentially.
- token message
- concerns:
  - token overhead
  - latency
  - single point of failure (token)




# Cable access network: FDM, TDM and random access!



- **multiple** downstream (broadcast) FDM channels: up to 1.6 Gbps/channel
  - single CMTS transmits into channels
- **multiple** upstream channels (up to 1 Gbps/channel)
  - **multiple access:** all users contend (random access) for certain upstream channel time slots; others assigned TDM

# Cable access network:



## DOCSIS: data over cable service interface specification

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
  - downstream MAP frame: assigns upstream slots
  - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots

# Summary of MAC protocols

- **channel partitioning**, by time, frequency or code
  - Time Division, Frequency Division
- **random access (dynamic)**,
  - ALOHA, S-ALOHA, CSMA, CSMA/CD
  - carrier sensing: easy in some technologies (wire), hard in others (wireless)
  - CSMA/CD used in Ethernet
  - CSMA/CA used in 802.11
- **taking turns**
  - polling from central site, token passing
  - Bluetooth, FDDI, token ring

# Link layer, LANs: roadmap

- introduction
- error detection, correction
- multiple access protocols
- **LANs**
  - addressing, ARP
  - Ethernet
  - switches
  - VLANs
- link virtualization: MPLS
- data center networking



- a day in the life of a web request


# MAC addresses

- 32-bit IP address:
    - *network-layer* address for interface
    - used for layer 3 (network layer) forwarding
    - e.g.: 128.119.40.136
  - MAC (or LAN or physical or Ethernet) address:
    - function: used “locally” to get frame from one interface to another physically-connected interface (same subnet, in IP-addressing sense)
    - 48-bit MAC address (for most LANs) burned in NIC ROM, also sometimes software settable
    - e.g.: 1A-2F-BB-76-09-AD
- hexadecimal (base 16) notation  
(each “numeral” represents 4 bits)*

# MAC addresses

each interface on LAN

- has unique 48-bit **MAC** address
- has a locally unique 32-bit IP address (as we've seen)




# MAC addresses

- MAC address allocation administered by IEEE
- manufacturer buys portion of MAC address space (to assure uniqueness)
- analogy:
  - MAC address: like Social Security Number
  - IP address: like postal address
- MAC flat address: portability
  - can move interface from one LAN to another
  - recall IP address *not* portable: depends on IP subnet to which node is attached

# ARP: address resolution protocol

*Question:* how to determine interface's MAC address, knowing its IP address?



**ARP table:** each IP node (host, router) on LAN has table

- IP/MAC address mappings for some LAN nodes:  
<IP address; MAC address; TTL>
- TTL (Time To Live): time after which address mapping will be forgotten (typically 20 min)


# ARP protocol in action

example: A wants to send datagram to B

- B's MAC address not in A's ARP table, so A uses ARP to find B's MAC address

- 1 A broadcasts ARP query, containing B's IP addr
- destination MAC address = FF-FF-FF-FF-FF-FF
  - all nodes on LAN receive ARP query


ARP table in A		
IP addr	MAC addr	TTL



# ARP protocol in action

example: A wants to send datagram to B


- B's MAC address not in A's ARP table, so A uses ARP to find B's MAC address



# ARP protocol in action

example: A wants to send datagram to B


- B's MAC address not in A's ARP table, so A uses ARP to find B's MAC address



# Routing to another subnet: addressing


walkthrough: sending a datagram from *A* to *B* via *R*

- focus on addressing – at IP (datagram) and MAC layer (frame) levels
- assume that:
  - A knows B's IP address
  - A knows IP address of first hop router, R (how?)
  - A knows R's MAC address (how?)




# Routing to another subnet: addressing

- A creates IP datagram with IP source A, destination B
- A creates link-layer frame containing A-to-B IP datagram
  - R's MAC address is frame's destination




# Routing to another subnet: addressing

- frame sent from A to R
- frame received at R, datagram removed, passed up to IP




# Routing to another subnet: addressing

- R determines outgoing interface, passes datagram with IP source A, destination B to link layer
- R creates link-layer frame containing A-to-B IP datagram. Frame destination address: B's MAC address




# Routing to another subnet: addressing

- R determines outgoing interface, passes datagram with IP source A, destination B to link layer
- R creates link-layer frame containing A-to-B IP datagram. Frame destination address: B's MAC address
- transmits link-layer frame



# Routing to another subnet: addressing

- B receives frame, extracts IP datagram destination B
- B passes datagram up protocol stack to IP



# Link layer, LANs: roadmap

- introduction
- error detection, correction
- multiple access protocols
- **LANs**
  - addressing, ARP
  - **Ethernet**
  - switches
  - VLANs
- link virtualization: MPLS
- data center networking




- a day in the life of a web request

# Ethernet

“dominant” wired LAN technology:

- first widely used LAN technology
- simpler, cheap
- kept up with speed race: 10 Mbps – 400 Gbps
- single chip, multiple speeds (e.g., Broadcom BCM5761)




*Metcalfe's Ethernet  
sketch*


# Ethernet: physical topology

- **bus:** popular through mid 90s
  - all nodes in same collision domain (can collide with each other)
- **switched:** prevails today
  - active link-layer 2 *switch* in center
  - each “spoke” runs a (separate) Ethernet protocol (nodes do not collide with each other)

bus: coaxial cable



switched



# Ethernet frame structure


sending interface encapsulates IP datagram (or other network layer protocol packet) in **Ethernet frame**



*preamble:*

- used to synchronize receiver, sender clock rates
- 7 bytes of 10101010 followed by one byte of 10101011

# Ethernet frame structure (more)



- **addresses:** 6 byte source, destination MAC addresses
  - if adapter receives frame with matching destination address, or with broadcast address (e.g., ARP packet), it passes data in frame to network layer protocol
  - otherwise, adapter discards frame
- **type:** indicates higher layer protocol
  - mostly IP but others possible, e.g., Novell IPX, AppleTalk
  - used to demultiplex up at receiver
- **CRC:** cyclic redundancy check at receiver
  - error detected: frame is dropped

# Ethernet: unreliable, connectionless

- **connectionless:** no handshaking between sending and receiving NICs
- **unreliable:** receiving NIC doesn't send ACKs or NAKs to sending NIC
  - data in dropped frames recovered only if initial sender uses higher layer rdt (e.g., TCP), otherwise dropped data lost
- Ethernet's MAC protocol: unslotted **CSMA/CD with binary backoff**

# 802.3 Ethernet standards: link & physical layers

- *many* different Ethernet standards
  - common MAC protocol and frame format
  - different speeds: 2 Mbps, 10 Mbps, 100 Mbps, 1Gbps, 10 Gbps, 40 Gbps
  - different physical layer media: fiber, cable

