

Managed Runtime Administration

Manage your organizations, projects, environments, and bundles associated with your Storefront Next storefront with various tools, including the [Runtime Admin](#) console, Business Manager, and Account Manager.

Alternatively, perform the administration tasks with the [Managed Runtime API](#).

Contents

- Prerequisites
- Organization**
- Projects
- Deployment Notifications
- Environments
- Environment Variables
- Redirects
- Users

Prerequisites

- For Runtime Admin access, contact your B2C Commerce administrator and ask them to add one of these roles to your account in Account Manager: **Managed Runtime User** or **Managed Runtime Admin**.

Organization

Organization admins can manage user access and permissions at the organization level, which affects user access across all projects within the organization.

Add Organization Users

To add a user at the organization level:

- Log in to [Account Manager](#).
- Find the users in your organization who need access.
- Add the **Managed Runtime Admin** or **Managed Runtime User** role and save. Users can now log in to [Runtime Admin](#) for your organization.



access individual projects.

Edit Organization User Permissions

To modify a user's organization-level permissions:

1. Navigate to **Organization Users**.
2. Click **Edit** next to the user's name.
3. Modify the permissions as needed.
 - **Certificates**: Allows the user to view, request, manage, and renew TLS certificates.
 - **View All Projects**: Allows read-only access to all projects within the organization.
4. Click **Save**.

Remove Organization Users

To remove a user from the organization:

1. Log in to [Account Manager](#).
2. Find the users in your organization who need access.
3. Remove the **Managed Runtime Admin** or **Managed Runtime User** role and save.

Warning

Removing a user from Managed Runtime revokes their access to all projects within the organization.

Projects

Projects help you manage multiple environments within an organization. Every Storefront Next project has a corresponding project within Managed Runtime for deploying and hosting the storefront code on Salesforce public cloud infrastructure. The storefront setup in Business Manager automatically creates a project for the storefront.

Find a Project

To find a project via the UI, start in Business Manager or Runtime Admin. To view the project, you must be assigned one of the project roles described in [Prerequisites](#).




 and then select **Administration** >

Sites > **Storefronts**, and then click your storefront.

2. In the storefront detail page, click the environment, and then click **Manage** next to **Deployments**. You're redirected to the Deployments page in Managed Runtime in a new tab.
3. Click the project name in the header.

To find an existing project in Managed Runtime:

1. Log in to [Runtime Admin](#) .
2. Select an organization from the organization menu (top left), if necessary.
3. Click the name of the project.



To quickly switch between projects, use the project menu at the top of the page.

View and Edit Project Settings

From the Project Settings page:

- Look up the project ID and ensure that it matches a Storefront Next configuration.
- Edit the project ID.
- View and edit the project's name and URL.
- Delete the project.
- Manage deployment notifications. (See next section.)

To access the Project Settings page:

1. Go to a project's Overview page.
2. Click Project Settings from the left navigation.

To edit the settings, click **Edit**, make your edits, and click **Update**. To discard your edits, click **Cancel**.

To delete a project, click **Delete**, enter the project name to confirm, and click **Yes, Delete**. To keep the project, click **No, Keep**.




deployment events:

- Start Deployment
- Successful Deployment
- Failed Deployment

Add a Notification

To add a notification:


1. Go to a project's Overview page.
2. Click **Project Settings** from the left navigation.
3. Click **Add Notification**.
4. Select one or more environments to be notified about.
5. Select one or more deployment events.
6. Enter email addresses for all notification recipients.
7. Click **Add Notification**.



Edit a Notification

To edit a notification:

1. Go to a project's Overview page.
2. Click **Project Settings** from the left navigation.
3. Click the ... button next to the notification.
4. Click **Edit**.
5. Change any of the notification settings.
6. Click **Update Notification**.



Remove a Notification

To remove a notification:

1. Go to a project's Overview page.



5. Click **Yes, Remove**.

Environments

Create and manage environments in Business Manager, in the storefront's page. When you create a storefront in Business Manager, it is preconfigured with the embedded content delivery network (eCDN) and a default domain. The default domain maps the domain to the MRT backend site.

To learn more about environments and other related concepts, see the [Managed Runtime Overview](#).

Prerequisites

- Business Administrator role in Account Manager or a role for the Business Manager Module and Organization context with read-write access to storefronts. See [Create a Role in B2C Commerce](#) [in Salesforce Help](#).

Create an Environment in Business Manager

See [Create an Environment in Business Manager](#).

Supported Regions

All supported regions have a paired backup region for failovers. Make sure that your application runs correctly in the selected primary and backup regions:

Primary Region	Backup Region
us-east-1 - US East (N. Virginia)	us-east-2 - US East (Ohio)
us-east-2 - US East (Ohio)	us-east-1 - US East (N. Virginia)
us-west-1 - US West (N. California)	us-west-2 - US West (Oregon)
us-west-2 - US West (Oregon)	us-west-1 - US West (N. California)

[Try for free](#)

sa-east-1 - South America (São Paulo)	us-east-1 - US East (Northern Virginia)
ap-south-1 - Asia Pacific (Mumbai)	ap-south-2 - Asia Pacific (Hyderabad)
ap-south-2 - Asia Pacific (Hyderabad)	ap-south-1 - Asia Pacific (Mumbai)
ap-southeast-1 - Asia Pacific (Singapore)	ap-northeast-2 - Asia Pacific (Seoul)
ap-southeast-2 - Asia Pacific (Sydney)	ap-southeast-1 - Asia Pacific (Singapore)
ap-southeast-3 - Asia Pacific (Jakarta)	ap-southeast-1 - Asia Pacific (Singapore)
ap-northeast-2 - Asia Pacific (Seoul)	ap-southeast-1 - Asia Pacific (Singapore)
ap-northeast-1 - Asia Pacific (Tokyo)	ap-northeast-3 - Asia Pacific (Osaka)
ap-northeast-3 - Asia Pacific (Osaka)	ap-northeast-1 - Asia Pacific (Tokyo)
eu-west-1 - EU (Ireland)	eu-west-3 - EU (Paris)
eu-west-2 - EU (London)	eu-west-1 - EU (Ireland)
eu-west-3 - EU (Paris)	eu-central-1 - EU (Frankfurt)
eu-central-1 - EU (Frankfurt)	eu-west-3 - EU (Paris)
eu-central-2 - EU (Zurich)	eu-central-1 - EU (Frankfurt)
eu-south-1 - EU (Milan)	eu-central-1 - EU (Frankfurt)
me-central-1 - Middle East (United Arab Emirates)	eu-west-2 - EU (London)



Deploy a Bundle

For any site that uses Storefront Next and Managed Runtime, designate only **one bundle at a time** as deployed per environment.

1. Go to a project's overview page.
2. Click the name of the environment you want to deploy to. For example: **production**.
3. Under **Bundles**, click **Deploy** next to the bundle you want to deploy.
4. Click **Confirm Deploy**.
5. Wait until the deployment is complete.

When the deployment has successfully completed, the bundle appears underneath the heading **Deployed Bundle**. (For your first deployment to a new environment, the process can take up to an hour to complete.)

Delete a Bundle

For any site that uses Storefront Next and Managed Runtime, you can delete only non-deployed bundles from a project.

1. In the project's overview page, click an environment.
2. Select one or more bundles that aren't currently deployed.
3. Click **Delete**.
4. When asked to confirm, click **Delete**.
5. Wait until the deletion is completed.

Deletions are handled asynchronously and can take time to process.

Edit Environment Settings

Access the environment settings in one of these ways:

- If you created the environment in Business Manager, go to **Administration > Sites > Storefronts**, click your storefront, and then next to the environment, click the caret dropdown and click **Edit**. Log in to Runtime Admin opens in a new tab and access Environment Settings.
- Otherwise, log in to [Runtime Admin](#) . From your project, click the environment, and then click **Environment Settings**.



- Change the deployment region.
- Enable or disable [Source Maps](#).
- Add, edit, or remove site IDs associated with an environment.

Note

Cookies are always enabled for Storefront Next and can't be disabled. See [Storage and Sessions](#).

To access the Environment Settings page for a storefront created in Business Manager:

1. In Business Manager, click App Launcher  and then select **Administration > Sites > Storefronts**, and then click your storefront.
2. In the storefront detail page, click the dropdown next to the environment, and then click **Edit**. You're redirected to the Environment Settings page in Managed Runtime.

To access the Environment Settings page in Runtime Admin:

1. Go to a project's Overview page.
2. Click the name of the environment whose settings you want to edit.
3. Click **Environment Settings** from the left navigation.

To make edits, click the **Edit** button next to either the **General** settings or the **Advanced** settings. After making your edits, click **Update** to save your changes or click **Cancel** to discard your changes.

Server-Side Rendering Architecture

Managed Runtime supports the ARM processor architecture for Server-Side Rendering (SSR) for Storefront Next. The ARM architecture represents the underlying compute infrastructure used to render your storefront.

ARM processors offer several advantages.

- **Enhanced Performance:** ARM architecture provides efficient processing capabilities optimized for modern web workloads.
- **Modern Infrastructure:** Built on the latest cloud computing technologies.



Redirects

Use a redirect to forward a request from one URL to another. Redirects can help avoid disruptions to the user experience caused by changes to your storefront. For example, consider a seasonal campaign page for spring. When the spring campaign ends and is replaced with a summer campaign, you can redirect from the spring URL to the summer URL.

Redirects is a powerful feature that can have significant security consequences on your storefront, including redirecting to malicious URLs or assets. Be careful when assigning roles to users that give them Redirect access.

Create a Redirect

✓ Tip

Before creating a redirect in a production environment, we recommend that you create it in a staging environment first.

Also create redirects using the [projects_target_redirect_create](#) API endpoint.

To create a redirect using Runtime Admin:

1. Go to a project's Overview page.
2. Click the name of the environment where you want to create the redirect.
3. Click **URL Redirects** from the left navigation.
4. Click **Create Redirect**.
5. In the **Redirect From** field, enter a relative URL path. For example, to redirect visitors from the URL `www.example.com/winter`, enter `/winter`.
6. In the **Redirect To** field, enter a relative URL path.
7. If needed, enable forwarding of query parameters and the wildcard path. (For more information, see [Forwarding Query Parameters](#).)
8. From the **Redirect Type** dropdown menu, select a redirect type based on the HTTP status code. (For more information, see [HTTP Status Codes](#).)



Paths

The value that you enter in the **Redirect From** field must always be a *relative* path. The **Redirect To** field can be either a relative path or a full URL. For example, to redirect visitors from `www.example.com/spring` to `www.example.com/summer`, set **Redirect From** to `/spring`. The **Redirect To** field can be either `/summer` or `www.example.com/summer`.

Wildcards

Add an asterisk (`*`) to the end of the **Redirect From** URL to indicate a wildcard. A wildcard matches any (0 or more) characters in the URL. For example, a redirect from `/a/*` would match `/a/`, `/a/b`, and `/a/b/c`.

A wildcard character can only be used at the end of the **Redirect From** URL.

Standard redirects are processed first by Managed Runtime, followed by redirects with wildcards.

HTTP Status Codes

Most redirects use the Permanent 301 status code, but you can also select Temporary 302. If you're unsure which HTTP status code to use, consult this [status code explainer](#) from MOZ.com.

Forwarding Query Parameters

Some requests contain query string parameters that you also want to include in the redirected request. For example, the relative path `/spring-landing-page` can be appended with a query string for analytics tracking, such as `/spring-landing-page?gclid=123`.

To enable query parameter forwarding, go to the **Forward** section of the form and select **Query Parameters**. Otherwise, query string parameters from the source URL aren't included in the redirect URL.

When both the **Redirect From** and **Redirect To** URLs have query strings and forwarding is enabled, the redirect URL combines both query strings. The query parameters from the **Redirect To** URL are appended to the query string in the request. For example, imagine your application receives a request for the relative path `/spring?year=2019`. If you've chosen to redirect `/spring` to `/summer?year=2020`, the redirect URL is `/summer?`



You can automatically include any path that comes after the wildcard portion of the **Redirect From** URL in the **Redirect To** URL. For example: if `/a/*` matches `/a/b/c` in the **Redirect From** URL, and the **Redirect To** URL is `/z/`, the redirect URL is `/z/b/c`.

To enable wildcard path forwarding, go to the **Forward** section of the form and select **Wildcard Path**.

Clone Redirects

✓ Tip

Always create redirects in a staging environment and clone them into production after testing.

Copy all the redirects from one environment to another using the clone redirects feature.

Also clone redirects using the [projects_target_redirect_clone_create](#) API endpoint.

To clone redirects using Runtime Admin:

1. Go to a project's Overview page.
2. Click the name of the environment that contains the redirects that you want to clone.
3. Click **URL Redirects** from the left navigation.
4. Click **Clone Redirects**. The **Clone Redirects** form appears. The current environment is listed under **From Environment** (the source).
5. Under **To Environment**, select the environment that you want to clone the redirects into (the destination).
6. Click **Clone n Redirects**. (Where n is the number of redirects to be cloned.)

⚠ Warning

When you clone redirects, you're replacing all the redirects in the destination environment with all the redirects from the source environment.

Edit a Redirect



Runtime Admin:

1. Go to a project's Overview page.
2. Click the name of the environment that contains the redirect that you want to edit.
3. Click **URL Redirects** from the left navigation.
4. Click the ellipsis button (...) next to the redirect.
5. Click **Edit**.
6. Update the settings.
7. Click **Update Redirect**.

Delete a Redirect

Delete a redirect using the [projects_target_redirect_destroy](#) API endpoint.

To delete a redirect using Runtime Admin:

1. Go to a project's Overview page.
2. Click the name of the environment that contains the redirect that you want to delete.
3. Click **URL Redirects** from the left navigation.
4. Click the ellipsis button (...) next to the redirect.
5. Click **Delete**.
6. Click **Yes, Delete Redirect**.

Troubleshooting Redirects

If a redirect isn't working as expected, try these troubleshooting steps:

- [Clear your browser cache](#)  because redirects are cached.
- Verify that you're viewing the settings for the correct environment.
- Edit the redirect and verify that the correct values are entered in the **Redirect From** and **Redirect To** fields.

Technical Limitations with Redirects

Redirects have the following technical limitations:

- Each environment can have a maximum of 10,000 redirects.



complex redirects with conditionals, use Express.js' [redirects support](#) in `ssr.js`.


- Redirects created with the Runtime Admin tool or the Managed Runtime API don't run on local development environments.
- Redirects aren't triggered by page transitions in the Storefront Next app. They can only be triggered by an HTTP request.
- To load a redirect in the context of a storefront, use the managed endpoint `/mobify/redirect/$path`.

Users

Add a User

To add a user to a project:

1. Go to a project's Overview page.
2. Click **Users & Permissions** from the left navigation.
3. Click **New User**.
4. Enter the user's email address. (Make sure that the user is part of your organization and has one of the following roles in Account Manager: **Managed Runtime User** or **Managed Runtime Admin**.)
5. Select a role.
6. Click **Add User**.



Change a User's Role

To change a user's role:

1. Go to a project's Overview page.
2. Click **Users & Permissions** from the left navigation.
3. Click the ... button next to the user's name.
4. Click **Edit**.
5. Select a role.
6. Click the popup menu that appears.
7. Select a new role.
8. Click **Save**.

[Try for free](#)

For a list of user abilities associated with each role, see the [Managed Runtime Overview](#).

Remove a User

To remove a user from a project:

1. Go to a project's Overview page.
2. Click **Users & Permissions** from the left navigation.
3. Click the ... button next to the user's name.
4. Click **Remove**.
5. Click **Yes, Remove User**.

**DID THIS ARTICLE
SOLVE YOUR ISSUE?**
Let us know so we can
improve!

[Share your feedback](#)

DEVELOPER CENTERS

[Heroku](#)
[MuleSoft](#)
[Tableau](#)
[Commerce Cloud](#)
[Lightning Design System](#)
[Einstein](#)
[Quip](#)

POPULAR RESOURCES

[Documentation](#)
[Component Library](#)
[APIs](#)
[Trailhead](#)
[Sample Apps](#)
[AppExchange](#)

COMMUNITY

[Trailblazer \(](#)
[Events and](#)
[Partner Cor](#)
[Blog](#)
[Salesforce /](#)
[Salesforce /](#)

© Copyright 2026 Salesforce, Inc. [All rights reserved](#). Various trademarks held by their respective owners.
Salesforce, Inc. Salesforce Tower, 415 Mission Street, 3rd Floor, San Francisco, CA 94105, United States

[Legal](#) [Terms of Service](#) [Privacy Information](#) [Responsible Disclosure](#) [Trust](#) [Contact](#)

[Use of Cookies](#) [Cookie Preferences](#)  [Your Privacy Choices](#)

