1. MEM

在树莓派上,使用Shell编程,输出以下内存信息:

时间	总量	剩余量	当前占用(%)	占用百分比动态平均值
2018-01-1215:00:28	1023M	200M	80.4%	60.8%

动态平均值=0.3动态平均值(上一次)+0.7当前占用比

在脚本编写过程中,可以参考以下内容:

```
awk '{printf("%s %s",$1,$2)}'
echo "scale=1;0.3*24+0.7*36" | bc
arry=(a c d e f)
arry=($1 $2)
free -m 查看内存占用
```

```
1 #!/bin/bash
2
3 time=`date +%Y-%m-%d__%H:%M:%S` # 当前时间
4 total=(`free -m | head -n 2 | tail -n 1 | awk '{printf $2" "$4}'`) # 总量 剩余量
5 current_occupancy=$[$[${total[0]}-${total[1]}]*100/${total[0]}] # 当前占用
6 dynamic=$(echo "scale=1;0.3*$1+0.7*$current_occupancy" | bc) # 占用百分比动态平均值
7
8 echo $time ${total[0]}M ${total[1]}M $current_occupancy% $dynamic%
```

2.DISK

- 1. 磁盘总量
- 2. 磁盘剩余量
- 3. 占用比例
 - 1. 各分区占用比例
 - 2. 各分区总量
 - 3. 分区剩余情况

输出格式: 2018-01-12_16:48:23 标识(0为整个磁盘,1为分区) 磁盘还是分区(disk| /boot , /) 磁盘/分区总量 磁盘/分区剩余量 占用比例

df 查看磁盘分区信息

```
#!/bin/bash
1
 2
 3
    time=`date +%Y-%m-%d__%H:%M:%S` # 时间
    information=(`df -T -x devtmpfs -m -x tmpfs | tail -n +2 | awk
    '{printf("a["NR"]=%s,%d,%d,%s ",$7,$3,$5,$6)}'`) # 磁盘分区信息
 5
   Total_memory=0 # 磁盘内存总量
   Available_memory=0 # 磁盘可用内存
    Occupancy_ratio=0 # 占用比例
 7
    ((num=${#information[@]}-1)) # 分区总数
9
    # 计算磁盘内存总量 磁盘可用内存 占用比例
10
11
    for i in `seq 0 $num`; do
        ((Total_memory=$Total_memory+`echo ${information[$i]} | cut -d "," -f 2`))
12
        ((Available_memory=$Available_memory+`echo ${information[$i]} | cut -d "," -f
13
    3`))
14
    done
15
    ((Occupancy_ratio=($Total_memory-$Available_memory)*100/$Total_memory))
16
17
18
   # 输出磁盘和分区信息
19
    echo "$time O disk $Total_memory $Available_memory $Occupancy_ratio%"
20
    for i in `seq 0 $num`; do
        echo "$time 1 `echo ${information[i]} | cut -d "=" -f 2 | tr "," " "`"
21
22
    done
```

3.系统运行概况

uname -a 查看系统全部信息

```
#!/bin/bash
 1
 2
   | time=`date +%Y-%m-%d__%H:%M:%S` # 时间
    system_information=(`uname -a | awk '{print $2" "$15" "$3}'`) # 系统信息
    up=`uptime -p | tr -d "," | tr " " "_"` # 运行时间
    load_average=`uptime | awk '{printf $8$9$10}'` # 平均负载
    information=(`df -m -x tmpfs | tail -n +2 | awk '{printf("%d,%d ",$2,$3 )}'`) # 磁盘
    分区信息
    total=(`free -m | grep Mem | awk '{printf $2" "$3}'`) # 内存总量 剩余量
    current_occupancy=$[${total[1]}*100/${total[0]}] # 当前内存占用比例
 9
    cpu_temperature=$[`cat /sys/class/thermal/thermal_zone0/temp`/1000] # cpu温度
10
    Alarm=(0 80 90 70 80 50 90) # 警报等级范围 (磁盘占比的两个界限 内存占比的两个界限 cup温度的两
11
    个界限)
    Percentage=($0ccupancy_ratio $current_occupancy $cpu_temperature) # 磁盘占用比例 内存占
12
    用比例 cup温度
13
    for i in `seq 0 $[${#information[@]}-1]`; do # $[${#information[@]}-1] 计算总分区数-1
14
```

```
((Total_memory=$Total_memory+`echo ${information[$i]} | cut -d "," -f 1`)) # 计算
    磁盘总量
16
        ((Occupied_memory=$0ccupied_memory+`echo ${information[$i]} | cut -d "," -f 2`))
    # 计算已用磁盘量
17
    ((Occupancy_ratio=$Occupied_memory*100/$Total_memory)) # 计算磁盘占用比例
18
19
   # 输出系统运行情况
20
   echo -e "$time ${system_information[0]} ${system_information[1]}
21
    ${system_information[2]} $up $load_average ${Total_memory}M $0ccupancy_ratio%
    ${total[0]}M $current_occupancy% $cpu_temperature""\c"
22
23
    for i in {0..2}; do # $i是Percentage数组的下标
        ((Alarm[0]=${Alarm[0]}+1)) # 通过Alarm[0]自加 遍历警报等级范围
24
        if [[ ${Percentage[$i]} -le ${Alarm[${Alarm[0]}]} ]]; then
25
            echo -e " normal""\c"
26
27
            ((Alarm[0]=${Alarm[0]}+1))
28
        elif ((Alarm[0]=${Alarm[0]}+1)) && [ ${Percentage[$i]} -le ${Alarm[$,{Alarm[0]}}}
    ]; then
            echo -e " note""\c"
29
30
        else
            echo -e " waring""\c"
31
32
        fi
33
   done
34
    echo
```