

Step 3: Download Filtered Scenes

Pull the scenes you kept — from Earth Engine (clipped, small) or the real archive (full files).

Downloads use two different mechanisms depending on where a product actually lives:

Source	Products	What you get
Earth Engine	Sentinel-2 L2A/L1C, Landsat 8/9, MODIS	Clipped to your AOI — small, no login needed
Real archive (CMR)	Sentinel-1, NISAR, Sentinel-6, HLS	Full original files — can be large, needs Earthdata login

One-time ASF DAAC authorization

The first time you download Sentinel-1 or NISAR data, ASF DAAC may reject your Earthdata credentials even though they're correct, until you authorize their specific application:

- 1 Go to `urs.earthdata.nasa.gov/profile/edit_applications` while logged in.
- 2 Under "Authorized Apps," search for and approve "**Alaska Satellite Facility Data Access**" (and similar ASF-related entries if prompted).
- 3 Retry the download — it should now authenticate successfully.

Before you click download

- Check the per-sensor size totals shown before downloading — **NISAR RSLC files run ~25 GB each**, by far the largest product this toolkit handles.
- You can select individual sensors to download rather than everything at once — skip the huge ones if you don't need them.
- Downloads resume safely: a file that's already completed is skipped, and an interrupted download never gets mistaken for a finished one on retry.

■■ **Watch out** — Your Earthdata password is only held in memory for the run — it is never written to disk or saved into a notebook file. You'll re-enter it each session.