MessageHandlingClass

5.3

Generated by Doxygen 1.8.14

Contents

1 Module Index **1**

1.1 Modules 1

2 Namespace Index **3**

2.1 Namespace List 3

3 Hierarchical Index **5**

3.1 Class Hierarchy 5

4 Data Structure Index **7**

4.1 Data Structures 7

5 File Index **9**

5.1 File List 9

6 Module Documentation **11**

6.1 Models 11

6.1.1 Detailed Description 11

6.2 Utils 12

6.2.1 Detailed Description 12

6.3 Message 13

6.3.1 Detailed Description 13

7 Namespace Documentation **15**

7.1 jeod Namespace Reference 15

7.1.1 Detailed Description 15

8 Data Structure Documentation 17

8.1 jeod::MessageHandler Class Reference . . . 17

8.1.1 Detailed Description . . . 20

8.1.2 Constructor & Destructor Documentation . . . 20

8.1.2.1 MessageHandler() [1/2] . . . 20

8.1.2.2 ~MessageHandler() . . . 21

8.1.2.3 MessageHandler() [2/2] . . . 21

8.1.3 Member Function Documentation . . . 21

8.1.3.1 add_suppressed_code() . . . 21

8.1.3.2 clear_suppressed_codes() . . . 21

8.1.3.3 debug() . . . 22

8.1.3.4 delete_suppressed_code() . . . 22

8.1.3.5 deregister_contents() . . . 22

8.1.3.6 error() . . . 23

8.1.3.7 fail() . . . 23

8.1.3.8 get_suppress_id() . . . 25

8.1.3.9 get_suppress_location() . . . 25

8.1.3.10 get_suppression_level() . . . 26

8.1.3.11 inform() . . . 26

8.1.3.12 no_handler_error() . . . 26

8.1.3.13 operator=() . . . 27

8.1.3.14 process_add_suppressed_code() . . . 27

8.1.3.15 process_clear_suppressed_codes() . . . 28

8.1.3.16 process_delete_suppressed_code() . . . 28

8.1.3.17 process_message() . . . 28

8.1.3.18 register_contents() . . . 29

8.1.3.19 send_message() . . . 29

8.1.3.20 set_mode() . . . 30

8.1.3.21 set_mode_internal() . . . 30

8.1.3.22 set_suppress_id() . . . 31

8.1.3.23 set_suppress_location() . . . 31
8.1.3.24 set_suppression_level() . . . 31
8.1.3.25 va_send_message() . . . 32
8.1.3.26 warn() . . . 32
8.1.4 Friends And Related Function Documentation . . . 33
8.1.4.1 init_attrjeod__MessageHandler . . . 33
8.1.4.2 InputProcessor . . . 33
8.1.5 Field Documentation . . . 33
8.1.5.1 Debug . . . 33
8.1.5.2 Error . . . 34
8.1.5.3 Failure . . . 34
8.1.5.4 handler . . . 34
8.1.5.5 mode . . . 35
8.1.5.6 Notice . . . 35
8.1.5.7 suppress_id . . . 35
8.1.5.8 suppress_location . . . 35
8.1.5.9 suppression_level . . . 36
8.1.5.10 Warning . . . 36
8.2 jeod::MessageMessages Class Reference . . . 36
8.2.1 Detailed Description . . . 37
8.2.2 Constructor & Destructor Documentation . . . 37
8.2.2.1 MessageMessages() [1/2] . . . 37
8.2.2.2 MessageMessages() [2/2] . . . 37
8.2.3 Member Function Documentation . . . 37
8.2.3.1 operator=() . . . 37
8.2.4 Field Documentation . . . 37
8.2.4.1 singleton_error . . . 38
8.3 jeod::SuppressedCodeMessageHandler Class Reference . . . 38
8.3.1 Detailed Description . . . 39
8.3.2 Constructor & Destructor Documentation . . . 39

8.3.2.1 SuppressedCodeMessageHandler() [1/2] . . . 39
8.3.2.2 ~SuppressedCodeMessageHandler() . . . 39
8.3.2.3 SuppressedCodeMessageHandler() [2/2] . . . 39
8.3.3 Member Function Documentation . . . 39
8.3.3.1 deregister_contents() . . . 40
8.3.3.2 message_is_to_be_printed() . . . 40
8.3.3.3 operator=() . . . 40
8.3.3.4 process_add_suppressed_code() . . . 40
8.3.3.5 process_clear_suppressed_code() . . . 41
8.3.3.6 process_delete_suppressed_code() . . . 41
8.3.3.7 register_contents() . . . 41
8.3.4 Friends And Related Function Documentation . . . 42
8.3.4.1 init_attrjeod__SuppressedCodeMessageHandler . . . 42
8.3.4.2 InputProcessor . . . 42
8.3.5 Field Documentation . . . 42
8.3.5.1 suppressed_codes . . . 42

9 File Documentation **43**

9.1 class_declarations.hh File Reference . . . 43
9.1.1 Detailed Description . . . 43
9.2 make_message_code.hh File Reference . . . 43
9.2.1 Detailed Description . . . 44
9.2.2 Macro Definition Documentation . . . 44
9.2.2.1 JEOD_MAKE_MESSAGE_CODE . . . 44
9.3 message_handler.cc File Reference . . . 44
9.3.1 Detailed Description . . . 44
9.4 message_handler.hh File Reference . . . 45
9.4.1 Detailed Description . . . 45
9.5 message_messages.cc File Reference . . . 45
9.5.1 Detailed Description . . . 45
9.5.2 Macro Definition Documentation . . . 46
9.5.2.1 MAKE_MESSAGE_MESSAGE_CODE . . . 46
9.6 message_messages.hh File Reference . . . 46
9.6.1 Detailed Description . . . 46
9.7 suppressed_code_message_handler.cc File Reference . . . 46
9.7.1 Detailed Description . . . 47
9.8 suppressed_code_message_handler.hh File Reference . . . 47
9.8.1 Detailed Description . . . 47

Index **49**

Chapter 1

Module Index

1.1 Modules

Here is a list of all modules:

Models 11
Utils 12
Message 13

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

jeod
Namespace jeod 15

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

jeod::MessageHandler 17
jeod::SuppressedCodeMessageHandler 38
jeod::MessageMessages 36

Chapter 4

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::MessageHandler
: The base class for generating JEOD messages 17

jeod::MessageMessages
: Specifies the message IDs used in the message handler model 36

jeod::SuppressedCodeMessageHandler
: Adds the capability to suppress messages by their message code to the base MessageHandler class 38

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

class_declarations.hh
Forward declarations of classes defined in this module . . . 43
make_message_code.hh
Define JEOD_MAKE_MESSAGE_CODE . . . 43
message_handler.cc
Define member functions for the class MessageHandler . . . 44
message_handler.hh
Define the class MessageHandler, the base class for generating messages . . . 45
message_messages.cc
Implement the class MessageMessages . . . 45
message_messages.hh
Define the class MessageMessages . . . 46
suppressed_code_message_handler.cc
Define member functions for the class SuppressedCodeMessageHandler . . . 46
suppressed_code_message_handler.hh
Define the class SuppressedCodeMessageHandler, which adds the capability to suppress messages by their message code . . . 47

Chapter 6

Module Documentation

6.1 Models

Modules

- Utils

6.1.1 Detailed Description

6.2 Utils

Modules

- Message

6.2.1 Detailed Description

6.3 Message

Files

- file class_declarations.hh

  Forward declarations of classes defined in this module.
- file make_message_code.hh

  Define JEOD_MAKE_MESSAGE_CODE.
- file message_handler.hh

  Define the class MessageHandler, the base class for generating messages.
- file message_messages.hh

  Define the class MessageMessages.
- file suppressed_code_message_handler.hh

  Define the class SuppressedCodeMessageHandler, which adds the capability to suppress messages by their message code.
- file message_handler.cc

  Define member functions for the class MessageHandler.
- file message_messages.cc

  Implement the class MessageMessages.
- file suppressed_code_message_handler.cc

  Define member functions for the class SuppressedCodeMessageHandler.

Namespaces

- jeod

  Namespace jeod.

6.3.1 Detailed Description

Chapter 7

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

- class MessageHandler

  The base class for generating JEOD messages.
- class MessageMessages

  Specifies the message IDs used in the message handler model.
- class SuppressedCodeMessageHandler

  Adds the capability to suppress messages by their message code to the base MessageHandler class.

7.1.1 Detailed Description

Namespace jeod.

Chapter 8

Data Structure Documentation

8.1 jeod::MessageHandler Class Reference

The base class for generating JEOD messages.

`#include <message_handler.hh>`

Inheritance diagram for jeod::MessageHandler:



Public Member Functions

- MessageHandler ()

  Construct a MessageHandler.
- virtual ~MessageHandler ()

  Destruct a MessageHandler.
- MessageHandler (const MessageHandler &)=delete
- MessageHandler & operator= (const MessageHandler &)=delete
- virtual void register_contents ()

  Register the checkpointable contents of the handler with the simulation interface.
- virtual void deregister_contents ()

  Deregister the checkpointable contents of the handler with the simulation interface.

Static Public Member Functions

- static void fail (const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generate a message with negative severity, MessageHandler::Failure, and terminate the simulation.
- static void error (const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generate a message with severity MessageHandler::Error.
- static void warn (const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generate a message with severity MessageHandler::Warning.
- static void inform (const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generates a message with severity MessageHandler::Notice.
- static void debug (const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generate a message with severity MessageHandler::Debug.
- static void send_message (int severity, const char *prefix, const char *file, unsigned int line, const char *msg_code, const char *format,...)

  Generic variable arguments message interface.
- static void va_send_message (int severity, const char *prefix, const char *file, unsigned int line, const char *msg_code, const char *format, va_list args)

  Generic variable arguments message interface.
- static void set_suppression_level (unsigned int suppression_level)

  Set the suppression level in the global message handler.
- static unsigned int get_suppression_level ()

  Get the suppress_id of the global massage handler.
- static void add_suppressed_code (const char *msg_code)

  Add a message code to the set of messages that are to be suppressed for messages with positive severity level.
- static void delete_suppressed_code (const char *msg_code)

  Delete a message code from the set of suppressed message codes.
- static void clear_suppressed_codes ()

  Clear the set of suppressed message codes.
- static void set_suppress_id (bool suppress_id)

  Set the suppress_id flag in the global message handler.
- static bool get_suppress_id ()

  Get the suppress_id of the global massage handler.
- static void set_suppress_location (bool suppress_location)

  Set the suppress_location in the global message handler.
- static bool get_suppress_location ()

  Get the suppress_location of the global massage handler.
- static void set_mode (JeodSimulationInterface::Mode new_mode)

  Set the message handler's simulation interface mode.

Static Public Attributes

- static const int Failure = -1

  The severity value passed by the static public MessageHandler::fail method to the derived class process_message method.
- static const int Error = 0

  The severity value passed by the static public MessageHandler::error method to the derived class process_message method.
- static const int Warning = 9

  The severity value passed by the static public MessageHandler::warn method to the derived class process_message method.
- static const int Notice = 99

  The severity value passed by the static public MessageHandler::inform method to the derived class process_message method.
- static const int Debug = 999

  The severity value passed by the static public MessageHandler::debug method to the derived class process_message method.

Protected Member Functions

- virtual void process_message (int severity, const char *prefix, const char *file, unsigned int line, const char *msg_code, const char *format, va_list args) const =0

  Generate the message.
- virtual void process_add_suppressed_code (const char *msg_code)

  Add a message code to the set of messages that are to be suppressed.
- virtual void process_delete_suppressed_code (const char *msg_code)

  Delete a message code from the set of suppressed message codes.
- virtual void process_clear_suppressed_codes ()

  Clear the set of suppressed message codes.

Static Protected Member Functions

- static void no_handler_error ()

  Handle the error condition where there is no global handler.

Protected Attributes

- unsigned int suppression_level

  All messages have an associated severity level, with increasingly positive values indicating warnings of decreasing severity.
- bool suppress_id {}

  This flag indicates whether the message ID is printed for unsuppressed messages.
- bool suppress_location {}

  This flag indicates whether the message source file and line number printed for unsuppressed messages.

Static Protected Attributes

- static MessageHandler * handler = nullptr

  The MessageHandler instance that generates messages.

Private Member Functions

- void set_mode_internal (JeodSimulationInterface::Mode new_mode)

  Set the mode and perform mode transitions.

Private Attributes

- JeodSimulationInterface::Mode mode

  Simulation interface mode.

Friends

- class InputProcessor
- void init_attrjeod__MessageHandler ()

8.1.1 Detailed Description

The base class for generating JEOD messages.

This class provides:

- A suite of public static message generation and message control functions. The message generation functions provide the mechanism to generate and present messages of various levels of severity to the simulation user. The message control functions provide the user the ability to control which messages will be presented and to control their presentation.
- A set of defined constants that denote the severity levels used by JEOD.
  - Failure (-1): Any negative severity level value indicates an irrecoverable error. The simulation will terminate immediately.
  - Error (0): Errors almost certainly invalidate the simulation output. All severity zero messages are printed; they cannot be disabled. The difference between failures and errors is that there is some recovery from an error that lets the simulation limp on and find the next error.
  - Warning (9): Warnings represent conditions that a model deems to be suspect but not necessarily dangerous. Warning messages are printed by default, but they can be disabled.
  - Notice (99): Notices represent condiitions that a model deems to be suspicious, but not necessarily in error. Notifications are not printed by default, but they can be enabled.
  - Debug (999): Debug messages typically demonstrate progress of some sort. Enabling them may well result in spew.
- A public default constructor and destructor. The constructor ensures that the created object is indeed a singleton.
-

Definition at line 107 of file message_handler.hh.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 MessageHandler() [1/2]

```
jeod::MessageHandler::MessageHandler ( )
```

Construct a MessageHandler.

This default constructor sets the suppression level to MessageHandler::Warning, which means that messages of that severity and lower will be printed. The suppress_id and suppress_location flags are set to false; auxiliary information is not suppressed.

Definition at line 538 of file message_handler.cc.

References error(), handler, and jeod::MessageMessages::singleton_error.

8.1.2.2 ~MessageHandler()

```
jeod::MessageHandler::~MessageHandler ( )  [virtual]
```

Destruct a MessageHandler.

Definition at line 561 of file message_handler.cc.

References handler.

8.1.2.3 MessageHandler() [2/2]

```
jeod::MessageHandler::MessageHandler (
            const MessageHandler &  )  [delete]
```

8.1.3 Member Function Documentation

8.1.3.1 add_suppressed_code()

```
void jeod::MessageHandler::add_suppressed_code (
            const char * msg_code )  [static]
```

Add a message code to the set of messages that are to be suppressed for messages with positive severity level.

Note: Fatal errors and serious errors cannot be suppressed.

Parameters

in	*msg_code*	Message code to be suppressed

Definition at line 338 of file message_handler.cc.

References handler, no_handler_error(), and process_add_suppressed_code().

8.1.3.2 clear_suppressed_codes()

```
void jeod::MessageHandler::clear_suppressed_codes ( )  [static]
```

Clear the set of suppressed message codes.

Definition at line 377 of file message_handler.cc.

References handler, no_handler_error(), and process_clear_suppressed_codes().

8.1.3.3 debug()

```
void jeod::MessageHandler::debug (
             const char * file,
             unsigned int line,
             const char * msg_code,
             const char * format,
              ... ) [static]
```

Generate a message with severity MessageHandler::Debug.

Debug messages should never be used for erroneous conditions. They should instead be used for describing nominal behavior. Note that debug messages are nominally suppressed.

Parameters

in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	*...*	sprintf arguments

Definition at line 199 of file message_handler.cc.

References Debug, handler, no_handler_error(), and process_message().

8.1.3.4 delete_suppressed_code()

```
void jeod::MessageHandler::delete_suppressed_code (
             const char * msg_code ) [static]
```

Delete a message code from the set of suppressed message codes.

Parameters

in	*msg_code*	Message code to be unsuppressed

Definition at line 358 of file message_handler.cc.

References handler, no_handler_error(), and process_delete_suppressed_code().

8.1.3.5 deregister_contents()

```
virtual void jeod::MessageHandler::deregister_contents ( ) [inline], [virtual]
```

Deregister the checkpointable contents of the handler with the simulation interface.

The base MessageHandler has not such content.

Reimplemented in jeod::SuppressedCodeMessageHandler.

Definition at line 216 of file message_handler.hh.

8.1.3.6 error()

```
void jeod::MessageHandler::error (
             const char * file,
             unsigned int line,
             const char * msg_code,
             const char * format,
              ... ) [static]
```

Generate a message with severity MessageHandler::Error.

An error represents a very serious problem. The intent is to represent errors that invalidate simulation results but for which a recovery path does exist. Using MessageHandler::error rather than MessageHandler::fail enables the user to address multiple errors at a time.

A conforming implementation of a class that derives MessageHandler will always report error messages. Errors should not be suppressed.

Parameters

in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	...	sprintf arguments

Definition at line 112 of file message_handler.cc.

References Error, handler, no_handler_error(), and process_message().

Referenced by MessageHandler().

8.1.3.7 fail()

```
void jeod::MessageHandler::fail (
             const char * file,
             unsigned int line,
             const char * msg_code,
             const char * format,
              ... ) [static]
```

Generate a message with negative severity, MessageHandler::Failure, and terminate the simulation.

The intent of this method is to handle erroneous situations for which no recovery path exists. If a recovery path does exist, even if very suspect, callers of this method should consider calling MessageHandler::error as an alternative.

A conforming implementation of a class that derives MessageHandler will force the simulation to terminate upon receipt of a message with negative severity.

Parameters

in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	*...*	sprintf arguments

Definition at line 78 of file message_handler.cc.

References Failure, handler, no_handler_error(), and process_message().

8.1.3.8 get_suppress_id()

```
bool jeod::MessageHandler::get_suppress_id ( )  [static]
```

Get the suppress_id of the global massage handler.

Returns

ID value
Units: Suppress

Definition at line 415 of file message_handler.cc.

References handler, no_handler_error(), and suppress_id.

8.1.3.9 get_suppress_location()

```
bool jeod::MessageHandler::get_suppress_location ( )  [static]
```

Get the suppress_location of the global massage handler.

Returns

Suppress location value

Definition at line 457 of file message_handler.cc.

References handler, no_handler_error(), and suppress_location.

8.1.3.10 get_suppression_level()

```
unsigned int jeod::MessageHandler::get_suppression_level ( )  [static]
```

Get the suppress_id of the global massage handler.

Returns

Suppression level value

Definition at line 312 of file message_handler.cc.

References handler, no_handler_error(), and suppression_level.

8.1.3.11 inform()

```
void jeod::MessageHandler::inform (
            const char * file,
            unsigned int line,
            const char * msg_code,
            const char * format,
             ... )  [static]
```

Generates a message with severity MessageHandler::Notice.

Informational notices should not represent problems of any significance as the default behavior is to suppress such messages.

Parameters

in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	...	sprintf arguments

Definition at line 170 of file message_handler.cc.

References handler, no_handler_error(), Notice, and process_message().

8.1.3.12 no_handler_error()

```
void jeod::MessageHandler::no_handler_error ( )  [static], [protected]
```

Handle the error condition where there is no global handler.

Note

That this condition exists means the simulation is non-compliant.

Assumptions and Limitations

- All JEOD-based simulations must have a message handler and memory handler that at instantiated prior to instantiating any other JEOD-based model and destroyed after all those other models have been destroyed.
- That no message handler exists means the simulation is not a compliant with the above restrictions.
- The handling of this condition is intentionally simplistic. An error message is printed and the simulation is terminated via a system call to exit.

Definition at line 523 of file message_handler.cc.

Referenced by add_suppressed_code(), clear_suppressed_codes(), debug(), delete_suppressed_code(), error(), fail(), get_suppress_id(), get_suppress_location(), get_suppression_level(), inform(), send_message(), set_mode(), set_suppress_id(), set_suppress_location(), set_suppression_level(), va_send_message(), and warn().

8.1.3.13 operator=()

```
MessageHandler& jeod::MessageHandler::operator= (
            const MessageHandler &  )  [delete]
```

8.1.3.14 process_add_suppressed_code()

```
virtual void jeod::MessageHandler::process_add_suppressed_code (
            const char * msg_code )  [inline], [protected], [virtual]
```

Add a message code to the set of messages that are to be suppressed.

The method add_suppressed_code relays the call to the message handler as a call to process_add_suppressed↩_code.

The default behavior is a no-op. Suppressing messages by the message code is an optional capability.

Parameters

msg_code	Message code to be suppressed

Reimplemented in jeod::SuppressedCodeMessageHandler.

Definition at line 311 of file message_handler.hh.

Referenced by add_suppressed_code().

8.1.3.15 process_clear_suppressed_codes()

```
virtual void jeod::MessageHandler::process_clear_suppressed_codes ( )  [inline], [protected],
[virtual]
```

Clear the set of suppressed message codes.

The method clear_suppressed_codes relays the call to the message handler as a call to process_clear_↩ suppressed_codes.

As with process_add_suppressed_code, the default for this function is a no-op; suppressed codes are an optional capability.

Definition at line 333 of file message_handler.hh.

Referenced by clear_suppressed_codes().

8.1.3.16 process_delete_suppressed_code()

```
virtual void jeod::MessageHandler::process_delete_suppressed_code (
            const char * msg_code )  [inline], [protected], [virtual]
```

Delete a message code from the set of suppressed message codes.

The method delete_suppressed_code relays the call to the message handler as a call to process_delete_↩ suppressed_code.

As with process_add_suppressed_code, the default for this function is a no-op; suppressed codes are an optional capability.

Parameters

msg_code	Message code to be suppressed

Reimplemented in jeod::SuppressedCodeMessageHandler.

Definition at line 323 of file message_handler.hh.

Referenced by delete_suppressed_code().

8.1.3.17 process_message()

```
virtual void jeod::MessageHandler::process_message (
            int severity,
            const char * prefix,
            const char * file,
            unsigned int line,
            const char * msg_code,
```

```
            const char * format,
            va_list args ) const  [protected], [pure virtual]
```

Generate the message.

All of the send_message() methods relay the message to the message handler in the form of a call to process_message().

An instantiable derived MessageHandler class must supply this function.

Parameters

severity	Severity level
prefix	Message prefix (e.g., Error)
file	Typically **FILE**
line	Typically **LINE**
msg_code	Message code
format	sprintf format
args	Arguments

Referenced by debug(), error(), fail(), inform(), send_message(), va_send_message(), and warn().

8.1.3.18 register_contents()

```
virtual void jeod::MessageHandler::register_contents ( )  [inline], [virtual]
```

Register the checkpointable contents of the handler with the simulation interface.

The base MessageHandler has not such content.

Reimplemented in jeod::SuppressedCodeMessageHandler.

Definition at line 209 of file message_handler.hh.

8.1.3.19 send_message()

```
void jeod::MessageHandler::send_message (
            int severity,
            const char * prefix,
            const char * file,
            unsigned int line,
            const char * msg_code,
            const char * format,
             ... ) [static]
```

Generic variable arguments message interface.

This method gives the caller control over the severity level and over the message prefix. These are automatically generated in the standard set of MessageHandler interface methods.

Parameters

in	*severity*	Severity level
in	*prefix*	Message prefix (e.g., Error)
in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	*...*	sprintf arguments

Definition at line 230 of file message_handler.cc.

References handler, no_handler_error(), and process_message().

8.1.3.20 set_mode()

```
void jeod::MessageHandler::set_mode (
             JeodSimulationInterface::Mode new_mode )  [static]
```

Set the message handler's simulation interface mode.

Assumptions and Limitations

- This method must not be called before the singleton message handler has been created or after it has been destroyed. A fatal error results when this is not true.

Parameters

in	*new_mode*	New mode

Definition at line 485 of file message_handler.cc.

References handler, no_handler_error(), and set_mode_internal().

8.1.3.21 set_mode_internal()

```
void jeod::MessageHandler::set_mode_internal (
             JeodSimulationInterface::Mode new_mode )  [private]
```

Set the mode and perform mode transitions.

Parameters

in	*new_mode*	New mode

Definition at line 504 of file message_handler.cc.

References mode.

Referenced by set_mode().

8.1.3.22 set_suppress_id()

```
void jeod::MessageHandler::set_suppress_id (
             bool suppress_id )  [static]
```

Set the suppress_id flag in the global message handler.

Parameters

in	*suppress_id*	New suppress id value

Definition at line 396 of file message_handler.cc.

References handler, no_handler_error(), and suppress_id.

8.1.3.23 set_suppress_location()

```
void jeod::MessageHandler::set_suppress_location (
             bool suppress_location )  [static]
```

Set the suppress_location in the global message handler.

Parameters

in	*suppress_location*	New suppress_loc value

Definition at line 438 of file message_handler.cc.

References handler, no_handler_error(), and suppress_location.

8.1.3.24 set_suppression_level()

```
void jeod::MessageHandler::set_suppression_level (
             unsigned int suppression_level )  [static]
```

Set the suppression level in the global message handler.

Parameters

in	*suppression_level*	New suppression level

Definition at line 293 of file message_handler.cc.

References handler, no_handler_error(), and suppression_level.

8.1.3.25 va_send_message()

```
void jeod::MessageHandler::va_send_message (
            int severity,
            const char * prefix,
            const char * file,
            unsigned int line,
            const char * msg_code,
            const char * format,
            va_list args )  [static]
```

Generic variable arguments message interface.

This method behaves similarly to MessageHandler::send_message except that the caller has already captured the variable arguments in the form of a va_list. Note that MessageHandler::va_send_message does not call va_end macro.

Parameters

in	*severity*	Severity level
in	*prefix*	Message prefix (e.g., Error)
in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in,out	*args*	Varargs stack

Definition at line 268 of file message_handler.cc.

References handler, no_handler_error(), and process_message().

8.1.3.26 warn()

```
void jeod::MessageHandler::warn (
            const char * file,
            unsigned int line,
            const char * msg_code,
            const char * format,
             ... )  [static]
```

Generate a message with severity MessageHandler::Warning.

Warnings represent situations where the model developer had to make some assumptions to recover from what would otherwise be an erroneous condition. The recovery based on those assumptions does not necessarily invalidate invalidate the simulation results.

Parameters

in	*file*	Typically **FILE**
in	*line*	Typically **LINE**
in	*msg_code*	Message code
in	*format*	sprintf format
in	...	sprintf arguments

Definition at line 142 of file message_handler.cc.

References handler, no_handler_error(), process_message(), and Warning.

8.1.4 Friends And Related Function Documentation

8.1.4.1 init_attrjeod__MessageHandler

```
void init_attrjeod__MessageHandler ( )  [friend]
```

8.1.4.2 InputProcessor

```
friend class InputProcessor  [friend]
```

Definition at line 109 of file message_handler.hh.

8.1.5 Field Documentation

8.1.5.1 Debug

```
const int jeod::MessageHandler::Debug = 999  [static]
```

The severity value passed by the static public MessageHandler::debug method to the derived class process_↩ message method.

This is set to 999 in the implementation. The intent is to summarize to the user of some event that the user requested did indeed transpire. Ideally, JEOD code, particularly initialization code, will be peppered with calls to MessageHandler::debug.trick_io(∗o) trick_units(–)

Definition at line 267 of file message_handler.hh.

Referenced by debug().

8.1.5.2 Error

```
const int jeod::MessageHandler::Error = 0  [static]
```

The severity value passed by the static public MessageHandler::error method to the derived class process_message method.

This is set to 0 in the implementation, representing the most severe non-fatal error.

Non-negative severity levels indicate non-fatal conditions for which messages might nonetheless need to be generated, depending on the value of the user-settable suppression_level.trick_io(∗o) trick_units(–)

Definition at line 241 of file message_handler.hh.

Referenced by error().

8.1.5.3 Failure

```
const int jeod::MessageHandler::Failure = -1  [static]
```

The severity value passed by the static public MessageHandler::fail method to the derived class process_message method.

This is set to -1 in the implementation, representing a fatal error.

A valid implementation of the process_message method must treat negative severity levels as fatal; they must not return to the calling procedure. In other words, failures eventually result in a call to exit.trick_io(∗o) trick_units(–)

Definition at line 229 of file message_handler.hh.

Referenced by fail().

8.1.5.4 handler

```
MessageHandler * jeod::MessageHandler::handler = nullptr  [static], [protected]
```

The MessageHandler instance that generates messages.

The static MessageHandler functions invoked by various models pass the message on to this instance in the form of a call to process_message.trick_io(∗o) trick_units(–)

Definition at line 342 of file message_handler.hh.

Referenced by add_suppressed_code(), clear_suppressed_codes(), debug(), delete_suppressed_code(), error(), fail(), get_suppress_id(), get_suppress_location(), get_suppression_level(), inform(), MessageHandler(), send_message(), set_mode(), set_suppress_id(), set_suppress_location(), set_suppression_level(), va_send_↩message(), warn(), and ∼MessageHandler().

8.1.5.5 mode

```
JeodSimulationInterface::Mode jeod::MessageHandler::mode  [private]
```

Simulation interface mode.

trick_units(–)

Definition at line 376 of file message_handler.hh.

Referenced by set_mode_internal().

8.1.5.6 Notice

```
const int jeod::MessageHandler::Notice = 99  [static]
```

The severity value passed by the static public MessageHandler::inform method to the derived class process_↩ message method.

This is set to 99 in the implementation. The intent is to indicate a non-error condition that might be worthy of a user notification.trick_io(∗o) trick_units(–)

Definition at line 257 of file message_handler.hh.

Referenced by inform().

8.1.5.7 suppress_id

```
bool jeod::MessageHandler::suppress_id {}  [protected]
```

This flag indicates whether the message ID is printed for unsuppressed messages.

The ID is not printed if this flag is set to true. The message ID is always printed for fatal errors.trick_units(–)

Definition at line 362 of file message_handler.hh.

Referenced by get_suppress_id(), and set_suppress_id().

8.1.5.8 suppress_location

```
bool jeod::MessageHandler::suppress_location {}  [protected]
```

This flag indicates whether the message source file and line number printed for unsuppressed messages.

The location is not printed if this flag is set to true. The message location is always printed for fatal errors.trick_↩ units(–)

Definition at line 370 of file message_handler.hh.

Referenced by get_suppress_location(), and set_suppress_location().

8.1.5.9 suppression_level

```
unsigned int jeod::MessageHandler::suppression_level  [protected]
```

All messages have an associated severity level, with increasingly positive values indicating warnings of decreasing severity.

Fatal errors have a negative severity level. Messages whose severity exceeds the value of the global message handler's suppression_level are suppressed. Note that fatal errors and severe errors cannot be suppressed.

Default value: MessageHandler::Warning (warnings and non-fatal errors).trick_units(–)

Definition at line 355 of file message_handler.hh.

Referenced by get_suppression_level(), and set_suppression_level().

8.1.5.10 Warning

```
const int jeod::MessageHandler::Warning = 9  [static]
```

The severity value passed by the static public MessageHandler::warn method to the derived class process_message method.

This is set to 9 in the implementation. The intent is to indicate a condition that might indicate that results are suspect.trick_io(∗o) trick_units(–)

Definition at line 249 of file message_handler.hh.

Referenced by warn().

The documentation for this class was generated from the following files:

- message_handler.hh
- message_handler.cc

8.2 jeod::MessageMessages Class Reference

Specifies the message IDs used in the message handler model.

```
#include <message_messages.hh>
```

Public Member Functions

- MessageMessages ()=delete
- MessageMessages (const MessageMessages &)=delete
- MessageMessages & operator= (const MessageMessages &)=delete

Static Public Attributes

- static const char * singleton_error = "utils/message/" "singleton_error"

  Error issued when multiple instance of a class that should be a singleton are created or when no such instance exists (but should).

8.2.1 Detailed Description

Specifies the message IDs used in the message handler model.

Definition at line 71 of file message_messages.hh.

8.2.2 Constructor & Destructor Documentation

8.2.2.1 MessageMessages() [1/2]

```
jeod::MessageMessages::MessageMessages ( )  [delete]
```

8.2.2.2 MessageMessages() [2/2]

```
jeod::MessageMessages::MessageMessages (
            const MessageMessages &  )  [delete]
```

8.2.3 Member Function Documentation

8.2.3.1 operator=()

```
MessageMessages& jeod::MessageMessages::operator= (
            const MessageMessages &  )  [delete]
```

8.2.4 Field Documentation

8.2.4.1 singleton_error

```
char const * jeod::MessageMessages::singleton_error = "utils/message/" "singleton_error"  [static]
```

Error issued when multiple instance of a class that should be a singleton are created or when no such instance exists (but should).

trick_units(–)

Definition at line 79 of file message_messages.hh.

Referenced by jeod::MessageHandler::MessageHandler().

The documentation for this class was generated from the following files:

- message_messages.hh
- message_messages.cc

8.3 jeod::SuppressedCodeMessageHandler Class Reference

Adds the capability to suppress messages by their message code to the base MessageHandler class.

```
#include <suppressed_code_message_handler.hh>
```

Inheritance diagram for jeod::SuppressedCodeMessageHandler:



Public Member Functions

- SuppressedCodeMessageHandler ()=default
- ~SuppressedCodeMessageHandler () override=default
- SuppressedCodeMessageHandler (const SuppressedCodeMessageHandler &)=delete
- SuppressedCodeMessageHandler & operator= (const SuppressedCodeMessageHandler &)=delete

Protected Member Functions

- void register_contents () override

  Register the MessageHandler's checkpointable contents.
- void deregister_contents () override

  Deregister the MessageHandler's checkpointable contents.
- void process_add_suppressed_code (const char *msg_code) override

  Add a message code to the set of messages that are to be suppressed.
- void process_delete_suppressed_code (const char *msg_code) override

  Delete a message code from the set of suppressed message codes.
- virtual void process_clear_suppressed_code ()

  Clear the set of messages that are to be suppressed.
- bool message_is_to_be_printed (int severity, const char *msg_code) const

  Determine whether output for a message is to be printed.

Protected Attributes

- JeodPrimitiveSet< std::string >::type suppressed_codes

  The set of message code that are to be suppressed.

Friends

- class InputProcessor
- void init_attrjeod__SuppressedCodeMessageHandler ()

Additional Inherited Members

8.3.1 Detailed Description

Adds the capability to suppress messages by their message code to the base MessageHandler class.

Definition at line 82 of file suppressed_code_message_handler.hh.

8.3.2 Constructor & Destructor Documentation

8.3.2.1 SuppressedCodeMessageHandler() [1/2]

```
jeod::SuppressedCodeMessageHandler::SuppressedCodeMessageHandler ( )  [default]
```

8.3.2.2 ~SuppressedCodeMessageHandler()

```
jeod::SuppressedCodeMessageHandler::~SuppressedCodeMessageHandler ( )  [override], [default]
```

8.3.2.3 SuppressedCodeMessageHandler() [2/2]

```
jeod::SuppressedCodeMessageHandler::SuppressedCodeMessageHandler (
            const SuppressedCodeMessageHandler &  )  [delete]
```

8.3.3 Member Function Documentation

8.3.3.1 deregister_contents()

```
void jeod::SuppressedCodeMessageHandler::deregister_contents ( )  [override], [protected],
[virtual]
```

Deregister the MessageHandler's checkpointable contents.

Reimplemented from jeod::MessageHandler.

Definition at line 55 of file suppressed_code_message_handler.cc.

References suppressed_codes.

8.3.3.2 message_is_to_be_printed()

```
bool jeod::SuppressedCodeMessageHandler::message_is_to_be_printed (
            int severity,
            const char * msg_code ) const  [inline], [protected]
```

Determine whether output for a message is to be printed.

Returns

True => print message

Parameters

in	*severity*	Severity level
in	*msg_code*	Message code

Definition at line 132 of file suppressed_code_message_handler.hh.

8.3.3.3 operator=()

```
SuppressedCodeMessageHandler& jeod::SuppressedCodeMessageHandler::operator= (
            const SuppressedCodeMessageHandler &  )  [delete]
```

8.3.3.4 process_add_suppressed_code()

```
void jeod::SuppressedCodeMessageHandler::process_add_suppressed_code (
            const char * msg_code )  [inline], [override], [protected], [virtual]
```

Add a message code to the set of messages that are to be suppressed.

Parameters

in	*msg_code*	Message code to be suppressed

Reimplemented from jeod::MessageHandler.

Definition at line 104 of file suppressed_code_message_handler.hh.

8.3.3.5 process_clear_suppressed_code()

```
virtual void jeod::SuppressedCodeMessageHandler::process_clear_suppressed_code ( )  [inline],
[protected], [virtual]
```

Clear the set of messages that are to be suppressed.

Definition at line 121 of file suppressed_code_message_handler.hh.

8.3.3.6 process_delete_suppressed_code()

```
void jeod::SuppressedCodeMessageHandler::process_delete_suppressed_code (
            const char * msg_code )  [inline], [override], [protected], [virtual]
```

Delete a message code from the set of suppressed message codes.

Parameters

in	*msg_code*	Message code to be unsuppressed

Reimplemented from jeod::MessageHandler.

Definition at line 113 of file suppressed_code_message_handler.hh.

8.3.3.7 register_contents()

```
void jeod::SuppressedCodeMessageHandler::register_contents ( )  [override], [protected], [virtual]
```

Register the MessageHandler's checkpointable contents.

Reimplemented from jeod::MessageHandler.

Definition at line 46 of file suppressed_code_message_handler.cc.

References suppressed_codes.

8.3.4 Friends And Related Function Documentation

8.3.4.1 init_attrjeod__SuppressedCodeMessageHandler

```
void init_attrjeod__SuppressedCodeMessageHandler ( )  [friend]
```

8.3.4.2 InputProcessor

```
friend class InputProcessor  [friend]
```

Definition at line 84 of file suppressed_code_message_handler.hh.

8.3.5 Field Documentation

8.3.5.1 suppressed_codes

```
JeodPrimitiveSet<std::string>::type jeod::SuppressedCodeMessageHandler::suppressed_codes
[protected]
```

The set of message code that are to be suppressed.

trick_io(**)

Definition at line 143 of file suppressed_code_message_handler.hh.

Referenced by deregister_contents(), and register_contents().

The documentation for this class was generated from the following files:

- suppressed_code_message_handler.hh
- suppressed_code_message_handler.cc

Chapter 9

File Documentation

9.1 class_declarations.hh File Reference

Forward declarations of classes defined in this module.

Namespaces

- jeod

  Namespace jeod.

9.1.1 Detailed Description

Forward declarations of classes defined in this module.

9.2 make_message_code.hh File Reference

Define JEOD_MAKE_MESSAGE_CODE.

Namespaces

- jeod

  Namespace jeod.

Macros

- #define JEOD_MAKE_MESSAGE_CODE(cname, path, id) char const * cname::id = path #id

  Shortcut macro to define the static member cname::id as the catenation of the path and the stringified id.

9.2.1 Detailed Description

Define JEOD_MAKE_MESSAGE_CODE.

9.2.2 Macro Definition Documentation

9.2.2.1 JEOD_MAKE_MESSAGE_CODE

```
#define JEOD_MAKE_MESSAGE_CODE(
              cname,
              path,
              id ) char const * cname::id = path #id
```

Shortcut macro to define the static member cname::id as the catenation of the path and the stringified id.

Parameters

in	*cname*	The name of the message class.
in	*path*	The path from $JEOD_HOME/models to the model in question. This must be a char* string and shoult terminate in a '/'.
in	*id*	The static member data name to be assigned.

Definition at line 71 of file make_message_code.hh.

9.3 message_handler.cc File Reference

Define member functions for the class MessageHandler.

```
#include <cstdarg>
#include <cstddef>
#include <cstdio>
#include <cstdlib>
#include "../include/message_handler.hh"
#include "../include/message_messages.hh"
```

Namespaces

- jeod

  Namespace jeod.

9.3.1 Detailed Description

Define member functions for the class MessageHandler.

9.4 message_handler.hh File Reference

Define the class MessageHandler, the base class for generating messages.

```
#include <cstdarg>
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/sim_interface/include/simulation_interface.hh"
#include "class_declarations.hh"
```

Data Structures

- class jeod::MessageHandler

  The base class for generating JEOD messages.

Namespaces

- jeod

  Namespace jeod.

9.4.1 Detailed Description

Define the class MessageHandler, the base class for generating messages.

9.5 message_messages.cc File Reference

Implement the class MessageMessages.

```
#include "utils/message/include/make_message_code.hh"
#include "../include/message_messages.hh"
```

Namespaces

- jeod

  Namespace jeod.

Macros

- #define MAKE_MESSAGE_MESSAGE_CODE(id) JEOD_MAKE_MESSAGE_CODE(MessageMessages, "utils/message/", id)

9.5.1 Detailed Description

Implement the class MessageMessages.

9.5.2 Macro Definition Documentation

9.5.2.1 MAKE_MESSAGE_MESSAGE_CODE

```
#define MAKE_MESSAGE_MESSAGE_CODE(
              id ) JEOD_MAKE_MESSAGE_CODE(MessageMessages, "utils/message/", id)
```

Definition at line 38 of file message_messages.cc.

9.6 message_messages.hh File Reference

Define the class MessageMessages.

Data Structures

- class jeod::MessageMessages
  Specifies the message IDs used in the message handler model.

Namespaces

- jeod
  Namespace jeod.

9.6.1 Detailed Description

Define the class MessageMessages.

9.7 suppressed_code_message_handler.cc File Reference

Define member functions for the class SuppressedCodeMessageHandler.

```
#include <cstdarg>
#include <cstddef>
#include <cstdio>
#include <cstdlib>
#include "utils/memory/include/jeod_alloc.hh"
#include "../include/suppressed_code_message_handler.hh"
```

Namespaces

- jeod
  Namespace jeod.

9.7.1 Detailed Description

Define member functions for the class SuppressedCodeMessageHandler.

9.8 suppressed_code_message_handler.hh File Reference

Define the class SuppressedCodeMessageHandler, which adds the capability to suppress messages by their message code.

```
#include "utils/container/include/primitive_set.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "message_handler.hh"
```

Data Structures

- class jeod::SuppressedCodeMessageHandler

  Adds the capability to suppress messages by their message code to the base MessageHandler class.

Namespaces

- jeod

  Namespace jeod.

9.8.1 Detailed Description

Define the class SuppressedCodeMessageHandler, which adds the capability to suppress messages by their message code.

This capability cannot be a part of the base MessageHandler class because that base class needs to stand on its own.

Index

~MessageHandler
    jeod::MessageHandler, 20
~SuppressedCodeMessageHandler
    jeod::SuppressedCodeMessageHandler, 39

add_suppressed_code
    jeod::MessageHandler, 21

class_declarations.hh, 43
clear_suppressed_codes
    jeod::MessageHandler, 21

Debug
    jeod::MessageHandler, 33
debug
    jeod::MessageHandler, 21
delete_suppressed_code
    jeod::MessageHandler, 22
deregister_contents
    jeod::MessageHandler, 22
    jeod::SuppressedCodeMessageHandler, 39

Error
    jeod::MessageHandler, 33
error
    jeod::MessageHandler, 23

fail
    jeod::MessageHandler, 23
Failure
    jeod::MessageHandler, 34

get_suppress_id
    jeod::MessageHandler, 25
get_suppress_location
    jeod::MessageHandler, 25
get_suppression_level
    jeod::MessageHandler, 25

handler
    jeod::MessageHandler, 34

inform
    jeod::MessageHandler, 26
init_attrjeod__MessageHandler
    jeod::MessageHandler, 33
init_attrjeod__SuppressedCodeMessageHandler
    jeod::SuppressedCodeMessageHandler, 42
InputProcessor
    jeod::MessageHandler, 33
    jeod::SuppressedCodeMessageHandler, 42

JEOD_MAKE_MESSAGE_CODE
    make_message_code.hh, 44
jeod, 15
jeod::MessageHandler, 17
    ~MessageHandler, 20
    add_suppressed_code, 21
    clear_suppressed_codes, 21
    Debug, 33
    debug, 21
    delete_suppressed_code, 22
    deregister_contents, 22
    Error, 33
    error, 23
    fail, 23
    Failure, 34
    get_suppress_id, 25
    get_suppress_location, 25
    get_suppression_level, 25
    handler, 34
    inform, 26
    init_attrjeod__MessageHandler, 33
    InputProcessor, 33
    MessageHandler, 20, 21
    mode, 34
    no_handler_error, 26
    Notice, 35
    operator=, 27
    process_add_suppressed_code, 27
    process_clear_suppressed_codes, 27
    process_delete_suppressed_code, 28
    process_message, 28
    register_contents, 29
    send_message, 29
    set_mode, 30
    set_mode_internal, 30
    set_suppress_id, 31
    set_suppress_location, 31
    set_suppression_level, 31
    suppress_id, 35
    suppress_location, 35
    suppression_level, 35
    va_send_message, 32
    warn, 32
    Warning, 36
jeod::MessageMessages, 36
    MessageMessages, 37
    operator=, 37
    singleton_error, 37
jeod::SuppressedCodeMessageHandler, 38

~SuppressedCodeMessageHandler, 39
deregister_contents, 39
init_attrjeod__SuppressedCodeMessageHandler, 42
InputProcessor, 42
message_is_to_be_printed, 40
operator=, 40
process_add_suppressed_code, 40
process_clear_suppressed_code, 41
process_delete_suppressed_code, 41
register_contents, 41
suppressed_codes, 42
SuppressedCodeMessageHandler, 39

MAKE_MESSAGE_MESSAGE_CODE
message_messages.cc, 46
make_message_code.hh, 43
JEOD_MAKE_MESSAGE_CODE, 44
Message, 13
message_handler.cc, 44
message_handler.hh, 45
message_is_to_be_printed
jeod::SuppressedCodeMessageHandler, 40
message_messages.cc, 45
MAKE_MESSAGE_MESSAGE_CODE, 46
message_messages.hh, 46
MessageHandler
jeod::MessageHandler, 20, 21
MessageMessages
jeod::MessageMessages, 37
mode
jeod::MessageHandler, 34
Models, 11

no_handler_error
jeod::MessageHandler, 26
Notice
jeod::MessageHandler, 35

operator=
jeod::MessageHandler, 27
jeod::MessageMessages, 37
jeod::SuppressedCodeMessageHandler, 40

process_add_suppressed_code
jeod::MessageHandler, 27
jeod::SuppressedCodeMessageHandler, 40
process_clear_suppressed_code
jeod::SuppressedCodeMessageHandler, 41
process_clear_suppressed_codes
jeod::MessageHandler, 27
process_delete_suppressed_code
jeod::MessageHandler, 28
jeod::SuppressedCodeMessageHandler, 41
process_message
jeod::MessageHandler, 28

register_contents
jeod::MessageHandler, 29
jeod::SuppressedCodeMessageHandler, 41

send_message
jeod::MessageHandler, 29
set_mode
jeod::MessageHandler, 30
set_mode_internal
jeod::MessageHandler, 30
set_suppress_id
jeod::MessageHandler, 31
set_suppress_location
jeod::MessageHandler, 31
set_suppression_level
jeod::MessageHandler, 31
singleton_error
jeod::MessageMessages, 37
suppress_id
jeod::MessageHandler, 35
suppress_location
jeod::MessageHandler, 35
suppressed_code_message_handler.cc, 46
suppressed_code_message_handler.hh, 47
suppressed_codes
jeod::SuppressedCodeMessageHandler, 42
SuppressedCodeMessageHandler
jeod::SuppressedCodeMessageHandler, 39
suppression_level
jeod::MessageHandler, 35

Utils, 12

va_send_message
jeod::MessageHandler, 32

warn
jeod::MessageHandler, 32
Warning
jeod::MessageHandler, 36