SKXXX - How to Setup a Ship Station

Purpose - Ensure the Ship Station has the necessary tools for daily operation

Procedure

Ship station client software

Run as Administrator: PowerShell ISE

 $\label{thm:linear_standalone} Execute $$\sum_{s,s} ShipStationSetup\ShipStation.ps1$$

Zebra printer setup

- 1. Press and hold the feed button until the status light flashes once
- 2. Two labels of configuration settings will print out, but the only setting that we need to pay attention to is the IP Address * It will be in the format of: 192.168.001.XXX
- 3. Log into the web browser with the printer's IP address
- 4. View and Modify Printer Settings * Enter Password: 1234 * Click to Proceed
- 5. Network Configuration * TCP/IP Settings * Input an available static IP address * Change IP Protocol to Permanent * Submit Changes * Save Current Configuration
- 6. Go back to the Home page * Printer Controls * Reset Printer
- 7. The printer's status light will turn orange, and then green once it is ready
- 8. Verify the static IP address took effect by logging into the web browser with said IP address

Install Zebra Printer to Prd-ConnectShip

- 1. RDP into Prd-ConnectShip and add the zebra printer via it's static IP address
- 2. Install the Zebra ZP 450-200 driver
- 3. The share name should be [Location]Zebra

Change Database Values

UPDATE CS_Portal.ship_station \
SET ship_label_printer_path='\\\Prd-ConnectShip\\New_Zebra_Printer_Share_Name' \
WHERE ship_id=#;