


# **ITNW1425 - PT EXAM 3**

# **Topology**



## **Addressing Table**

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
		IPv6 Address/Prefix	IPv6 Link-local	
R1	G0/0	192.168.0.1	255.255.255.128	N/A
		2001:DB8:ACAD::1/64	FE80::1	N/A
	G0/1	192.168.0.129	255.255.255.192	N/A
		2001:DB8:ACAD:1::1/64	FE80::1	N/A
	G0/2	192.168.0.193	255.255.255.224	N/A
		2001:DB8:ACAD:2::1/64	FE80::1	N/A
	S0/0/1	172.16.1.2	255.255.255.252	N/A
		2001:DB8:2::1/64	FE80::1	N/A
Central	S0/0/0	209.165.200.226	255.255.255.252	N/A
		2001:DB8:1::1/64	FE80::2	N/A
	S0/0/1	172.16.1.1	255.255.255.252	N/A
		2001:DB8:2::2/64	FE80::2	N/A
S1	VLAN 1	192.168.0.2	255.255.255.128	192.168.0.1
S2	VLAN 1	192.168.0.130	255.255.255.192	192.168.0.129
S3	VLAN 1	192.168.0.194	255.255.255.224	192.168.0.193
Staff	NIC	192.168.0.3	255.255.255.128	192.168.0.1
		2001:DB8:ACAD::2/64	FE80::2	FE80::1
Sales	NIC	192.168.0.131	255.255.255.192	192.168.0.129
		2001:DB8:ACAD:1::2/64	FE80::2	FE80::1
IT	NIC	192.168.0.195	255.255.255.224	192.168.0.193
		2001:DB8:ACAD:2::2/64	FE80::2	FE80::1
Web	NIC	64.100.0.3	255.255.255.248	64.100.0.1
		2001:DB8:CAFE::3/64	FE80::2	FE80::1

### Scenario / Background

The router Central, ISP cluster and the Web server are completely configured. You have been tasked with creating a new IPv4 addressing scheme that will accommodate 4 subnets using 192.168.0.0/24 network. The IT department requires 25 hosts. The Sales department needs 50 hosts. The subnet for the rest of the staff requires 100 hosts. A Guest subnet will be added in the future to accommodate 25 hosts. You are also tasked with finishing the basic security settings and interface configurations on R1. Furthermore, you will configure the SVI interface and basic security setting on switches S1, S2 and S3.

### Requirements

#### **IPv4 Addressing**

Create subnets that meet the host requirements using 192.168.0.0/24.

Staff: 100 hostsSales: 50 hostsIT: 25 hosts

Guest network to be added later: 25 hosts

Document the assigned IPv4 addresses in the Addressing Table.

#### **PC Configurations**

- Configure the assigned IPv4 address, subnet mask, and default gateway settings on the Staff, Sales and IT PCs using your addressing scheme.
- Assign IPv6 unicast and link local addresses and default gateway to the Staff, Sales, and IT networks according to the Addressing Table.

#### **R1 Configurations**

- Configure the device name according to the Addressing Table.
- Disable DNS lookup.
- Assign Ciscoenpa55 as the encrypted privileged EXEC mode password.
- Assign Ciscoconpa55 as the console password and enable login.
- Require that a minimum of 10 characters be used for all passwords.
- Encrypt all plaintext passwords.
- Create a banner that warns anyone accessing the device that unauthorized access is prohibited. Make sure to include the word **Warning** in the banner.
- Configure all the Gigabit Ethernet interfaces.
  - Configure the IPv4 addresses according to your addressing scheme.
  - Configure the IPv6 addresses according to the Addressing Table.
- Configure SSH on R1:
  - o Set the domain name to CCNA-lab.com
  - Generate a 1024-bit RSA key.
  - Configure the VTY lines for SSH access.
  - o Use the local user profiles for authentication.
  - Create a user Admin1 with a privilege level of 15 using the encrypted password for Admin1pa55.
- Configure the console and VTY lines to log out after five minutes of inactivity.
- Block anyone for three minutes who fails to log in after four attempts within a two-minute period.

### **Switch Configurations**

- Configure the device name according to the Addressing Table.
- Configure the SVI interface with the IPv4 address and subnet mask according your addressing scheme.

#### **ITNW1425 - PT EXAM 3**

- Configure the default gateway.
- Disable DNS lookup.
- Assign Ciscoenpa55 as the encrypted privileged EXEC mode password.
- Assign Ciscoconpa55 as the console password and enable login.
- Configure the console and VTY lines to log out after five minutes of inactivity.
- Encrypt all plaintext passwords.

# **Verify Connectivity**

- Using the web browser from Staff, Sales, and IT PCs, navigate to www.cisco.pka.
- Using the web browser from Staff, Sales, and IT PCs, navigate to www.cisco6.pka.
- All PCs should be able to ping all the devices.