

Administration Guide

SQream Technologies

Version 3.3



Copyright © 2010-2019. All rights reserved.

This document is provided for information purposes only and the contents hereof are subject to change without notice. This document is not warranted to be error-free, nor subject to any other warranties or conditions, whether expressed orally or implied in law, including implied warranties and conditions of merchant- ability or fitness for a particular purpose.

We specifically disclaim any liability with respect to this document and no contractual obligations are formed either directly or indirectly by this document.

This document may not be reproduced in any form, for any purpose, without our prior written permission.



Table of Contents

Table of Contents	3
SQream DB Administrator Guide	5
Overview	5
Administration Guide	6
Getting Started	7
Understanding the SQream DB environment	7
Setting up SQream DB	8
Create the cluster	9
Configure the instances	9
Configuring instances parameters	10
Starting and Stopping the SQream DB daemons	11
SQream based on Docker	11
SQream based on RPM	12
Connect to the SQream DB server with ClientCmd	14
Using SSL Server Authentication with SQream	14
Enabling SSL server authentication within SQream Instance:	14
Configure SSL Authentication for JDBC/ODBC drivers	15
Adding SSL to JDBC	15
Adding SSL to ODBC	15
Highly available installations	15
Operations	16
Upgrading a version	16
Key administration concepts	16
Monitoring the system	16
From the OS	16
From each node	16
See connections to the server	16
Show server / cluster status	17
By running a query	18



Stopping existing statements	18
Logs	18
Support Utilities	20
Report Collection	20
Export Reproducible Sample Data	20



SQream DB Administrator Guide

Version 3.3

Overview

This guide is intended for SQream DB administrators.

The guide will go through the DBA main tasks, as well as describing some of the best practices in SQream DB.

This guide is a complementary guide to the SQL Reference.

For further support please contact **support@sqreamtech.com** or your account manager.

Version 3.3 - 5 - Administration Guide



Administration Guide

This document is mostly a conceptual overview and recommendations on best practices regarding SQream internal behavior. For SQL syntax and supported features, please refer to the SQL Reference Guide.

NOTE:

All keywords in are case insensitive.




Getting Started

Understanding the SQream DB environment

The SQream environment is usually made up of two folders - the installation directory and the storage cluster.

The installation directory

This folder contains the SQream DB binary applications.



The main applications found in the binary directory are:


Executable Name	Description
sqreamd	The sqreamd server daemon
ClientCmd	Command line client
upgrade_storage	Metadata storage upgrader to be used between versions
SqreamStorage	Storage utility to create new clusters and restore access
metadata_server	Metadata server for clustered installations
server_picker	Load balancer for clustered installations

The storage cluster root

This directory contains the entire database storage.

Version 3.3 - 7 - Administration Guide





Directory	Description
databases	The files containing all databases, tables, columns, chunks, etc.
metadata	Internal metadata structures for accessing data from disk
temp	Temporary spools
logs	The logs folder contains subfolders per SQream instance with folder name = [IP_port]. One folder per running SQream instance.
127.0.0.1_	Contains all logs files of a specific SQream instance
5000 [IP_	
port]	

Setting up SQream DB


If you would like to deploy SQream DB on AWS or Azure please contact SQream directly at info@sqream.com.

Make sure that you are running on a 64-bit Linux operating system, and have an Nvidia GPU installed.

See the Hardware Requirements page to verify your system meets the minimum requirements for running SQream DB.

Version 3.3 - 8 - Administration Guide





Create the cluster

- 1. Enter the sqream directory and create a storage cluster
- 2. ./bin/SqreamStorage -C -r <full path to new cluster>

Example: Create storage cluster

```
If your main storage is on /mnt/storage, you can run
./bin/SqreamStorage -C -r /mnt/storage/sqream storage
```

Configure the instances

Each SQream DB daemon must run against a configuration file.

Below is a sample minimal configuration file. It is recommended that it be placed in /etc/sqream/sqream_config.json. This file will start the server on port 5000, against GPU #0.

```
Example minimal configuration JSON

{
    "compileFlags": {
    },
    "runtimeFlags": {
    },
    "runtimeGlobalFlags": {
    },
    "server": {
```



```
"licensePath" : "/etc/sqream/license.enc",
    "port": 5000,
    "cluster": "/mnt/storage/sqream_storage",
    "gpu": 0,
    "ssl_port": 5100
}
```

NOTE:

- JSON files can not contain any comments
- When altering the JSON file, pay close attention to the field-separating commas at the end of the lines.

Permanent instance options may be placed in this file, based on consultation with SQream support or through the configuration utility.

Configuring instances parameters

Table 20. Common parameters setting

Flag Name	Description	Defau It Value	Range of Values	Remark		
spoolmemorygb	Select what size spool SQream DB can use for writing intermediate results to RAM, in GB	128gb	1- machine ram size	Should consider total ram size and number of SQream instances		
insertParsers	Set the number of parsing threads to be launched for each file, during the bulk load process	4	1-32	Should consider total ram size and number of SQream instances		
insertCompressors	Set the number of compression threads to be launched for each file, during	4	1-32	Should consider total ram size and number of		



Flag Name	Description	Defau It Value	Range of Values	Remark
	the bulk load process			SQream instances
statementLockTimeout	Set the number of seconds SQream will wait for a lock before returning an error	3	1-no limit	
showFullExceptionInfo	Show complete error message	FALSE	TRUE/FAL SE	Enabling this setting will often show more detailed error message
initialSubscribedServi ces	List of services the instance will be subscribed to	sqrea m	list of strings	Example: "sqream,etl_ service,quer y_service"
useLogMaxFileSize	Defines whether SQream logs should be cycle every logMaxFileSize MB size	TRUE	TRUE/FAL SE	
logMaxFileSizeMB	Set the size of SQream logs cycle	20	>0	Set in MB

Starting and Stopping the SQream DB daemons

The procedure for starting and stopping the SQream DB daemons varies depending on your installation type:

- SQream based on Docker
- SQream based on RPM

SQream based on Docker

Use the start and stop options of the sqreamd command as described in the sqream-console commands in Start the SQream Console.

Version 3.3 - 11 - Administration Guide



SQream based on RPM

A SQream RPM installation uses the Monit service to control the SQream services.

To start the SQream demons (Metadata, Server Picker and SQreamD):

```
$ sudo systemctl start monit
```

To check the SQream demons (Metadata, Server Picker and SQreamD):

• Option 1:

```
$ sqream_status
```

Expected output:

```
SQreamDB monit.service: ACTIVE pid=6406 [ OK ]
SQreamDB metadataserver.service: ACTIVE pid=6427 [ OK ]
SQreamDB serverpicker.service: ACTIVE pid=6579 [ OK ]
SQreamDB sqream1.service: ACTIVE pid= 7440 [ OK ]
```

• Option 2:

```
$ ps axuwww | grep -v 'grep\|tail\|monitor' | grep -i
'sqreamd\|metadata_server\|server_pick\|monit'
```

Expected output:

```
7690 0.0 0.0 191916 2464 ?
/bin/su - sqream -c /bin/nohup /usr/local/sqream/bin/metadata
server &>> /var/log/sqream/metadataserver.log
sqream 7693 0.0 0.0 115304 1680 ? Ss 15:27 0:00 -
bash -c /bin/nohup /usr/local/sqream/bin/metadata_server &>>
/var/log/sqream/metadataserver.log
sqream 7708 0.2 1.8 1110888704 183644 ? S1 15:27 0:02
/usr/local/sqream/bin/metadata server
       8105 0.0 0.0 19191\overline{6} 2456 ? Ss 15:27 0:00
/bin/su - sqream -c exec /usr/local/sqream/bin/server picker
127.0.0.1 3105 &>> /var/log/sgream/serverpicker.log
sgream 8116 0.2 1.5 34887308 156592 ? Ssl 15:27 0:02
/usr/local/sqream/bin/server_picker 127.0.0.1 3105
root 8450 0.2 0.0 131124 3452 ? Ssl 15:34 0:01
/usr/bin/monit -I
root 8453 0.0 0.0 191916 2460 ? Ss
                                               15:34 0:00
/bin/su - sqream -c exec /usr/local/sqream/bin/sqreamd -config
/etc/sqream/sqream1\_config.json &>> /var/log/sqream/sqream1.log
sqream 8456 0.6 5.5 1111154756 542644 ? Ssl 15:34 0:04
/usr/local/sqream/bin/sqreamd -config /etc/sqream/sqream1
config.json
```

To stop all SQream services:



\$ sudo /usr/local/sqream/config/sqream-stop.sh

Expected output:

-----==>Stopping SQreamDB Services LOAD ACTIVE SUB DESCRIPTION UNTT • metadataserver.service loaded Metadata Server For SQreamDB • serverpicker.service loaded Server Picker - Load Balancer For SQreamDB loaded SQream SQL Server • sqream1.service LOAD = Reflects whether the unit definition was properly loaded. ACTIVE = The high-level unit activation state, i.e. generalization of SUB = The low-level unit activation state, values depend on unit type. 3 loaded units listed. Pass --all to see loaded but inactive units, too. To show all installed unit files use 'systemctl list-unit-files'. ==>SQreamDB Services have been stopped

To stop a specific SQream service:

1. Stop the Monit service:

```
$ sudo systemctl stop monit
```

- 2. Stop the specific SQream service, for example stopping sqream1:
 - Option 1:

```
$ sudo systemctl stop sqream1
```

• Option 2:

```
$ pkill -9 sqreamd
```

To restart a service that was stopped:

• Option 1:

Start the Monit service and monit will start all stopped services:

```
$ sudo systemctl start monit
```

• Option 2:



Start the stopped service manually:

```
$ sudo systemctl start sqream1.service
```

Connect to the SQream DB server with ClientCmd

To connect to the database server, you may use the ClientCmd command line interface by running

```
ClientCmd command line arguments

./bin/ClientCmd --user=<username> --password=<password> --
database=<database name> --host=<host> --port=<port> --
service=<service_name>
```

Connect to the master database:

```
Connecting to master on a local host running SQream DB on port 5000 via service 'etl_ service'

./bin/ClientCmd --user=sqream --password=sqream --database=master --
-host=127.0.0.1 --port=5000 --service=etl_service
```

Using SSL Server Authentication with SQream

From version 2.1, SQream DB supports secure sockets layer (SSL) encryption and authentication for connections to its cluster via JDBC and ODBC drivers.

To use this option, the server must first be set-up to accept SSL connections.

Enabling SSL server authentication within SQream Instance:

Configure the SERVER flag ssl_port in the SQream instance configuration file to the needed port number.

For Example:

```
{
  "server":{
     "port": 5001,
     "ssl_port": 5100,
     "cluster": "/path/sqream_cluster",
     "gpu": 0,
     "licensePath": "/path/license.enc"
}
}
```

Version 3.3 - 14 - Administration Guide



NOTE:

Restart the SQream DB daemons after making this configuration change

Configure SSL Authentication for JDBC/ODBC drivers Adding SSL to JDBC

- 1. Add ssl=true in the connection string
- 2. Change the port to the SSL port

NOTE:

When connecting via load balancer, the default endpoint for SSH is port 3109

Example for direct connection

jdbc:Sqream://hostname:5100/master;user=sqream;password=mypassword; ssl=true;

Example for connection to load balancer

jdbc:Sqream://hostname:3109/master;user=sqream;password=mypassword; service=sqream;cluster=true;ssl=true;

Adding SSL to ODBC

In Windows, make sure the SSL checkbox is selected in the DSN settings.

In Linux, add SsI=true to the connection string

Linux ODBC connection string sample

Driver=

{libODBCDrv.so}:Server=hostname:Port=5100:Database=master:User=sqre am:Password=mypassword:Ssl=true:Service=sqream

Highly available installations

Contact your SQream representative for further information about installing our highly available solutions.

Version 3.3 - 15 - Administration Guide



Operations

Upgrading a version

Here are the necessary steps that ensure a smooth upgrade of your SQream DB version

- 1. Stop SQream instances on all servers
- 2. On each node that SQream is installed, unpack the new tarball alongside the old SQream DB directory.

 For example:

```
$ cd /home/sqream
$ mv sqream sqream-old
$ tar xf sqream-<version>.tar.gz
```

- 3. Repeat the above step for each node that the SQream DB executables exist
- 4. It may be necessary to run the metadata upgrade utility. (This may take a few moments)

```
$ cd sqream/bin
$ ./upgrade_storage <path to sqream storage cluster>
```

5. Restart the services

Key administration concepts

See Concepts above

Monitoring the system

Because SQream DB can be run in a distributed setting, all nodes should be monitored to ensure smooth operation. It is possible to monitor SQream DB with third party tools like Zabbix, Nagios and others, but also through the OS and SQream DB directly.

From the OS

See Identifying which SQream daemons are running

From each node

See connections to the server

You can monitor existing connections to the database by using the <code>show_connections()</code> utility function:



```
SELECT show_connections();
```

Table 21. Sample result from show connections ()

ip	conn_id	conn_start_ time	stmt_id	stmt_start_ time	stmt
192.168.0.93	19	2017-06-22 18:56:54	14	2017-06-22 18:56:54	select show_ connections ()
192.168.0.93	17	2017-06-22 18:56:48	-1	2017-06-22 18:56:48	

Show server / cluster status

The <code>show_server_status()</code> utility function can be used to see which statements are running across the cluster, across all databases.

NOTE:

If no queries are running, this query will return 0 rows in the result set.

```
SELECT show_server_status();
```

Table 22. Sample result from show server status()

ser vic e_ id	conn ectio n_id	serv er ip	se rv er po rt	data bas e_ nam e	us e r_ na m e	clie nt ip	stat eme nt id	stat eme nt	stat eme nt star t time	state ment status	statem ent status start
sqr ea m	32	192.1 68.0. 93	50 00	faa	sq re am	192. 168. 0.1	25	SELE CT Year	Carr	destCi tyNam e	COUNT (DISTIN CT originCi tyNam e) from ontime JOIN I_ airport_ i

Version 3.3 - 17 - Administration Guide



Possible statement status values

Status	Description
Executing	The statement is in execution, awaiting results
Preparing	The statement is compiling, and is awaiting execution
Waiting	The statement is waiting in the queue for execution

The DBA can use the show server status output as a baseline for identifying locks and if needed to stop running statements (based on the **server ip : server port** and **statement_id** columns).

By running a query

Running a query, even the most basic one, should give you an indication if a server is up. If you immediately get "Connection refused" or similar, the server is down.

```
SELECT 1;
```

Stopping existing statements

The **stop_statement()** utility function can be used to cancel or stop a running statement before it finishes.

Usage

- Identify the running statement ID and server IP and port (see show server status or show_connections above)
- From the same server/port combination run the stop_statement command:

```
SELECT stop_statement(42);
```

Logs

SQream DB generates the following log files for the DBA everyday work

Log files:

- clientLogger_statement Keeps track of statements being run in the server, including success/failure, number of rows returned from the query and number of rows processed by the query.
- clientLogger_server Keeps track of server start/stop times
- clientLogger_session Keeps track of different sessions



- clientLogger_login Tracks user login times and IP addresses
- clientLogger_exception Tracks system exceptions
- clientLogger_execution Tracks heavy statements execution statistics (over nodeInfoLoggingSec flag)
- clientLogger_debug Logs debug information. Default debug log level = 4 (INFO). The debug log level can be changed running a statement (e.g., SET logDebugLevel = 6;). No need to restart the SQream instance.
- metadata_server.log Tracks metadata server status and executions queue

NOTE:

File names: Log file names contain a day and time stamp. For example: clientLogger_statement_20181108_000000.log

Statement log messages are cut at a length of 10,000 characters. This is to allow loading statements logs files (CSV) into External Tables of SQream. Remember: Row length is limited to 10,240 characters.

Log file configuration:

From V2.18.1 the following default behavior is configured:

- Each SQream instance generates a separate set of log files into a dedicated folder (folder name contains IP and port). For example: /home/sqream/sqream_storage/sqreamdb/logs/127.0.0.1_5000.
- Log file rotation: One separate log file per calendar day. New file is generated at midnight.

Related runtimeGlobalflags:

- useClientLog: This flag is set the TRUE (by default) to activate the new logging framework.
- useLogFileRotateHourOfDay: Enable/disable the rotation of log files. By default this flag is set to TRUE to allow seperate files for separate days.
- **logFileRotateHourOfDay**: Rollover time parameter. By default this flag is set to 0 (=rotation at midnight). Set in the hour of the day. Possible range of values: 0-23.
- enableLogDebug: Activate / deactivate the debug log. Default value = true;
- logDebugLevel: Supported Log Levels are: 0 = [SYSTEM], 1 [FATAL], 2 -



[ERROR], 3 - [WARN], 4 - [INFO], 5 - [DEBUG], 6 - [TRACE]. Default = 4 (INFO);

Support Utilities

Report Collection

This support utility is used to collect logs and/or the leveldb at a client's site. The generated tar file can then be sent to the SQream support team for further investigation.

Output file format: report_[date]_[time].tar

Can run as a utility function or executable, allowing to collect information also if the SQream server is not running. Supported collection modes:

- log = only log files are collected
- db = only leveldb
- db and log = both log files and leveldb are collected

```
Syntax and example when running as a utility function:

SELECT report_collection('</pathToOutputFolder>', '<mode>');

SELECT report_collection('/home/sqream/log_collection','log'); )
```

Syntax and example for executable. The executable works only when no SQream instance is running:

```
./bin/report_collection <pathToSqreamDb> </pathToOutputFolder>
<mode>./bin/report_collection /home/sqream/sqream_storage/
/home/sqream/log_collection log
```

Export Reproducible Sample Data

This support utility is used to collect data in order to reproduce a problematic query in a support lab (not only onsite at customer's site). Typically used for query issues that are data related. It runs a query, collects the data and stores the data in a small SQream DB (compressed into a single tar file). This file together with the query can be used in a remote system (support lab) to recreate and investigate the issue.

The output folder contains both the final tar file and data before its compression. It is sufficient to send the tar file. Works as utility function. No executable.

```
Syntax and example:

select export_reproducible_sample('</pathToOutputFolder>', 'sql
query1', 'sql query 2', ..);
```



select export_reproducible_sample('home/sqream/data_collection',
'select * from t');

Version 3.3 - 21 - Administration Guide