

embedded scripting language

Process control and Foreign Function Interface

November 2006

Abstract

The "Process control and Foreign Function Interface" extension module provides functions to launch other programs and to call functions from DLLs (Microsoft Windows) or shared libraries (Unix/Linux).

The software that is associated with this application note can be obtained from the company homepage, see section "Resources".

Introduction
Library calls
Launching programs
Security, stability
Implementing the library
USAGE
Native functions5
RESOURCES
Index

"Microsoft" and "Microsoft Windows" are registered trademarks of Microsoft Corporation.

Copyright © 2005–2006, ITB CompuPhase; Eerste Industriestraat 19–21, 1401VL Bussum, The Netherlands (Pays Bas); telephone: (+31)-(0)35 6939 261 e-mail: info@compuphase.com, WWW: http://www.compuphase.com

The information in this manual and the associated software are provided "as is". There are no guarantees, explicit or implied, that the software and the manual are accurate.

Requests for corrections and additions to the manual and the software can be directed to ITB CompuPhase at the above address.

Typeset with TeX in the "Computer Modern" and "Palatino" typefaces at a base size of 11 points.

[&]quot;Linux" is a registered trademark of Linus Torvalds.

[&]quot;CompuPhase" is a registered trademark of ITB CompuPhase.

Introduction

The Process control and Foreign Function Interface module enables PAWN programs to run executable programs and call functions from libraries. When running executable programs, the PAWN script can also interact with that program (send "input", receive "output").

This appendix assumes that the reader understands the PAWN language. For more information on PAWN, please read the manual "The PAWN booklet — The Language" which is available from the site www.compuphase.com.

Library calls

A PAWN script calls functions that are implemented inside the script itself and it calls functions that have been specifically registered for use from PAWN. These are PAWN functions and *native* functions, respectively. A Foreign Function Interface allows the PAWN script to call functions in general purpose libraries that do not adhere to any "PAWN" calling convention. Modern operating systems provide a large set of "system calls" that reside in pre-compiled libraries —in the Microsoft Windows world, these are DLLs, or Dynamically Linked Libraries; for Unix, Linux and similar operating systems, these are *shared libraries*.

The Foreign Function Interface, therefore, makes this wealth of functions available to a PAWN script, but there are several caveats:

- ♦ Since the "foreign" functions are based on a different machine model than PAWN, you have to pass additional "bookkeeping" information to the function call.
- ♦ Calling functions in DLLs and shared libraries breaks the *sandbox* model of the PAWN abstract machine. It is very easy to crash an application by sending invalid parameters to a foreign function.
- ♦ And there are security & stability issues; see page 2

Launching programs

The extension module supports launching executable programs. If the launched program is a "console application", it can also provide input to the launched program and read its output. The external program sees the input as standard

console/terminal input, and any text that it writes to standard console/terminal output is read back by the PAWN script.

In the current version, I/O redirection only works for a single launched program.

Security, stability

The ability launch any program, or to call any function from a system DLL or shared library may obviously cause the system to become unstable. Passing the wrong parameters to a program or library function may crash the system immediately, and it could even damage (system) files.

When the PAWN abstract machine is implemented in an environment where scripts are automatically loaded from a network connection, it also becomes vulnerable to sabotage or "malware".

Implementing the library

The Process control and Foreign Function Interface module consists of this document and the files AMXPROCESS.C and PROCESS.INC. The C file may be "linked in" to a project that also includes the PAWN abstract machine (AMX.C), or it may be compiled into a DLL (Microsoft Windows) or a shared library (Linux). The .INC file contains the definitions for the PAWN compiler of the native functions in AMXPROCESS.C. In your PAWN programs, you may either include this file explicitly, using the #include preprocessor directive, or add it to the "prefix file" for automatic inclusion into any PAWN program that is compiled.

The "Implementer's Guide" for the PAWN toolkit gives details for implementing the extension module described in this application note into a host application. The initialization function, for registering the native functions to an abstract machine, is amx_ProcessInit and the "clean-up" function is amx_ProcessCleanup. In the current implementation, calling the clean-up function is not required.

If the host application supports dynamically loadable extension modules, you may alternatively compile the C source file as a DLL or shared library. No explicit initialization or clean-up is then required. Again, see the Implementer's Guide for details.

When compiling the library under Unix or Linux, you need the "dyncall" library. This library can be obtained from http://www.dyncall.org/. When compiling for Microsoft Windows, you may also need this library, depending on your compiler. If the dyncall library is absent, the Process control module will still compile, but it will exclude the support for shared libraries.

Usage

Depending on the configuration of the PAWN compiler, you may need to explicitly include the PROCESS.INC definition file. To do so, insert the following line at the top of each script:

#include cess>

The angle brackets "<...>" make sure that you include the definition file from the system directory, in the case that a file called PROCESS.INC or PROCESS.PAWN also exists in the current directory.

Native functions

Foreign Function Interface: DLL call

libcall		Call a function in a library			
Syntax:	<pre>libcall(const libname[], const funcname[],</pre>				
	libname	The module name or filename of the DLL or of the shared library. This library is automatically loaded on first use. The library name look-up is case-sensitive.			
	funcname	The name of the function to call. This must be the symbol name as it exists in the library, including all "decorations" added by compilers or linkers.			
	typestring	A string that tells the types of the function parameters, as defined by the foreign function. See the notes for the syntax.			
		The values of the foreign parameters.			

Returns:

This function returns the return value of the foreign function.

Notes:

The typestring format is a string where the types of the parameters that follow on the parameter list are represented by tokens. A token is basically a single letter, but it may be decorated with attributes. White space is permitted between the tokens, but not inside each token specification. The string "ii[4]&u16s" is equivalent to "i i[4] &u16s" (but it is easier on the eye).

Basic types:

- i signed integer, by default 16-bit in Windows 3.x and 32-bit in Win32 and Linux
- u unsigned integer, by default 16-bit in Windows 3.x and 32-bit in Win32 and Linux
- f IEEE floating point, 32-bit (single precision)
- p packed string
- s unpacked string

The difference between packed and unpacked strings is only relevant when the parameter is passed by reference (see below).

Pass-by-value and pass-by-reference:

By default, parameters are passed by value. To pass a parameter by reference, prefix the type letter with an "k". For example:

a signed integer passed by reference

a signed integer passed by value

The same applies for "&u" versus "u" and "&f" versus "f".

Arrays are passed by "copy & copy-back". That is, libcall allocates a block of dynamic memory to copy the array into. On return from the foreign function, libcall copies the array back to the abstract machine. The net effect is similar to pass by reference, but the foreign function does not work in the AMX stack directly. During the copy and the copy-back operations, libcall may also transform the array elements, for example between 16-bit and 32-bit elements. This is done because PAWN only supports a single cell size, which may not fit the required integer size of the foreign function.

See "element ranges" (below) for the syntax of passing an array.

Strings may either be passed by copy, or by "copy & copy-back". When the string is an output parameter (for the foreign function), the size of the array that will hold the return string must be indicated between square brackets behind the type letter (see "element ranges", below). When the string is *input only*, this is not needed -libcall will determine the length of the input string itself.

The tokens "p" and "s" are equivalent, but "p[10]" and "s[10]" are not equivalent: the latter syntaxes determine whether the output from the foreign function will be stored as a packed or an unpacked string.

Element sizes:

To set the size in bits of a parameter, add an integer behind the type letter; for example, "i16" indicates a 16-bit signed integer. Note that the value behind the type letter must be either 8, 16 or 32.

You should only use element size specifiers on the "i" and "u" types. That is, do not use these specifiers on "f", "s" and "p".

Element ranges:

For passing arrays, the size of the array should be given behind the type letter (and the optional element size). The token "u[4]" indicates an array of four unsigned integers, which are typically 32-bit. The token "i16[8]" is an array of 8 signed 16-bit integers. Arrays are always passed by "copy & copy-back".

When compiled as Unicode, this library converts all strings to Unicode strings, prior to calling the foreign function. Unicode functions should only be used with unpacked strings, since packed strings can only represent 8-bit character sets.

The calling convention for the foreign functions is assumed to be:

- ♦ __stdcall for Win32,
- ♦ far pascal for Win16
- ♦ and the GCC default for Unix/Linux (_cdecl)

 ${\rm C}^{++}$ name mangling of the called function is not handled (there is no standard convention for name mangling, so there is no portable way to convert ${\rm C}^{++}$ function names to mangled names). Win32 name mangling (used by default by Microsoft compilers on functions declared as __stdcall) is also not handled.

See also:

libfree

Free DLL

libfree

Unload a library from memory

Syntax:

bool: libfree(const libname[]="")

libname

The module name or filename of the DLL or of the shared library to remove from memory. If this parameter is an empty string (the default), all libraries that have been loaded by the extension module are removed.

Returns:

true on success, false on failure (the function fails on an attempt to unload a DLL/shared library that was not loaded).

Notes:

Function libcall keeps DLLs or shared libraries in memory after the first call to a function in it. This speeds up the subsequent calls to any of the functions in the same library, but it also increases the memory footprint of the process. You would use libfree to unload DLLs or shared libraries that the script will not be needing again for some time. Doing so reduces the memory footprint of the process. At the next call to libcall, any unloaded library is automatically loaded again.

See also:

libcall

Execute; Process; PID

procexec	Launch an external executable program			
Syntax:	PID: procexec(const commandline[])			
	commandline The filename or complete path of the external program, including any command line options.			
Returns:	An identifier for the new process ("Process ID", or PID) on success, or zero on failure.			
See also:	procread, procwait, procwrite			
	I/O-redirection			

procread		Read output of the external program			
Syntax:	bool: pro	<pre>bool: procread(line[], size=sizeof line,</pre>			
	line	This parameter will contain the output of the external program (the text that the external program wrote to "standard out").			
	size	The size of parameter line parameter, in cells.			
	striplf	If true, and terminating newline and carriage return characters are stripped from parameter line.			

packed If true, the returned text is stored in parameter line

as a packed string; otherwise the string is unpacked.

Returns: true on success, false on failure.

See also: procexec, procwrite

Wait for termination; Process; PID

procwait Wait until an executable program finishes

Syntax: PID: procwait(PID: pid)

The Process ID of the program on which you wish to

wait. This value is returned by procexec.

Returns: This function currently always returns zero.

See also: procexec

I/O-redirection

procwrite Send "input" to the external program

Syntax: bool: procwrite(const line[], bool: appendlf=false)

line The text to send to the external program.

appendlf If true, a newline character is automatically appended

to text that is sent.

Returns: true on success, false on failure.

 $See \ also: \qquad {\tt procexec}, {\tt procread}$

Resources

The PAWN toolkit can be obtained from www.compuphase.com in various formats (binaries and source code archives). The manuals for usage of the language and implementation guides are also available on the site in Adobe Acrobat format (PDF files).

The dyncall library is available at http://www.dyncall.org/.

Index

- \diamond Names of persons (not products) are in italics.
- ♦ Function names, constants and compiler reserved words are in typewriter font.

!	#include, 3	M	Microsoft Windows, 3
A	Abstract Machine, 3 Adobe Acrobat, 10	N	Native functions, 3 registering, 3
Ъ		P	PID, 8
D	DLL, 3		Prefix file, 3
	dyncall, 3, 10		Preprocessor directive, 3
_			procexec, 8
F	Foreign Function Interface, 1		procread, 8
	,		procwait, 9
Н	Host application, 3		procwrite, 9
_		R	Registering, 3
L	libcall, 5	_	
	libfree, 7	S	Security, 2
	Linux, 3		Shared library, 3