

The *cloze* package*

Josef Friedrich

josef@friedrich.rocks

github.com/Josef-Friedrich/cloze

v1.2 from 2016/06/23

*Many thanks to Robert-Michael Huber for his advice and to Paul Isambert for his article "*Three things you can do with LuaTeX that would be extremely painful otherwise*" in TUGboat, Volume 31 (2010), No. 3. This article helped a lot to write this package.

Contents

1	Introduction	3
2	Usage	3
2.1	The commands and environments	3
2.1.1	\cloze	3
2.1.2	\clozesetfont	4
2.1.3	\clozefix	4
2.1.4	\clozefil	5
2.1.5	clozepar	5
2.1.6	\clozeline	5
2.1.7	\clozelinefil	5
2.2	The options	5
2.2.1	Local and global options	5
2.2.2	\clozeset	6
2.2.3	\clozereset	6
2.2.4	\clozeshow and \clozehide	6
2.2.5	align	7
2.2.6	distance	7
2.2.7	hide and show	7
2.2.8	linecolor and textcolor	7
2.2.9	margin	8
2.2.10	thickness	8
2.2.11	width	8
2.3	Special application areas	8
2.3.1	The tabbing environment	8
2.3.2	The picture environment	9
2.3.3	The tabular environment	9
3	Implementation	10
3.1	The file cloze.sty	10
3.1.1	Internal macros	10
3.1.2	Options	11
3.1.2.1	align	12
3.1.2.2	distance	12
3.1.2.3	hide	12
3.1.2.4	linecolor	12
3.1.2.5	margin	13
3.1.2.6	show	13
3.1.2.7	textcolor	13
3.1.2.8	thickness	13
3.1.2.9	width	13
3.1.3	Public macros	13
3.2	The file cloze.lua	16

3.2.0.1	Initialisation of the function tables	16
3.2.1	Node precessing (node)	17
3.2.1.1	Color handling (color)	17
3.2.1.2	Line handling (line)	18
3.2.1.3	Handling of extendable lines (linefil)	19
3.2.1.4	Kern handling (kern)	20
3.2.2	Option handling (registry)	20
3.2.2.1	Marker processing (marker)	21
3.2.2.2	Storage functions (storage)	23
3.2.2.3	Option processing (option)	23
3.2.3	Assembly to cloze texts (cloze)	25
3.2.3.1	Paragraph	25
3.2.3.2	Tabular environment	26
3.2.3.3	Picture environment	26
3.2.4	Basic module functions (base)	31

1 Introduction

cloze is a L^AT_EX package to generate cloze texts. It uses the capabilities of the modern T_EX engine *LuaT_EX*. Therefore, you must use LuaL^AT_EX to create documents containing gaps.

```
lualatex cloze-text.tex
```

The main feature of the package is that the formatting doesn't change when using the `hide` and `show` (→ 2.2.7) options.

Lorem ipsum dolor sit amet, consectetur adipisicing elit, sed do eiusmod tempor
 incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud
 exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

The command `\clozeset{hide}` only shows gaps. When you put both texts on top of each other you will see that they perfectly match.

Lorem ipsum _____ amet, consectetur _____ elit, sed do eiusmod tempor
 incididunt ut labore et _____ aliqua. Ut enim ad minim veniam, quis nostrud
 _____ ullamco laboris nisi ut _____ ex ea commodo consequat.

2 Usage

There are three commands and one environment to generate cloze texts: `\cloze`, `\clozefix`, `\clozefil` and `clozepar`.

2.1 The commands and environments

2.1.1 `\cloze`

`\cloze` `\cloze[<options>]{<some text>}`: The command `\cloze` is similar to a command that offers the possibility to underline the texts. `\cloze` does not prevent line breaks. The width of a gap depends on the number of letters and the font used. The only option which affects the widths of a gap is the option `margin` (→ 2.2.9).

Lorem ipsum dolor sit amet, consectetur adipisicing elit, sed do eiusmod tempor
 incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud
 exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

It is possible to convert a complete paragraph into a 'gap'. But don't forget: There is a special environment for this: `clozepar` (→ 2.1.5).

Lorem ipsum dolor sit amet, consectetur adipisicing elit, sed do eiusmod tempor
 incididunt ut labore et dolore magna aliqua. Ut enim ad minim veniam, quis nostrud
 exercitation ullamco laboris nisi ut aliquip ex ea commodo consequat.

The command `\cloze` doesn't change the behavior of the hyphenation. Let's try some long German words:

es Telekommunikationsüberwachung geht Unternehmenssteuerfortentwicklungs-
gesetz Abteilungsleiterin Oberkommisarin auch Filialeiterin kurz Oberkommisarin Unternehmenssteuerfortentwicklungs-
gesetz Filialeiterin Metzgermeisterin in Abteilungsleiterin der Oberkommisarin Hochleistungsflüssigkeitschromato-
graphie Filialeiterin Kürze Unternehmenssteuerfortentwicklungs-gesetz Metzger-
meisterin liegt Abteilungsleiterin die Metzgermeisterin Abteilungsleiterin Würze
Oberkommisarin

2.1.2 \clozesetfont

\clozesetfont The gap font can be changed by using the command \clozesetfont. \clozesetfont redefines the command \clozefont which contains the font definition. Thus, the command \clozesetfont{\Large} has the same effect as \renewcommand{\clozefont}{\Large}.

Excepteur sint occaecat cupidatat non proident.

Please do not put any color definitions in \clozesetfont, as it won't work. Use the option `textcolor` instead (→ 2.2.8).

\clozesetfont{\ttfamily\normalsize} changes the gap text for example into a normal sized typewriter font.

Excepteur sint occaecat cupidatat non proident.

2.1.3 \clozefix

\clozefix \clozefix[*options*]{*some text*}: The command \clozefix creates gaps with a fixed width. The clozes are default concerning the width 2cm.

Lorem ipsum dolor sit amet:
 1. consectetur
 2. adipisicing
 3. elit
 sed do eiusmod.

Gaps with a fixed width are much harder to solve.

Lorem ipsum dolor sit amet, consectetur adipisicing elit, sed do eiusmod tempor incididunt ut labore et dolore magna aliqua.

Using the option `align` you can make nice tabulars like this:

Composer	Life span
<u>Joseph Haydn</u>	<u>1732-1809</u>
<u>Wolfgang Amadeus Mozart</u>	<u>1756-1791</u>
<u>Ludwig van Beethoven</u>	<u>1770-1827</u>

2.1.4 \clozefil

\clozefil \clozefil[*options*]{*some text*}: The name of the command is inspired by \hfil, \hfill, and \hfilll. Only \clozefil fills out all available horizontal spaces with a line.

```
    Lorem ipsum dolor sit amet, consectetur adipisicing elit, sed do eiusmod.  
    Ut enim ad minim veniam _____ exercitiation.
```

2.1.5 clozepar

clozepar \begin{clozepar}[*options*] ...*some text* ...\end{clozepar}: The environment clozepar transforms a complete paragraph into a cloze text. The options align, margin and width have no effect on this environment.

```
    Lorem ipsum dolor sit amet, consectetur adipisicing elit ullamco laboris nisi.  
    Ut enim ad minim veniam, quis nostrud exercitation ullamco laboris nisi ut aliquip  
    ex ea commodo consequat. Duis aute irure dolor in reprehenderit in voluptate velit  
    esse cillum.  
    Excepteur sint occaecat cupidatat non proident.
```

2.1.6 \clozeline

\clozeline \clozeline[*options*]: To create a cloze line of a certain width, use the command \clozeline. The default width of the line is 2cm. In combination with the other cloze commands you can create for example an irregular alignment of the cloze text.

```
    Ut enim ad  
    \clozeline[width=1cm]\cloze{minim}\clozeline[width=3cm]  
    minim veniam
```

```
    Ut enim ad _____ minim _____ minim veniam,
```

2.1.7 \clozelinefil

\clozelinefil \clozelinefil[*options*]: This command \clozelinefil fills the complete available horizontal space with a line. Moreover, \clozelinefil was used to create \clozefil.

```
    Lorem_____
```

2.2 The options

2.2.1 Local and global options

The cloze package distinguishes between *local* and *global* options. Besides the possibility to set *global* options in the \usepackage[*global options*]{cloze} declaration, the cloze package offers a special command to set *global* options: \clozeset{*global options*}

2.2.2 \clozeset

\clozeset \clozeset{\langle global options \rangle}: The command can set *global* options for each paragraph.

```
\clozeset{textcolor=red} Lorem \cloze{ipsum} dolor \par  
\clozeset{textcolor=green} Lorem \cloze{ipsum} dolor
```

```
  Lorem ipsum dolor  
  Lorem ipsum dolor
```

\clozeset does not change the options within a paragraph. As you can see in the example below the last \clozeset applies the color green for both gaps.

```
\clozeset{textcolor=red} Lorem \cloze{ipsum} dolor  
\clozeset{textcolor=green} Lorem \cloze{ipsum} dolor
```

```
  Lorem ipsum dolor  Lorem ipsum dolor
```

2.2.3 \clozereset

\clozereset \clozereset: The command resets all *global* options to the default values. It has no effect on the *local* options.

```
\clozeset{  
  thickness=3mm,  
  linecolor=yellow,  
  textcolor=magenta,  
  margin=-2pt  
}
```

```
Very silly global options
```

```
\clozereset
```

```
Relax! We can reset those options.
```

2.2.4 \clozeshow and \clozehide

\clozeshow \clozeshow and \clozehide: This commands are shortcuts for \clozeset{\langle show \rangle} and \clozeset{\langle hide \rangle}.

```
\clozehide
```

```
  Lorem _____ amet, consectetur _____ elit.
```

```
\clozeshow
```

```
  Lorem ipsum dolor sit amet, consectetur adipisicing elit.
```

2.2.5 align

[align=⟨left/center/right⟩]: Only the macro \clozefix (→ 2.1.3) takes the option `align` into account. Possible values are `left`, `center` and `right`. This option only makes sense, if the width of the line is larger than the width of the text.

<i>Lorem ipsum</i>			
	<i>Lorem ipsum</i>		(left)
		<i>Lorem ipsum</i>	(center)
			(right)

2.2.6 distance

[distance=⟨dimen⟩]: The option `distance` specifies the spacing between the baseline of the text and the gap line. The larger the dimension of the option `distance`, the more moves the line down. Negative values cause the line to appear above the baseline. The default value is 1.5pt.

<i>Lorem ipsum dolor sit amet.</i>		(1.5pt)
<i>Lorem ipsum dolor sit amet.</i>		(3pt)
<i>Lorem ipsum dolor sit amet.</i>		(-3pt)

2.2.7 hide and show

[`hide`] and [`show`]: By default the cloze text is displayed. Use the option `hide` to remove the cloze text from the output. If you accidentally specify both options – `hide` and `show` – the last option "wins".

			(hide)
			(show)
			(show,hide)
			(hide,show)

2.2.8 linecolor and textcolor

[`linecolor=⟨color name⟩`] and [`textcolor=⟨color name⟩`]: Values for both color options are color names used by the xcolor package. To define your own color use the following command:

```
\definecolor{myclozecolor}{rgb}{0.1,0.4,0.6}
\cloze[textcolor=myclozecolor]{Lorem ipsum}
```

<i>Lorem ipsum dolor sit amet, consectetur</i>		(myclozecolor)
<i> </i>		(red)
<i> </i>		(green)

You can use the same color names to colorize the cloze lines.

<i> </i>		(myclozecolor)
<i> </i>		(red)
<i> </i>		(green)

2.2.9 margin

[margin=<dimen>]: The option `margin` indicates how far the line sticks up from the text. The option can be used with the commands `\cloze`, `\clozefix` and `\clozefil`. The default value of the option is 3pt.

Lore ipsum <u>dolor</u> sit amet.	(0pt)
Lore ipsum <u>dolor</u> sit amet.	(5mm)
Lore ipsum <u>dolor</u> sit amet.	(1cm)
Lore ipsum <u>dolor</u> sit amet.	(6em)
Lore ipsum <u>dolor</u> sit amet.	(-4pt)

Is a punctuation mark placed directly after a gap, then the line breaks after this punctuation mark. Even the most large value of `margin` does not affect this behavior.

<u>Lore</u> ,	<u>ipsum</u> ,	<u>dolor</u> ;	<u>sit</u> :	<u>amet</u> ,	<u>consectetur</u> .
<u>adipiscing</u> ;	<u>elit</u> :	<u>sed</u> ,	<u>do</u> ,	<u>eiusmod</u> ,	<u>tempor</u> .

2.2.10 thickness

[thickness=<dimen>]: The option `thickness` indicates how thick the line is. The option `distance` (→ 2.2.6) is not affected by this option, because the bottom of the line moves down. The default value of this option is 0.4pt.

Lore <u>ipsum dolor sit</u> amet.	(0.01pt)
Lore <u>ipsum dolor sit</u> amet.	(1pt)
Lore <u>ipsum dolor sit</u> amet.	(2pt)

2.2.11 width

[width=<dimen>]: The only command which can be changed by the option `width` is `\clozefix` (→ 2.1.3). The default value of the option is 2cm.

Lore <u>dolor</u> amet.	(3cm)
Lore <u>dolor</u> amet.	(5cm)
Lore <u>dolor</u> amet.	(7cm)

2.3 Special application areas


2.3.1 The tabbing environment

```
\begin{tabbing}
col1 \hspace{1cm} \= col2 \hspace{1cm} \= col3 \hspace{1cm} \= col4 \\
\cloze{col1} \> \> \clozefix{col3} \\
\end{tabbing}
```

col1	col2	col3	col4
<u>col1</u>		<u>col3</u>	

2.3.2 The picture environment

```
\begin{picture}(320,100)
\put(80,25){\cloze{Lorem}}
\put(160,50){\clozefix{ipsum}}
\put(240,75){\clozefill{dolor}}
\end{picture}
```



2.3.3 The tabular environment

```
\begin{tabular}{l c}
\cloze{Lorem} & \cloze{ipsum} \\
\clozefix{amet} & \clozefix{consectetur} \\
\cloze{sed} & \cloze{do} \\
\end{tabular}
```

<u> <i> Lorem </i></u>	<u> <i> ipsum </i></u>
<u> <i> amet </i></u>	<u> <i> consectetur </i></u>
<u> <i> sed </i></u>	<u> <i> do </i></u>

3 Implementation

3.1 The file cloze.sty

This four packages are used to build *cloze*:

- `fontspec` is not necessarily required. When using Lua^LA_TE_X it is good form to load it. Apart from this the package supplies helpful messages, when you compile a Lua^LA_TE_X document with pdflA_TE_X.
- `luatexbase` allows to register multiple Lua callbacks.
- `kvoptions` takes the handling of the options.
- `xcolor` is required to colorize the text and the line of a gap.

```
26 \RequirePackage{fontspec,luatexbase-mcb,kvoptions,xcolor}
```

Load the cloze lua module and put all return values in the variable `cloze`.

```
27 \directlua{  
28   cloze = require('cloze')  
29 }
```

3.1.1 Internal macros

`\cloze@set@to@global` Set the Lua variable `registry.is_global` to `true`. All options are then stored in the variable `registry.global_options`.

```
30 \def\cloze@set@to@global{  
31   \directlua{cloze.set_is_global(true)}  
32 }
```

`\cloze@set@to@local` First unset the variable `registry.local_options`. Now set the Lua variable `registry.is_global` to `false`. All options are then stored in the variable `registry.local_options`.

```
33 \def\cloze@set@to@local{  
34   \directlua{  
35     cloze.unset_local_options()  
36     cloze.set_is_global(false)  
37   }  
38 }
```

`\cloze@set@option` `\cloze@set@option` is a wrapper for the Lua function `registry.set_option`. `\cloze@set@option[<key>]{<value>}` sets a key `<key>` to the value `<value>`.

```
39 \def\cloze@set@option[#1]#2{  
40   \directlua{cloze.set_option('#1', '#2')}  
41 }
```

`\cloze@color` Convert a color definiton name to a PDF colorstack string, for example convert the color name `blue` to the colorstack string `0 0 1 rg 0 0 1 RG`. The macro definition `\cloze@color{blue}` builds itself the macro `\color@blue`, which expands to the PDF colorstack string. The colorstack string is necessary to generate a PDF colorstack whatsit.

```
42 \def\cloze@color#1{\csname\string\color@#1\endcsname}
```

`\cloze@set@local@options` This macro is used in all cloze commands to handle the optional arguments. First it sets the option storage to local and then it commits the options to the package `kvoptions` via the macro `\kvsetkeys{CLZ}{}`.

```
43 \def\cloze@set@local@options#1{%
44   \cloze@set@to@local%
45   \kvsetkeys{CLZ}{#1}%
46 }
```

`\cloze@start@marker` At the begining `\cloze@start@marker` registers the required Lua callbacks. Then it inserts a whatsit marker which marks the begin of a gap.

```
47 \def\cloze@start@marker#1{%
48   \strut\directlua{%
49     cloze.register('#1')
50     cloze.marker('#1', 'start')
51   }%
52 }
```

`\cloze@stop@marker` `\cloze@stop@marker` inserts a whatsit marker that marks the end of gap.

```
53 \def\cloze@stop@marker#1{%
54   \strut\directlua{%
55     cloze.marker('#1', 'stop')
56   }%
57 }
```

`\cloze@margin` `\cloze@margin` surrounds a text in a gap with two kerns.

```
58 \def\cloze@margin#1{%
59   \directlua{cloze.margin()}%
60   #1%
61   \directlua{cloze.margin()}%
62 }
```

3.1.2 Options

`cloze` offers key-value pairs to use as options. For processing the key-value pairs we use the package `kvoptions`. To make all key-value pairs accessibly to Lua code, we use the declaration `\define@key{⟨CLZ⟩}{⟨option⟩}[⟨/⟩]{⟨...⟩}`. This declaration comes from the package `keyval`.

At start all values are declared as global options. At the Lua side all values are now stored in the `registry.global_options` table.

```
63 \cloze@set@to@global
```

We use the abbreviation `CLZ` for `cloze` as family name and prefix.

```
64 \SetupKeyvalOptions{  
65   family=CLZ,  
66   prefix=CLZ@  
67 }
```

3.1.2.1 align

Please read the section (→ 2.2.5) how to use the option `align`. `align` affects only the command `\clozefix` (→ 2.1.3).

```
68 \DeclareStringOption{align}  
69 \define@key{CLZ}{align}[]{\cloze@set@option[align]{#1}}
```

3.1.2.2 distance

Please read the section (→ 2.2.6) how to use the option `distance`.

```
70 \DeclareStringOption{distance}  
71 \define@key{CLZ}{distance}[]{\cloze@set@option[distance]{#1}}
```

3.1.2.3 hide

If the option `hide` appears in the commands, `hide` will be set to `true` and `show` to `false` on the Lua side. Please read the section (→ 2.2.7) how to use the option `hide`.

```
72 \DeclareVoidOption{hide}{%  
73   \cloze@set@option[hide]{true}%;  
74   \cloze@set@option[show]{false}%;  
75 }
```

3.1.2.4 linecolor

Please read the section (→ 2.2.8) how to use the option `linecolor`.

```
76 \DeclareStringOption{linecolor}  
77 \define@key{CLZ}{linecolor}[]{%  
78   \cloze@set@option[linecolor]{\cloze@color{#1}}%;  
79 }
```

3.1.2.5 margin

Please read the section (→ 2.2.9) how to use the option `margin`.

```
80 \DeclareStringOption{margin}
81 \define@key{CLZ}{margin}[]{\cloze@set@option[margin]{#1}}
```

3.1.2.6 show

If the option `show` appears in the commands, `show` will be set to `true` and `true` to `false` on the Lua side. Please read the section (→ 2.2.7) how to use the option `show`.

```
82 \DeclareVoidOption{show}{%
83   \cloze@set@option[show]{true}%
84   \cloze@set@option[hide]{false}%
85 }
```

3.1.2.7 textcolor

Please read the section (→ 2.2.8) how to use the option `textcolor`.

```
86 \DeclareStringOption{textcolor}
87 \define@key{CLZ}{textcolor}[]{%
88   \cloze@set@option[textcolor]{\cloze@color{#1}}%
89 }
```

3.1.2.8 thickness

Please read the section (→ 2.2.10) how to use the option `thickness`.

```
90 \DeclareStringOption{thickness}
91 \define@key{CLZ}{thickness}[]{\cloze@set@option[thickness]{#1}}
```

3.1.2.9 width

Please read the section (→ 2.2.11) how to use the option `width`. `width` affects only the command `\clozefix` (→ 2.1.3).

```
92 \DeclareStringOption{width}
93 \define@key{CLZ}{width}[]{\cloze@set@option[width]{#1}}
94 \ProcessKeyvalOptions{CLZ}
```

3.1.3 Public macros

All public macros are prefixed with `\cloze`.

`\clozeset` The usage of the command `\clozeset` is described in detail in section (→ [2.2.2](#)).

```
95 \newcommand{\clozeset}[1]{%
96   \cloze@set@to@global%
97   \kvsetkeys{CLZ}{#1}%
98 }
```

`\clozereset` The usage of the command `\clozereset` is described in detail in section (→ [2.2.3](#)).

```
99 \newcommand{\clozereset}{%
100   \directlua{cloze.reset()}%
101 }
```

`\clozeshow` The usage of the command `\clozeshow` is described in detail in section (→ [2.2.4](#)).

```
102 \newcommand{\clozeshow}{%
103   \clozeset{show}%
104 }
```

`\clozehide` The usage of the command `\clozehide` is described in detail in section (→ [2.2.4](#)).

```
105 \newcommand{\clozehide}{%
106   \clozeset{hide}%
107 }
```

`\clozefont` The usage of the command `\clozefont` is described in detail in section (→ [2.1.2](#)).

```
108 \newcommand{\clozefont}{\itshape}
```

`\clozesetfont` The usage of the command `\clozesetfont` is described in detail in section (→ [2.1.2](#)).

```
109 \newcommand{\clozesetfont}[1]{%
110   \renewcommand{\clozefont}[1]{%
111     #1%
112   }%
113 }
```

`\cloze` The usage of the command `\cloze` is described in detail in section (→ [2.1.1](#)).

```
114 \newcommand{\cloze}[2][]{%
115   \cloze@set@local@options{#1}%
116   \cloze@start@marker{basic}%
117   {%
118     \clozefont\relax%
119     \cloze@margin{#2}%
120   }
```

```
120  }%
121  \cloze@stop@marker{basic}%
122 }
```

\clozefix The usage of the command `\clozefix` is described in detail in section (→ 2.1.3).

```
123 \newcommand{\clozefix}[2] []{%
124   \cloze@set@local@options{#1}%
125   \cloze@start@marker{fix}%
126   {%
127     \clozefont\relax%
128     \cloze@margin{#2}%
129   }%
130   \cloze@stop@marker{fix}%
131 }
```

\clozepar The usage of the environment `\clozepar` is described in detail in section (→ 2.1.5).

```
132 \newenvironment{\clozepar}[1] []{%
133 {%
134   \par%
135   \cloze@set@local@options{#1}%
136   \cloze@start@marker{par}%
137   \clozefont\relax%
138 }%
139 {%
140   \cloze@stop@marker{par}%
141   \par%
142   \directlua{\cloze.unregister('par')}%
143 }
```

\clozefil The usage of the command `\clozefil` is described in detail in section (→ 2.1.4).

```
144 \newcommand{\clozefil}[2] []{%
145   \cloze[#1]{#2}\clozelinefil[#1]%
146 }
```

\clozeline The usage of the command `\clozeline` is described in detail in section (→ 2.1.6).

```
147 \newcommand{\clozeline}[1] []{%
148   \cloze@set@local@options{#1}%
149   \directlua{\cloze.line()}%
150 }
```

\clozelinefil The usage of the command `\clozelinefil` is described in detail in section (→ 2.1.7).

```
151 \newcommand{\clozelinefil}[1] []{%
152   \cloze@set@local@options{#1}%
```

```

153   \strut%
154   \directlua{cloze.linefil()}%
155   \strut%
156 }

```

3.2 The file cloze.lua

3.2.0.1 Initialisation of the function tables

It is good form to provide some background informations about this Lua module.

```

1 if not modules then modules = {} end modules ['cloze'] = {
2   version    = '0.1',
3   comment    = 'cloze',
4   author     = 'Josef Friedrich, R.-M. Huber',
5   copyright  = 'Josef Friedrich, R.-M. Huber',
6   license    = 'The LaTeX Project Public License Version 1.3c 2008-05-04'
7 }

```

`nodeX` is a abbreviation for *node eXtended*.

```
8 local nodeX = {}
```

All values and functions, which are related to the option management, are stored in a table called `registry`.

```
9 local registry = {}
```

I didn't know what value I should take as `user_id`. Therefore I took my birthday and transformed it to a large number.

```

10 registry.user_id = 3121978
11 registry.storage = {}
12 registry.defaults = {
13   ['align'] = 'l',
14   ['distance'] = '1.5pt',
15   ['hide'] = false,
16   ['linecolor'] = '0 0 0 rg 0 0 0 RG', -- black
17   ['margin'] = '3pt',
18   ['resetcolor'] = '0 0 0 rg 0 0 0 RG', -- black
19   ['show_text'] = true,
20   ['show'] = true,
21   ['textcolor'] = '0 0 1 rg 0 0 1 RG', -- blue
22   ['thickness'] = '0.4pt',
23   ['width'] = '2cm',
24 }
25 registry.global_options = {}
26 registry.local_options = {}

```

All those functions are stored in the table `cloze` that are registered as callbacks to the pre and post linebreak filters.

```
27 local cloze = {}
```

In the status table are stored state information, which are necessary for the recursive cloze generation.

```
28 cloze.status = {}
```

The `base` table contains some basic functions. `base` is the only table of this Lua module that will be exported.

```
29 local base = {}
30 base.is_registered = {}
```

3.2.1 Node precessing (nodeX)

All functions in this section are stored in a table called `nodeX`. `nodeX` is a abbreviation for *node eXtended*. The `nodeX` table bundles all functions, which extend the built-in `node` library.

3.2.1.1 Color handling (color)

`create_colorstack`

Create a whatsit node of the subtype `pdf_colorstack`. `data` is a PDF colorstack string like `0 0 0 rg 0 0 0 RG`.

```
31 function nodex.create_colorstack(data)
32   if not data then
33     data = '0 0 0 rg 0 0 0 RG' -- black
34   end
35   local whatsit = node.new('whatsit', 'pdf_colorstack')
36   whatsit.stack = 0
37   whatsit.data = data
38   return whatsit
39 end
```

`create_color`

`nodex.create_color()` is a wrapper for the function `nodex.create_colorstack()`. It queries the current values of the options `linecolor` and `textcolor`. The argument `option` accepts the strings `line`, `text` and `reset`.

```
40 function nodex.create_color(option)
41   local data
42   if option == 'line' then
43     data = registry.get_value('linecolor')
44   elseif option == 'text' then
45     data = registry.get_value('textcolor')
46   elseif option == 'reset' then
47     data = nil
```

```

48   else
49     data = nil
50   end
51   return nodex.create_colorstack(data)
52 end

```

3.2.1.2 Line handling (line)

`create_line`

Create a rule node, which is used as a line for the cloze texts. The `depth` and the `height` of the rule are calculated from the options `thickness` and `distance`. The argument `width` must have the length unit *scaled points*.

```

53 function nodex.create_line(width)
54   local rule = node.new(node.id('rule'))
55   local thickness = tex.sp(registry.get_value('thickness'))
56   local distance = tex.sp(registry.get_value('distance'))
57   rule.depth = distance + thickness
58   rule.height = - distance
59   rule.width = width
60   return rule
61 end

```

`insert_list`

Insert a list of nodes after or before the `current`. The `head` argument is optional. In some edge cases it is unfortunately necessary. If `head` is omitted the `current` node is used. The argument `position` can take the values 'after' or 'before'.

```

62 function nodex.insert_list(position, current, list, head)
63   if not head then
64     head = current
65   end
66   for i, insert in ipairs(list) do
67     if position == 'after' then
68       head, current = node.insert_after(head, current, insert)
69     elseif position == 'before' then
70       head, current = node.insert_before(head, current, insert)
71     end
72   end
73   return current
74 end

```

`insert_line`

Enclose a rule node (cloze line) with two PDF colorstack whatsits. The first colorstack node dyes the line, the second resets the color.

Node list:

Variable name	Node type	Node subtype	Parameter
<code>n.color_line</code>	whatsit	pdf_colorstack	Line color
<code>n.line</code>	rule		width
<code>n.color_reset</code>	whatsit	pdf_colorstack	Reset color

```
75 function nodex.insert_line(current, width)
```

```

76     return nodex.insert_list(
77         'after',
78         current,
79         {
80             nodex.create_color('line'),
81             nodex.create_line(width),
82             nodex.create_color('reset')
83         }
84     )
85 end

```

write_line

This function encloses a rule node with color nodes as it the function `nodex.insert_line` does. In contrast to `nodex.insert_line` the three nodes are appended to TeX's 'current list'. They are not inserted in a node list, which is accessed by a Lua callback.

Node list:

Variable name	Node type	Node subtype	Parameter
-	whatsit	pdf_colorstack	Line color
-	rule		width
-	whatsit	pdf_colorstack	Reset color

```

86 function nodex.write_line()
87     node.write(nodex.create_color('line'))
88     node.write(nodex.create_line(tex.sp(registry.get_value('width'))))
89     node.write(nodex.create_color('reset'))
90 end

```

3.2.1.3 Handling of extendable lines (linefil)

create_linefil

This function creates a line which stretches indefinitely in the horizontal direction.

```

91 function nodex.create_linefil()
92     local glue = node.new('glue')
93     glue.subtype = 100
94     glue.stretch = 65536
95     glue.stretch_order = 3
96     local rule = nodex.create_line(0)
97     rule.dir = 'TLT'
98     glue.leader = rule
99     return glue
100 end

```

write_linefil

The function `nodex.write_linefil` surrounds a indefinitely stretchable line with color whatsits and puts it to TeX's 'current (node) list'.

```

101 function nodex.write_linefil()
102     node.write(nodex.create_color('line'))
103     node.write(nodex.create_linefil())
104     node.write(nodex.create_color('reset'))
105 end

```

3.2.1.4 Kern handling (kern)

`create_kern`

This function creates a kern node with a given width. The argument `width` had to be specified in scaled points.

```
106 function nodex.create_kern(width)
107   local kern = node.new(node.id('kern'))
108   kern.kern = width
109   return kern
110 end
```

`strut_to_hlist`

To make life easier: We add at the beginning of each hlist a strut. Now we can add line, color etc. nodes after the first node of a hlist not before - after is much more easier.

```
111 function nodex.strut_to_hlist(hlist)
112   local n = {} -- node
113   n.head = hlist.head
114   n.kern = nodex.create_kern(0)
115   n.strut = node.insert_before(n.head, n.head, n.kern)
116   hlist.head = n.head.prev
117   return hlist, n.strut, n.head
118 end
```

`write_margin`

Write kern nodes to the current node list. This kern nodes can be used to build a margin.

```
119 function nodex.write_margin()
120   local kern = nodex.create_kern(tex.sp(registry.get_value('margin')))
121   node.write(kern)
122 end
```

`search_hlist`

Search for a hlist (subtype line). Return false, if no hlist can be found.

```
123 function nodex.search_hlist(head)
124   while head do
125     if head.id == node.id('hlist') and head.subtype == 1 then
126       return nodex.strut_to_hlist(head)
127     end
128     head = head.next
129   end
130   return false
131 end
```

3.2.2 Option handling (registry)

The table `registry` bundles functions that deal with option handling.

3.2.2.1 Marker processing (marker)

A marker is a whatsit node of the subtype `user_defined`. A marker has two purposes:

1. Mark the begin and the end of a gap.
2. Store a index number, that points to a Lua table, which holds some additional data like the local options.

`create_marker`

We create a user defined whatsit node that can store a number (type = 100). In order to distinguish this node from other user defined whatsit nodes we set the `user_id` to a large number. We call this whatsit node a marker. The argument `index` is a number, which is associated to values in the `registry.storage` table.

```
132 function registry.create_marker(index)
133   local marker = node.new('whatsit','user_defined')
134   marker.type = 100 -- number
135   marker.user_id = registry.user_id
136   marker.value = index
137   return marker
138 end
```

`write_marker`

Write a marker node to `TEX`'s current node list. The argument `mode` accepts the string values `basic`, `fix` and `par`. The argument `position`. The argument `position` is either set to `start` or to `stop`.

```
139 function registry.write_marker(mode, position)
140   local index = registry.set_storage(mode, position)
141   local marker = registry.create_marker(index)
142   node.write(marker)
143 end
```

`is_marker`

This functions checks if the given node `item` is a marker.

```
144 function registry.is_marker(item)
145   if item.id == node.id('whatsit')
146     and item.subtype == node.subtype('user_defined')
147     and item.user_id == registry.user_id then
148     return true
149   else
150     return false
151   end
152 end
```

`check_marker`

This functions tests, whether the given node `item` is a marker. The argument `item` is a node. The argument `mode` accepts the string values `basic`, `fix` and `par`. The argument `position` is either set to `start` or to `stop`.

```
153 function registry.check_marker(item, mode, position)
```

```

154   local data = registry.get_marker_data(item)
155   if data and data.mode == mode and data.position == position then
156     return true
157   else
158     return false
159   end
160 end
get_marker
    registry.get_marker returns the given marker. The argument item is a node.
    The argument mode accepts the string values basic, fix and par. The argument
    position is either set to start or to stop.

161 function registry.get_marker(item, mode, position)
162   local out
163   if registry.check_marker(item, mode, position) then
164     out = item
165   else
166     out = false
167   end
168   if out and position == 'start' then
169     registry.get_marker_values(item)
170   end
171   return out
172 end
get_marker_data
    registry.get_marker_data tests whether the node item is a marker. The argu-
    ment item is a node of unspecified type.

173 function registry.get_marker_data(item)
174   if item.id == node.id('whatsit')
175     and item.subtype == node.subtype('user_defined')
176     and item.user_id == registry.user_id then
177       return registry.get_storage(item.value)
178   else
179     return false
180   end
181 end
get_marker_values
    First this function saves the associated values of a marker to the local options
    table. Second it returns this values. The argument marker is a whatsit node.

182 function registry.get_marker_values(marker)
183   local data = registry.get_marker_data(marker)
184   registry.local_options = data.values
185   return data.values
186 end
remove_marker
    This function removes a given whatsit marker. It only deletes a node, if a marker
    is given.

```

```

187 function registry.remove_marker(marker)
188   if registry.is_marker(marker) then node.remove(marker, marker) end
189 end

```

3.2.2.2 Storage functions (storage)

`get_index`

`registry.index` is a counter. The functions `registry.get_index()` increases the counter by one and then returns it.

```

190 function registry.get_index()
191   if not registry.index then
192     registry.index = 0
193   end
194   registry.index = registry.index + 1
195   return registry.index
196 end

```

`set_storage`

`registry.set_storage()` stores the local options in the Lua table `registry.storage`. It returns a numeric index number. This index number is the key, where the local options in the Lua table are stored. The argument `mode` accepts the string values `basic`, `fix` and `par`.

```

197 function registry.set_storage(mode, position)
198   local index = registry.get_index()
199   local data = {
200     ['mode'] = mode,
201     ['position'] = position
202   }
203   data.values = registry.local_options
204   registry.storage[index] = data
205   return index
206 end

```

`get_storage`

The function `registry.get_storage()` retrieves values which belong to a whatsit marker. The argument `index` is a numeric value.

```

207 function registry.get_storage(index)
208   return registry.storage[index]
209 end

```

3.2.2.3 Option processing (option)

`set_option`

This function stores a value `value` and his associated key `key` either to the global (`registry.global_options`) or to the local (`registry.local_options`) option table. The global boolean variable `registry.local_options` controls in which table the values are stored.

```

210 function registry.set_option(key, value)
211   if value == '' or value == '\\color@' then

```

```

212     return false
213   end
214   if registry.is_global == true then
215     registry.global_options[key] = value
216   else
217     registry.local_options[key] = value
218   end
219 end

set_is_global
  registry.set_is_global() sets the variable registry.is_global to the value
  value. It is intended, that the variable takes boolean values.

220 function registry.set_is_global(value)
221   registry.is_global = value
222 end

unset_local_options
  This function unsets the local options.

223 function registry.unset_local_options()
224   registry.local_options = {}
225 end

unset_global_options
  registry.unset_global_options empties the global options storage.

226 function registry.unset_global_options()
227   registry.global_options = {}
228 end

get_value
  Retrieve a value from a given key. First search for the value in the local options,
  then in the global options. If both option storages are empty, the default value
  will be returned.

229 function registry.get_value(key)
230   if registry.has_value(registry.local_options[key]) then
231     return registry.local_options[key]
232   end
233   if registry.has_value(registry.global_options[key]) then
234     return registry.global_options[key]
235   end
236   return registry.defaults[key]
237 end

get_value_show
  The function registry.get_value_show() returns the boolean value true if the
  option show is true. In contrast to the function registry.get_value() it converts
  the string value ‘true’ to a boolean value.

238 function registry.get_value_show()
239   if
240     registry.get_value('show') == true
241   or

```

```
242     registry.get_value('show') == 'true'
243   then
244     return true
245   else
246     return false
247 end
248 end

has_value
This function tests whether the value value is not empty and has a value.

249 function registry.has_value(value)
250   if value == nil or value == '' or value == '\\color@' then
251     return false
252   else
253     return true
254 end
255 end


get_defaults
registry.get_defaults(option) returns a the default value of the given option.

256 function registry.get_defaults(option)
257   return registry.defaults[option]
258 end
```


3.2.3 Assembly to cloze texts (cloze)

Some graphics for better understanding of the node tree:


3.2.3.1 Paragraph



3.2.3.2 Tabular environment



3.2.3.3 Picture environment



basic_make

The function `cloze.basic_make()` makes one gap. The argument `start` is the node, where the gap begins. The argument `stop` is the node, where the gap ends.

```
259 function cloze.basic_make(start, stop)
260   local n = {}
261   local l = {}
262   n.head = start
263   if not start or not stop then
264     return
265   end
266   n.start = start
267   n.stop = stop
268   l.width = node.dimensions(
269     cloze.status.hlist.glue_set,
270     cloze.status.hlist.glue_sign,
271     cloze.status.hlist.glue_order,
272     n.start,
273     n.stop
274   )
275   n.line = nodex.insert_line(n.start, l.width)
```

```

276   n.color_text = nodex.insert_list('after', n.line, {nodex.create_color('text')})
277   if registry.get_value_show() then
278     nodex.insert_list('after', n.color_text, {nodex.create_kern(-l.width)})
279     nodex.insert_list('before', n.stop, {nodex.create_color('reset')}, n.head)
280   else
281     n.line.next = n.stop.next
282     n.stop.prev = n.line.prev
283   end

```

In some edge cases the lua callbacks get fired up twice. After the cloze has been created, the start and stop whatsit markers can be deleted.

```

284   registry.remove_marker(n.start)
285   registry.remove_marker(n.stop)
286 end

```

`basic_search_stop`

Search for a stop marker.

```

287 function cloze.basic_search_stop(head)
288   local stop
289   while head do
290     cloze.status.continue = true
291     stop = head
292     if registry.check_marker(stop, 'basic', 'stop') then
293       cloze.status.continue = false
294       break
295     end
296     head = head.next
297   end
298   return stop
299 end

```

`basic_search_start`

Search for a start marker. Also begin a new cloze, if the boolean value `cloze.status.continue` is true. The knowledge of the last hlist node is a requirement to begin a cloze.

```

300 function cloze.basic_search_start(head)
301   local start
302   local stop
303   local n = {}
304   if cloze.status.continue then
305     n.hlist = nodex.search_hlist(head)
306     if n.hlist then
307       cloze.status.hlist = n.hlist
308       start = cloze.status.hlist.head
309     end
310   elseif registry.check_marker(head, 'basic', 'start') then
311     start = head
312   end
313   if start then

```

```

314     stop = cloze.basic_search_stop(start)
315     cloze.basic_make(start, stop)
316   end
317 end

```

`basic_recursion`

Parse recursivley the node tree. Start and stop markers can be nested deeply into the node tree.

```

318 function cloze.basic_recursion(head)
319   while head do
320     if head.head then
321       cloze.status.hlist = head
322       cloze.basic_recursion(head.head)
323     else
324       cloze.basic_search_start(head)
325     end
326     head = head.next
327   end
328 end

```

`basic`

The corresponding L^AT_EX command to this lua function is `\cloze` (→ 2.1.1). The argument `head` is the head node of a node list.

```

329 function cloze.basic(head)
330   cloze.status.continue = false
331   cloze.basic_recursion(head)
332   return head
333 end

```

`fix_length`

Calculate the length of the whitespace before (`l.kern_start`) and after (`l.kern_stop`) the text.

```

334 function cloze.fix_length(start, stop)
335   local l = {}
336   l.width = tex.sp(registry.get_value('width'))
337   l.text_width = node.dimensions(start, stop)
338   l.align = registry.get_value('align')
339   if l.align == 'right' then
340     l.kern_start = - l.text_width
341     l.kern_stop = 0
342   elseif l.align == 'center' then
343     l.half = (l.width - l.text_width) / 2
344     l.kern_start = - l.half - l.text_width
345     l.kern_stop = l.half
346   else
347     l.kern_start = - l.width
348     l.kern_stop = l.width - l.text_width
349   end
350   return l.width, l.kern_start, l.kern_stop
351 end

```

`fix_make`

The function `cloze.fix_make` generates a gap of fixed width.

Node lists

Show text:

Variable name	Node type	Node subtype	Parameter
n.start	whatsit	user_definded	index
n.line	rule		l.width
n.kern_start	kern		Depends on align
n.color_text	whatsit	pdf_colorstack	Text color
	glyphs		Text to show
n.color_reset	whatsit	pdf_colorstack	Reset color
n.kern_stop	kern		Depends on align
n.stop	whatsit	user_definded	index

Hide text:

Variable name	Node type	Node subtype	Parameter
n.start	whatsit	user_definded	index
n.line	rule		l.width
n.stop	whatsit	user_definded	index

The argument `start` is the node, where the gap begins. The argument `stop` is the node, where the gap ends.

```
352 function cloze.fix_make(start, stop)
353   local l = {} -- length
354   local n = {} -- node
355   l.width, l.kern_start, l.kern_stop = cloze.fix_length(start, stop)
356   n.line = nodex.insert_line(start, l.width)
357   if registry.get_value_show() then
358     nodex.insert_list(
359       'after',
360       n.line,
361       {
362         nodex.create_kern(l.kern_start),
363         nodex.create_color('text')
364       }
365     )
366     nodex.insert_list(
367       'before',
368       stop,
369       {
370         nodex.create_color('reset'),
371         nodex.create_kern(l.kern_stop)
372       },
373       start
374     )
375   else
376     n.line.next = stop.next
377   end
378   registry.remove_marker(start)
379   registry.remove_marker(stop)
380 end
```

fix_recursion

Function to recurse the node list and search after marker. `head` is the head node of a node list.

```

381 function cloze.fix_recursion(head)
382   local n = {} -- node
383   n.start, n.stop = false
384   while head do
385     if head.head then
386       cloze.fix_recursion(head.head)
387     else
388       if not n.start then
389         n.start = registry.get_marker(head, 'fix', 'start')
390       end
391       if not n.stop then
392         n.stop = registry.get_marker(head, 'fix', 'stop')
393       end
394       if n.start and n.stop then
395         cloze.fix_make(n.start, n.stop)
396         n.start, n.stop = false
397       end
398     end
399     head = head.next
400   end
401 end

```

fix

The corresponding L^AT_EX command to this Lua function is `\clozefix` (→ 2.1.3). The argument `head` is the head node of a node list.

```

402 function cloze.fix(head)
403   cloze.fix_recursion(head)
404   return head
405 end

```

par

The corresponding L^AT_EX environment to this lua function is `clozepar` (→ 2.1.5).

Node lists**Show text:**

Variable name	Node type	Node subtype	Parameter
n.strut	kern		width = 0
n.line	rule		l.width (Width from hlist)
n.kern	kern		-l.width
n.color_text	whatsit	pdf_colorstack	Text color
	glyphs		Text to show
n.tail	glyph		Last glyph in hlist
n.color_reset	whatsit	pdf_colorstack	Reset color

Hide text:

Variable name	Node type	Node subtype	Parameter
n.strut	kern		width = 0
n.line	rule		l.width (Width from hlist)

The argument `head` is the head node of a node list.

```
406 function cloze.par(head)
407   local l = {} -- length
408   local n = {} -- node
409   for hlist in node.traverse_id(node.id('hlist'), head) do
410     for whatsit in node.traverse_id(node.id('whatsit'), hlist.head) do
411       registry.get_marker(whatsit, 'par', 'start')
412     end
413     l.width = hlist.width
414     hlist, n.strut, n.head = nodex.strut_to_hlist(hlist)
415     n.line = nodex.insert_line(n.strut, l.width)
416     if registry.get_value_show() then
417       nodex.insert_list(
418         'after',
419         n.line,
420         {
421           nodex.create_kern(-l.width),
422           nodex.create_color('text')
423         }
424       )
425       nodex.insert_list(
426         'after',
427         node.tail(head),
428         {nodex.create_color('reset')}
429       )
430     else
431       n.line.next = nil
432     end
433   end
434   return head
435 end
```

3.2.4 Basic module functions (base)

`register` The `base` table contains functions which are published to the `cloze.sty` file. This function registers the functions `cloze.par`, `cloze.basic` and `cloze.fix` the Lua callbacks. `cloze.par` and `cloze.basic` are registered to the callback `post_linebreak_filter` and `cloze.fix` to the callback `pre_linebreak_filter`. The argument `mode` accepts the string values `basic`, `fix` and `par`.

```
436 function base.register(mode)
437   local basic
438   if mode == 'par' then
439     luatexbase.add_to_callback(
440       'post_linebreak_filter',
441       cloze.par,
442       mode
443     )
444   return true
445 end
```

```

445   end
446   if not base.is_registered[mode] then
447     if mode == 'basic' then
448       luatexbase.add_to_callback(
449         'post_linebreak_filter',
450         cloze.basic,
451         mode
452       )
453     elseif mode == 'fix' then
454       luatexbase.add_to_callback(
455         'pre_linebreak_filter',
456         cloze.fix,
457         mode
458       )
459     else
460       return false
461     end
462     base.is_registered[mode] = true
463   end
464 end

```

unregister

`base.unregister(mode)` deletes the registered functions from the Lua callbacks.
The argument `mode` accepts the string values `basic`, `fix` and `par`.

```

465 function base.unregister(mode)
466   if mode == 'basic' then
467     luatexbase.remove_from_callback('post_linebreak_filter', mode)
468   elseif mode == 'fix' then
469     luatexbase.remove_from_callback('pre_linebreak_filter', mode)
470   else
471     luatexbase.remove_from_callback('post_linebreak_filter', mode)
472   end
473 end

```

Publish some functions to the `cloze.sty` file.

```

474 base.linefil = nodex.write_linefil
475 base.line = nodex.write_line
476 base.margin = nodex.write_margin
477 base.set_option = registry.set_option
478 base.set_is_global = registry.set_is_global
479 base.unset_local_options = registry.unset_local_options
480 base.reset = registry.unset_global_options
481 base.get_defaults = registry.get_defaults
482 base.marker = registry.write_marker

483 return base

```

Change History

v0.1	General: Converted to DTX file . . .	9	LuaTeX version 0.95	9
v1.0	General: Initial release	9	v1.2	
v1.1	General: Make cloze compatible to		General: The cloze makros are now working in tabular, tabbing and picture environments	9

Index

Numbers written in italic refer to the page where the corresponding entry is described; numbers underlined refer to the code line of the definition; numbers in roman refer to the code lines where the entry is used.

Symbols			
\\"	211, 250	\clozefix	<u>123</u>
C		\clozefont	<u>108</u> , 110, 118, 127, 137
\cloze	<u>114</u> , 145	\clozehide	<u>105</u>
\cloze@color	<u>42</u> , 78, 88	\clozeline	<u>147</u>
\cloze@margin	<u>145</u> , 58, 119, 128	\clozelinefil	<u>145</u> , <u>151</u>
\cloze@set@local@options	<u>43</u> , 115, 124, 135, 148, 152	\clozepar	(environment) <u>132</u>
\cloze@set@option	<u>39</u> , 69, 71, 73, 74, 78, 81, 83, 84, 88, 91, 93	\clozereset	<u>99</u>
\cloze@set@to@global	<u>30</u> , 63, 96	\clozeset	<u>95</u> , 103, 106
\cloze@set@to@local	<u>33</u> , 44	\clozesetfont	<u>109</u>
\cloze@start@marker	<u>47</u> , 116, 125, 136	\clozeshow	<u>102</u>
\cloze@stop@marker	<u>53</u> , 121, 130, 140	\color@	42
\clozefil	<u>144</u>	\csname	42
D			
		\DeclareStringOption	68, 70,
			76, 80, 86, 90, 92
		\DeclareVoidOption	72, 82
		\define@key	69, 71, 77, 81, 87, 91, 93
E			
		\endcsname	42
		environments:	
		\clozepar	<u>132</u>
I			
		\itshape	108
K			
		\kvsetkeys	45, 97
P			
		\par	134, 141
		\ProcessKeyvalOptions	94
R			
		\relax	118, 127, 137
		\renewcommand	110
		\RequirePackage	26
S			
		\SetupKeyvalOptions	64
		\string	42
		\strut	48, 54, 153, 155