COMPUTER SYSTEMS FUNDAMENTALS (4COSCO04W)

Real values in Binary

In this lecture we will cover:

- Representation of Real values in Binary
 - Fixed Point representation
 - Floating Point representation

REAL NUMBERS

Bicimal & IEEE754

By the end of this unit, you will:

- Understand the representation of Real values in Binary form
 - Bicimal
- Be able to represent Decimal real values in Bicimal form
- Be able to represent Bicimal values in Decimal
- Appreciate the limitations of fixed point representations
- Be able to represent Decimal Real values using IEEE754
- Be able to convert from IEEE754 to a real Decimal value

Real values

- Not all values are Integers
 - 1, 2, 3, 77,
- Real (Fractional) values
 - 1.5
 - 1.25
 - 2.75
 - *.....*

Bicimal

- Binary format for representing fractional values
 - Fixed point

| | 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} | |
|---|---------------|---------------|---------------|----------------|--|
| | $\frac{1}{2}$ | $\frac{1}{4}$ | $\frac{1}{8}$ | $\frac{1}{16}$ | |
| | 0.5 | 0.25 | 0.125 | 0.0625 | |
| • | | | | | |

Bicimal 0.5

- Binary format for representing fractional values
 - Fixed point

| 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} | |
|----------|----------------|----------|---------------|--|
| 1 | 1 | 1 | 1 | |
| 2 | $\overline{4}$ | 8 | 16 | |
| 0.5 | 0.25 | 0.125 | 0.0625 | |

=0.5

Bicimal 0.25

- Binary format for representing fractional values
 - Fixed point

| | 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} | |
|---|---------------|---------------|---------------|----------------|-------|
| | $\frac{1}{2}$ | $\frac{1}{4}$ | $\frac{1}{8}$ | $\frac{1}{16}$ | |
| | 0.5 | 0.25 | 0.125 | 0.0625 | |
| • | 0 | 1 | | | =0.25 |

Bicimal 0.75

- Binary format for representing fractional values
 - Fixed point

| 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} |
|----------|----------|----------|----------|
| 1 | 1 | 1 | 1 |
| 2 | 4 | 8 | 16 |
| 0.5 | 0.25 | 0.125 | 0.0625 |

=0.75

Bicimal 1.625

- Binary format for representing fractional values
 - Fixed point

| | | 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} | |
|---|---|---------------|---------------|---------------|----------------|--------|
| | | $\frac{1}{2}$ | $\frac{1}{4}$ | $\frac{1}{8}$ | $\frac{1}{16}$ | |
| | | 0.5 | 0.25 | 0.125 | 0.0625 | |
| 1 | • | 1 | 0 | 1 | | =1.625 |

Decimal of Bicimal 1.101

| 1 | • | 1 | 0 | 1 | | |
|---|---|----------|----------|----------|---------------|--------|
| | | 2^{-1} | 2^{-2} | 2^{-3} | 2^{-4} | |
| | | 1 | 1 | 1 | 1 | |
| | | 2 | 4 | 8 | 16 | |
| 1 | | 0.5 | 0.25 | 0.125 | 0.0625 | |
| 1 | | 0.5 | | 0.125 | | =1.625 |

Limitations of Bicimal Fixed Point values

- Only positive values
- Not suitable for storing very small or very large real numbers
 - Avogardo's number $6.0221367 \times 10^{+23}$
 - Would require about 80 bits for the integer part
 - Mass of Hydrogen atom 1.6733 imes 10^{-24}
 - Would require well over 80 bits for the fractional part
- Hence fixed point format is of limited use for computer representation of different numbers.

Exact values may require a high resolution:

■ With 4 Bicimal Bits:

```
0 \ 0 \ 0 \ 0 = 0
 0 0 0 1 = 0.0625
    0 1 0 = 0.125
    0 1 1 = 0.1875
 0 1 0 0 = 0.25
 0 1 0 1 = 0.3125
 0 1 1 0 = 0.375
    1 1 1 = 0.4375
  1 0 0 0 = 0.5
  1 0 0 1 = 0.5625
 1 0 1 0 = 0.625
    0 1 1 = 0.6875
    1 \quad 0 \quad 0 = 0.75
  1 1 0 1 = 0.8125
  1 1 1 0 = 0.875
1 1 1 1 = 0.9375
```

IEEE754

Floating Point representation

Floating point format

- Very large or very small numbers
- Before IEEE754 standard, different manufacturers used different methods.
- IEEE754 standardised the method of Floating Point representation
- Now adopted by all computer manufacturers
- IEEE754 is simple and efficient method to represent Floating Point format

A few concepts first:

- Normalized format
 - Mantissa
 - Exponent

Normalised Format - Decimal

- 3 parts to a normalised representation:
 - The integer part (single digit)
 - The part beyond the decimal point
 - The power part (Exponent)

Examples:

- 10.0 in normalised form is 1.0×10^{1}
- 312.0 in normalised form is 3.12×10^2
- 3.15 in normalised form is 3.15×10^{0}
- 0.0004 in normalised form is 4.0×10^{-4}
- -400.0 in normalised form is -4.0×10^2

Mantissa & Exponent - Decimal

| Number | Normalised | Mantissa | Exponent |
|--------|----------------------|----------|----------|
| 10 | 1.0×10^{1} | 1.0 | 1 |
| 312 | 3.12×10^2 | 3.12 | 2 |
| 0.0004 | 4.0×10^{-4} | 4.0 | -4 |
| 3.15 | 3.15×10^{0} | 3.15 | 0 |
| -400 | -4.0×10^{2} | -4.0 | 2 |

Mantissa & Exponent - Decimal

| Number | Normalised | Mantissa | Exponent |
|----------|------------|----------|----------|
| 1002 | | | |
| -231 | | | |
| -2 | | | |
| -0.004 | | | |
| -0.12345 | | | |
| | | | |
| | | | |

Floating point in Binary

- **0.00001**
 - $= 1.0 \times 2^{-5}$
 - Mantissa = 1.0
 - Exponent = -5
- **-1001.11**
 - $= 1.00111 \times 2^{+3}$
 - Mantissa = 1.00111
 - Exponent = +3
 - Sign will be dealt with separately


Converting Decimal 31.75 to Normalised Bicimal Form

| Step 1 | Convert the integer part (ie. 31) to Binary | | | | |
|--------|--|--------------------|---------------|--|--|
| Step 2 | • | $\frac{1}{2}$ | $\frac{1}{4}$ | | |
| | | | • | | |
| Step 3 | Combine the results from Step 1 and Step 2 | | | | |
| Step 4 | Normalise: Move Bicimal point till there is just a single 1 t | | | | |
| | | Value of Mantissa: | | | |
| | | Value of Exponent: | | | |

- Single precision
 - 32 bit in total
 - First bit : Sign Bit
 - Next 8 bits : Exponent (in excess form)
 - Last 23 bits: Mantissa


| S | Exponent (Excess form) | Mantissa |
|---|------------------------|----------|
| | | |


| Step 1: | Original number | 3.25 ₁₀ |
|---------|---|--------------------|
| Step 2: | Convert 3 ₁₀ to Binary | |
| Step 3: | Convert 0.25 ₁₀ to Binary | |
| Step 4: | Combine steps 2& 3 | |
| Step 5: | Normalise the result of step 4 | |
| Step 6: | Mantissa from Step 5 | |
| Step 7: | Exponent from Step 5 in excess form | |
| | IEEE754 Sign Bit (O Positive, 1 Negative) | |
| | IEEE754 Exponent Bits | |
| | IEEE754 Mantissa Bits | |




| Denary | Binary | | | / | Hexadecimal |
|--------|--------|---|---|---|-------------|
| 0 | 0 | 0 | 0 | 0 | 0 |
| 1 | 0 | 0 | 0 | 1 | 1 |
| 2 | 0 | 0 | 1 | 0 | 2 |
| 3 | 0 | 0 | 1 | 1 | 3 |
| 4 | 0 | 1 | 0 | 0 | 4 |
| 5 | 0 | 1 | 0 | 1 | 5 |
| 6 | 0 | 1 | 1 | 0 | 6 |
| 7 | 0 | 1 | 1 | 1 | 7 |
| 8 | 1 | 0 | 0 | 0 | 8 |
| 9 | 1 | 0 | 0 | 1 | 9 |
| 10 | 1 | 0 | 1 | 0 | Α |
| 11 | 1 | 0 | 1 | 1 | В |
| 12 | 1 | 1 | 0 | 0 | С |
| 13 | 1 | 1 | 0 | 1 | D |
| 14 | 1 | 1 | 1 | 0 | E |
| 15 | 1 | 1 | 1 | 1 | F |

| Step 1: | Original number | -0.125_{10} |
|---------|---|---------------|
| Step 2: | Convert 0 ₁₀ to Binary | |
| Step 3: | Convert 0.125 ₁₀ to Binary | |
| Step 4: | Combine steps 2& 3 | |
| Step 5: | Normalise the result of step 4 | |
| Step 6: | Mantissa from Step 5 | |
| Step 7: | Exponent from Step 5 in excess form | |
| | IEEE754 Sign Bit (O Positive, 1 Negative) | |
| | IEEE754 Exponent Bits | |
| | IEEE754 Mantissa Bits | |







_




| Step 1: | Original number | -195_{10} |
|---------|---|-------------|
| Step 2: | Convert 195 ₁₀ to Binary | |
| Step 3: | Convert 0.0_{10} to Binary | |
| Step 4: | Combine steps 2& 3 | |
| Step 5: | Normalise the result of step 4 | |
| Step 6: | Mantissa from Step 5 | |
| Step 7: | Exponent from Step 5 in excess form | |
| | IEEE754 Sign Bit (O Positive, 1 Negative) | |
| | IEEE754 Exponent Bits | |
| | IEEE754 Mantissa Bits | |





_



IEEE754

- Further examples in tutorial
 - Try out random numbers of your choice
- This module will not cover:
 - Double precision (64-bit)
 - Zero

For this module, we will only consider 4 Bicimal Bits:

```
0 \quad 0 = 0
     0 0 1 = 0.0625
     0 1 0 = 0.125
     0 1 1 = 0.1875
        0 \quad 0 = 0.25
     1 0 1 = 0.3125
     1 1 0 = 0.375
        1 1 = 0.4375
     0 \quad 0 \quad 0 = 0.5
     0 0 1 = 0.5625
     0 \quad 1 \quad 0 = 0.625
         1 1 = 0.6875
        0 \quad 0 = 0.75
         0 1 = 0.8125
  1 1 1 0 = 0.875
1 1 1 1 = 0.9375
```

In this lecture we looked at:

- Real numbers
 - Fixed point (Bicimal)
 - Floating point (IEEE754)

Further reading:

- Computer Systems
 - 3.5

Thank you

© The University of Westminster (2021)

These notes were modified from the lecture slides generated by Noam Weingarten.

The right of Noam Weingarten to be identified as author of this work has been asserted by them in accordance with the Copyright, Designs and Patents Act 1988