

Params

The following params are used exclusively by the BASE24-pos product. Each of the following params should have the usage code POS (and only the code POS) entered in the USAGE CODES field on the LNCF Param screen.

ADJ-ADVICE-RC — IA code used by the ISO Host Interface process to specify for outgoing BASE24-pos 0220 adjustment messages whether the transaction response code or reversal code is to be included in the P-39 (Response Code) data element of the external message. Typically, only a response code or reversal code (one or the other) is present and meaningful for a transaction. For example, in a normal response message, the response code is present and meaningful, and in an approved adjustment/reversal request/advice, the reversal code is present and meaningful. However, in the case of declined adjustment advices, both a reversal code (the reason for the adjustment) and a response code (the reason for the decline) are present in the PSTM. Since declined adjustments are supported by BASE24-pos and can be sent to a host, hosts are provided the option of including the response code or reversal code in the P-39 external message data element for 0220 adjustment messages. Valid values are as follows:

- 1 = Reversal code. Default.
- 2 = Reversal code for approved advices, response code for declined advices
- 3 = Response code

CRT-ADMN-APPRV-CDE-LGTH — A code specifying the approval code length that the BASE24-pos CRT Device Handler/Router/Authorization process generates for administrative transactions. Only CRT Administration Device Handler modules use this param. Valid values are 2 through 6.

Param Default: 6

CRT-ADMN-MAX-AQFS — The maximum number of Administrative Queue File (AQF) records that the BASE24-pos CRT Device Handler/Router/Authorization process can store in memory at one time. Only CRT Administrative Device Handler modules use this param. Valid values include any numeric value greater than zero.

Param Default: 75