

MERCHANT LINK



ML RELEASE 6.0

LOG MESSAGES MANUAL

Version A

This document contains **PROPRIETARY** and **CONFIDENTIAL** information and such information may not be disclosed to others for any purpose without written permission from:

ACI Worldwide (Canada) Inc.

200 Wellington Street West,
Suite 700,
Toronto, Ontario M5V 3C7

©2004 by ACI Worldwide (Canada) Inc.

All rights reserved. All information contained in this manual is confidential and proprietary to ACI Worldwide Inc. and has been delivered for use pursuant to license. No part of this manual may be photocopied, electronically transferred, modified, or reproduced in any manner that is contrary to license without the prior written consent of ACI Worldwide Inc.

ACI, ACI Worldwide, ACI Worldwide Inc., BASE24, BASE24-atm, BASE24-atm non-currency dispense, BASE24-atm self-service banking, BASE24-billpay, BASE24-CARD, base24-check auth, BASE24-debit/credit auth, BASE24-fraud control, BASE24-frequent shopper, BASE24-from host maintenance, BASE24-gift certificates, BASE24-InfoBase, BASE24-mail, BASE24-pos, BASE24-refunds auth, BASE24 Remote Banking, BASE24-telebanking, BASE24-teller, BASE24 Visa Cash, CO-ach, ICE, NET24, NET24-XPNET, Perfmon, and TSA are trademarks or registered trademarks of ACI Worldwide Inc., Transaction Systems Architects, Inc., or their subsidiaries.

Other companies' trademarks, service marks or registered trademarks and service marks are trademarks, service marks or registered trademarks and service marks of their respective companies.

REVISION HISTORY

Record of Changes

Author	Date	Version	Comments
ME	Apr 2004	A	Initial Version for release 6.0

Change Control Index

Change Control Reference	Description of Change	Modules Effected

TABLE OF CONTENTS

<u>1.</u>	<u>INTRODUCTION</u>	<u>1</u>
<u>2.</u>	<u>MERCHANT LINK INTERFACE MESSAGES</u>	<u>2</u>

1. INTRODUCTION

This manual contains documentation for log messages that can be generated by the Merchant Link (ML) interface code.

For messages that can be generated by the standard code, please refer to the BASE24 Release 6.0 Documentation.

2. MERCHANT LINK INTERFACE MESSAGES

Message-Number: 1005
Severity: 2 - Error
Message-Text: Unrecognized command \?
Variables: \? = Command text
Cause: An NCS command was received that contained an unrecognized command token.
Effect: ML ignores the command.
Response: Check the list of NCS commands and send the correct command token.

Message-Number: 1010
Severity: 0 - Informational
Message-Text: ML trace switch: \?
Variables: \? = New trace bit settings
Cause: An NCS TRACE command was received.
Effect: ML sets the trace bits according to the command arguments.
Response: For information only.

Message-Number: 1015
Severity: 0 - Informational
Message-Text: Operator issued command to DEBUG
Variable: N/A
Cause: An NCS DEBUG command was received.
Effect: ML calls DEBUG.
Response: The ML process may be inspected. Note that only ACI Worldwide personnel should issue the DEBUG command.

Message-Number: 1020
Severity: 0 - Informational
Message-Text: Operator issued command to programmatic DUMP
Variable: N/A
Cause: An NCS DUMP command was received.
Effect: ML performs a programmatic dump.
Response: The dump file may be examined. Note the DUMP command should only be issued by ACI Worldwide personnel.

Message-Number: 1025
Severity: 0 - Informational
Message-Text: Command not yet supported.
Variables: N/A
Cause: An NCS command was received that is not yet supported.
Effect: ML does not process the command.
Response: Contact ACI Help Desk.

Message-Number: 1030
Severity: 2 - Error
Message-Text: Invalid command format \?
Variables: \? = command text
Cause: An invalid NCS command was received.
Effect: ML cannot process the command.
Response: Enter a valid NCS command or check the syntax of the command and resend it.

Message-Number: 1035
Severity: 0 - Informational
Message-Text: Process Trace Audit file A named \F
Variables: \F = new name
Cause: An NCS ANA/ANB command was received and the indicated trace audit file was renamed.
Effect: ML uses the new trace audit file name.
Response: For information only.

Message-Number: 1040
Severity: 2 - Error
Message-Text: Process Trace Audit file A not renamed
Variables: N/A
Cause: An NCS ANA/ANB command was received but the name of the indicated audit trace file could not be changed.
Effect: ML continues using the previous audit trace file name if possible.
Response: Resend the ANA/ANB command with a different file name.

Message-Number: 1045
Severity: 0 - Informational
Message-Text: Process Trace Audit file B named \F
Variables: \F = new name
Cause: An NCS ANA/ANB command was received and the indicated trace audit file was renamed.
Effect: ML uses the new trace audit file name.
Response: For information only.

Log Message Number: 1050
Severity: 2 - Error
Message-Text: Process Trace Audit file B not renamed
Variables: N/A
Cause: An NCS ANA/ANB command was received but the name of the indicated audit trace file could not be changed.
Effect: ML continues using the previous audit trace file name if possible.
Response: Resend the ANA/ANB command with a different file name.

Message-Number: 1055
Severity: 2 - Error
Message-Text: Process Trace Audit extent not set
Variables: N/A
Cause: An NCS ADX command was received but the trace audit extent size specified was not numeric.
Effect: ML does not alter the trace audit extent size.
Response: Resend the ADX command with a valid extent size.

Message-Number: 1060
Severity: 0 - Informational
Message-Text: Process Trace Audit extent set to #
Variables: # = extent size
Cause: An NCS ADX command was received.
Effect: ML creates subsequent trace audit files with the indicated extent size.
Response: For information only.

Message-Number: 1065
Severity: 0 - Informational
Message-Text: Process Trace Audit file switched
Variables: N/A
Cause: An NCS SWA command was received and the trace audit file was switched to audit file A and audit file name A was changed to audit file name B.
Effect: ML begins using the new trace audit file.
Response: For information only.

Message-Number: 1070
Severity: 2 - Error
Message-Text: Process Trace Audit file not switched
Variables: N/A
Cause: An NCS SWA command was received but the trace audit file could not be switched.
Effect: ML does not switch the trace audit files.
Response: Resend the ANA, ANB and SWA commands.

Message-Number: 1075
Severity: 0 - Informational
Message-Text: Process Trace Audit file - \F
Variables: \F = file name
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1080
Severity: 0 - Informational
Message-Text: Process Trace Audit file - NO FILE NAME
Variables: N/A
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1085
Severity: 0 - Informational
Message-Text: Process Trace Audit file A - \F
Variables: \F = file name
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1090
Severity: 0 - Informational
Message-Text: Process Trace Audit file A - NO FILE NAME
Variables: N/A
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1095
Severity: 0 - Informational
Message-Text: Process Trace Audit file B - \F
Variables: \F = file name
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1100
Severity: 0 - Informational
Message-Text: Process Trace Audit file B - NO FILE NAME
Variables: N/A
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1105
Severity: 0 - Informational
Message-Text: Process Trace Audit file extent size = #
Variables: # = audit file extent size
Cause: An NCS INFOAuditfiles command was received.
Effect: ML displays the current trace and audit file configuration.
Response: For information only.

Message-Number: 1110
Severity: 0 - Informational
Message-Text: Counter ##: \\\\: Offset: :# Error: #
Variables: ## = counter
\\\: = counter Name
= counter offset
= error count
Cause: An NCS MEASURE (show) command was received.
Effect: ML displays the current measure counters and their corresponding values.
Response: For information only.

Message-Number: 1115
Severity: 0 - Informational
Message-Text: No user counters defined in any active Measurement
Variables: N/A
Cause: An NCS MEASURE (show) command was received and no measure counters can be displayed since none are defined .
Effect: None.
Response: Start a new measure if desired.

Message-Number: 1120
Severity: 0 - Informational
Message-Text: User Measurement is not active
Variables: N/A
Cause: An NCS MEASURE (show) command was received and there is currently no measure running.
Effect: None.
Response: Start a measure if desired.

Message-Number: 1125
Severity: 0 - Informational
Message-Text: User Measurement Initiated
Variables: N/A
Cause: An NCS MEASURE START command was received.
Effect: ML starts to update the measure counters.
Response: For information only.

Message-Number:	1130
Severity:	0 - Informational
Message-Text:	User Measurement Terminated
Variables:	N/A
Cause:	An NCS MEASURE STOP command was received.
Effect:	ML stops the currently running measurement.
Response:	For information only.
Message-Number:	1135
Severity:	1 - Warning
Message-Text:	Invalid MEASURE option: \?
Variables:	\? = entered option
Cause:	An invalid NCS MEASURE command was received.
Effect:	ML ignores the command.
Response:	Resend the command with a valid measure option. Either blank (show), START or STOP.
Message-Number:	1140
Severity:	2 - Error
Message-Text:	Process Trace Audit filename is bad - \?
Variables:	\? = file name
Cause:	An NCS ANA/ANB command was received but the file name specified was invalid.
Effect:	ML ignores the command.
Response:	Resend the command with a valid file name.
Message-Number:	1142
Severity:	0 - Informational
Message-Text:	New B24 Posting date = \\\\\\\
Variables:	\\\\\\ = yymmdd
Cause:	An NCS CUTOVER command was received and the BASE24 Posting date was set.
Effect:	ML begins using the new posting date.
Response:	For information only.
Message-Number:	1150
Severity:	0 - Informational
Message-Text:	KEYF = \F fnum= #
Variables:	\F = file name # = file number
Cause:	AN NCS DISPLAY FILES command was received.
Effect:	ML displays the current file names and file numbers for the indicated file type.
Response:	For information only.

Message-Number: 1155
Severity: 0 - Informational
Message-Text: LMCF = \F fnum= #
Variables: \F = file name
= file number
Cause: AN NCS DISPLAY FILES command was received.
Effect: ML displays the current file names and file numbers for the indicated file type.
Response: For information only.

Message-Number: 1160
Severity: 0 - Informational
Message-Text: MLCF = \F fnum= #
Variables: \F = file name
= file number
Cause: AN NCS DISPLAY FILES command was received.
Effect: ML displays the current file names and file numbers for the indicated file type.
Response: For information only.

Message-Number: 1165
Severity: 0 - Informational
Message-Text: MMF = \F fnum= #
Variables: \F = file name
= file number
Cause: AN NCS DISPLAY FILES command was received.
Effect: ML displays the current file names and file numbers for the indicated file type.
Response: For information only.

Message-Number: 1170
Severity: 0 - Informational
Message-Text: MTF = \F fnum= #
Variables: \F = file name
= file number
Cause: AN NCS DISPLAY FILES command was received.
Effect: ML displays the current file names and file numbers for the indicated file type.
Response: For information only.

Message-Number: 1175
Severity: 0 - Informational
Message-Text: Timer type= # subtype= # exptime= ##:##:##:##:##
Variables: # = timer name
= timer subtype
##:##:##:##:## = HH:MM:SS:TS:MS
Cause: AN NCS DISPLAY TIMERS command was received.
Displayed with message number 1180
Effect: ML displays the current values of active timers.
Response: For information only.

Message-Number:	1180
Severity:	0 - Informational
Message-Text:	# timers active of # maximum timers
Variables:	# = number of timers # = max timers
Cause:	AN NCS DISPLAY TIMERS command was received. Displayed with message number 1175.
Effect:	ML displays the current values of active timers.
Response:	For information only.
Message-Number:	1185
Severity:	0 - Informational
Message-Text:	Trace Bit settings: \\\\\\\
Variables:	\\\\\\ = trace bit values
Cause:	AN NCS DISPLAY TRACEBITS command was received.
Effect:	ML displays the current Tracebit settings.
Response:	For information only.
Message-Number:	1190
Severity:	0 - Informational
Message-Text:	DPC \\\\: MAC typ= \ Exchg Key= \?
Variables:	\\\\ = DPC number \\ = MAC key type \\? = Exchange key value
Cause:	AN NCS DISPLAY KEYS command was received. Displayed with message numbers 1195 and 1200
Effect:	ML displays the current inbound and outbound MAC keys for each DPC.
Response:	For information only.
Message-Number:	1195
Severity:	0 - Informational
Message-Text:	IN => MAC Key1= \? MAC Key2= \? Idx= \
Variables:	\\? = MAC key value 1 \\? = MAC key value 2 \\ = Current MAC key index
Cause:	AN NCS DISPLAY KEYS command was received. Displayed with message numbers 1190 and 1200.
Effect:	ML displays the current inbound and outbound MAC keys for each DPC.
Response:	For information only.

Message-Number: 1200
Severity: 0 - Informational
Message-Text: OUT => MAC Key1= \? MAC Key2= \? Idx= \
Variables: \? = MAC key value 1
 \? = MAC key value 2
 \ = Current MAC key index
Cause: AN NCS DISPLAY KEYS command was received.
 Displayed with message numbers 1190 and 1195.
Effect: ML displays the current inbound and outbound MAC keys for each DPC.
Response: For information only.

Message-Number: 1205
Severity: 0 - Informational
Message-Text: ===== DISPLAY =====
Variables: N/A
Cause: AN NCS DISPLAY command was received.
Effect: ML logs the DISPLAY header message.
Response: For information only.

Message-Number: 1210
Severity: 2 - Error
Message-Text: Invalid DISPLAY command given: \?
Variables: \? = command text
Cause: AN NCS DISPLAY command was received that contained an invalid display option or parameter.
 Displayed with message number 1215.
Effect: ML ignores the command.
Response: Resend the command with the correct option or parameter as specified in message 1215.

Message-Number: 1215
Severity: 0 - Informational
Message-Text: Commands: FILES, TIMERS, TRACEBITS, KEYS
Variables: N/A
Cause: AN NCS DISPLAY command was received that contained an invalid display option or parameter.
 Displayed with message number 1210.
Effect: ML ignores the command.
Response: Resend the command with the correct option or parameter.

Message-Number: 1220
Severity: 2 - Error
Message-Text: Invalid Filename \?
Variables: \? = file name
Cause: An NCS SWL command was received that contained an invalid file name.
Effect: ML ignores the command.
Response: Resend the command with the correct file name.

Message-Number: 1225
Severity: 1 - Warning
Message-Text: \? is not a valid DPC number - check DPC number
Variables: \? = DPC number
Cause: An NCS TOTALS or NEWMACKEY or MLNEWMACKEY command was received that contained an invalid DPC Number.
Effect: ML ignores the command.
Response: Resend the command with a valid DPC number for this ML process.

Message-Number: 1240
Severity: 0 - Informational
Message-Text: DPC \\\\: MACing is not enabled for DPC
Variables: \\\\: = DPC number
Cause: An NCS NEWMACKEY command was received for the indicated DPC but MAC generation is not enabled for this DPC.
Effect: The NEWMACKEY cannot be sent.
Response: If required, turn MAC generation on for the DPC using the ICF screen and restart or warmboot ML.

Message-Number: 1245
Severity: 0 - Informational
Message-Text: DPC \\\\: Key change already in progress
Variables: \\\\: = DPC number
Cause: AN NCS NEWMACKEY command was received for the indicated DPC which has a MAC key change in progress.
Effect: The NEWMACKEY cannot be sent.
Response: Wait until the current key change is complete. If necessary, the command can be re-executed after the first one is complete.

Message-Number: 1250
Severity: 0 - Informational
Message-Text: DPC \\\\: is not logged on
Variables: \\\\: = DPC number
Cause: AN NCS NEWMACKEY command was received for the indicated DPC that is not currently logged on.
Effect: The NEWMACKEY cannot be sent.
Response: This command can only be sent if the DPC is up and logged on and has an available station. Resend the command with another DPC number or logon to this DPC before sending the command.

Message-Number: 1255
Severity: 0 - Informational
Message-Text: DPC \\\\: link is down
Variables: \\\\: = DPC number
Cause: An NCS NEWMACKEY command was received for the indicated DPC that is not currently up.
Effect: The NEWMACKEY cannot be sent.
Response: This command can only be sent if the DPC is up and logged on and has an available station. Bring this DPC up before sending the command.

Message-Number: 1260
Severity: 0 - Informational
Message-Text: DPC \\\\: No stations are available
Variables: \\\\: = DPC number
Cause: AN NCS NEWMACKEY command was received for the indicated DPC which does not currently have any stations up.
Effect: The NEWMACKEY cannot be sent.
Response: This command can only be sent if the DPC is up and logged on and has an available station. Bring this DPC up before sending the command.

Message-Number: 1265
Severity: 0 - Informational
Message-Text: DPC \\\\: MAC Key Exchange sent to \S
Variables: \\\\: = DPC number
 \S = Symbolic station name
Cause: An NCS NEWMACKEY command was received for the indicated DPC.
Effect: The NEWMACKEY was successfully sent.
Response: For information only.

Message-Number: 1270
Severity: 0 - Informational
Message-Text: DPC \\\\: Error occurred sending MAC Key Exchange \S
Variables: \\\\: = DPC number
 \S = Symbolic station name
Cause: AN NCS NEWMACKEY command was received for the indicated DPC but a failure occurred when the message was actually being sent.
Effect: The NEWMACKEY cannot be sent.
Response: Check for previous log messages that will indicate the reason that the message could not be sent.

Message-Number: 1280
Severity: 0 - Informational
Message-Text: -----
Variables: N/A
Cause: AN NCS PERFORMANCE or NCS STATUS command was received.
Effect: None.
Response: For information only.

Message-Number: 1285
Severity: 0 - Informational
Message-Text: \S PERFORMANCE COMMAND - RELEASE 1.0 -
Variables: \S = Symbolic process name
Cause: AN NCS PERFORMANCE command was received.
Displayed with message numbers 1280, 1290, 1295, 1300 and 1305
Effect: ML logs all of the above stated log messages with message numbers 1300 and 1305 repeated for each DPC.
Response: For information only.

Message-Number: 1290
Severity: 0 - Informational
Message-Text: DPC PER IN/ OUT IN/ OUT PERCENT AVG RESP
Variables: N/A
Cause: AN NCS PERFORMANCE command was received.
 Displayed with message numbers 1280, 1285, 1295, 1300 and 1305
Effect: ML logs all of the above stated log messages with message numbers 1300 and 1305 repeated for each DPC.
Response: For information only.

Message-Number: 1295
Severity: 0 - Informational
Message-Text: NUM REQUESTS TIMEOUTS TIMEOUTS TIME
Variables: N/A
Cause: AN NCS PERFORMANCE command was received.
 Displayed with message numbers 1280, 1285, 1290, 1300 and 1305
Effect: ML logs all of the above stated log messages with message numbers 1300 and 1305 repeated for each DPC.
Response: For information only.

Message-Number: 1300
Severity: 0 - Informational
Message-Text: \\\ # \$\$\$\$ \$\$\$\$ \$\$\$% ##.## <== IN
Variables: \\\ = DPC number
 # = Perf Int number
 \$\$\$ = Number requests
 \$\$\$ = Number timeouts
 \$\$\$% = Timeout percentage
 ##.## = Avg resp time
Cause: AN NCS PERFORMANCE command was received.
 Displayed with message numbers 1280, 1285, 1290, 1295 and 1305
Effect: ML logs all of the above stated log messages with message numbers 1300 and 1305 repeated for each DPC.
Response: For information only.

Message-Number: 1305
Severity: 0 - Informational
Message-Text: \\\ # \$\$\$\$ \$\$\$\$ \$\$\$% ##.## <== OUT
Variables: \\\ = DPC number
 # = Perf Int number
 \$\$\$ = Number requests
 \$\$\$ = Number timeouts
 \$\$\$% = Timeout percentage
 ##.## = Avg resp time
Cause: AN NCS PERFORMANCE command was received.
 Displayed with message numbers 1280, 1285, 1290, 1295 and 1300
Effect: ML logs all of the above stated log messages with message numbers 1300 and 1305 repeated for each DPC.
Response: For information only.

Message-Number: 1325
Severity: 0 - Informational
Message-Text: \S STATUS COMMAND - RELEASE 1.0 -
Variables: \S = Symbolic process name
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1335, 1340, 1345, 1350, 1355, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1335
Severity: 0 - Informational
Message-Text: DPC LINK LOGON OUTBOUND OUTBOUND INBOUND INBOUND
Variables: N/A
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1340, 1345, 1350, 1355, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1340
Severity: 0 - Informational
Message-Text: STATUS STATUS MESSAGES MSGS MAX MESSAGES MSGS MAX
Variables: N/A
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1345, 1350, 1355, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1345
Severity: 0 - Informational
Message-Text: \\\ \\\ \\\ #### #### #### ####
Variables: \\\ = DPC Number
\\ = Link Status
= Logon Status
= number out Messages
= Max Out Messages
= number in Messages
= Max In Messages
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1350, 1355, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1350
Severity: 0 - Informational
Message-Text: => STATION NAME STATUS MESSAGES TIMEOUTS TRAFFIC
Variables: N/A
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1355, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1355
Severity: 0 - Informational
Message-Text: PENDING
Variables: N/A
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1350, 1360, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1360
Severity: 0 - Informational
Message-Text: \\\生\\生 ##### \\\生\\生
\\生\\生\\生\\生 = Symbolic Station Name
\\生\\生\\生\\生 = Link Status
= Number Messages Outstanding
= Number of Timeouts
\\生\\生\\生\\生 = Busy Flag

Variables: N/A
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1350, 1355, 1365, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1365
Severity: 0 - Informational
Message-Text: # outbound requests pending of # maximum requests
Variables: # = Number of outbound requests
= Maximum number of outbound requests
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1350, 1355, 1360, 1370 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1370
Severity: 0 - Informational
Message-Text: # inbound requests pending of # maximum requests
Variables: # = Number of inbound requests
= Maximum number of inbound requests
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1350, 1355, 1360, 1365 and 1375.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1375
Severity: 0 - Informational
Message-Text: # timers active of # maximum timers
Variables: # = Number of timers
= Max number of timers
Cause: AN NCS STATUS command was received.
Displayed with message numbers 1325, 1335, 1340, 1345, 1350, 1355, 1360, 1365 and 1370.
Effect: ML logs all of the above stated log messages with message numbers 1335 through 1355 repeated for each DPC and message number 1360 repeated for each station within each DPC.
Response: For information only.

Message-Number: 1391
Severity: 0 - Informational
Message-Text: MTF Key= \?
Variables: \? = Primary key of the MTF file used to retrieve the totals
Cause: AN NCS TOTALS command was received for the indicated DPC.
Effect: The ML process uses this key to get the TOTALS information that will be sent for the desired DPC.
Response: For information only.

Message-Number: 1392
Severity: 0 - Informational
Message-Text: DPC \\\\: No stations are available
Variables: \\\\: = DPC number
Cause: AN NCS TOTALS command was received for the indicated DPC which does not currently have any stations up.
Effect: The TOTALS cannot be sent for this DPC.
Response: This command can only be sent if the DPC is up and logged on and has an available station. Bring this DPC up before sending the command.

Message-Number: 1394
Severity: 1 - Warning
Message-Text: MTF record not found - TOTALS command failed
Variables: N/A
Cause: AN NCS TOTALS command was received for the indicated DPC but a Merchant Totals File record was not found for this DPC.
Effect: The TOTALS cannot be sent.
Response: An incorrect parameter was entered. Check the parameters that were entered. See message 1391 for the key that was used in reading the MTF.

Message-Number: 1395
Severity: 0 - Informational
Message-Text: The following totals will be sent for DPC \\\\
Variables: \\\\
= DPC number
Cause: AN NCS TOTALS command was received for the indicated DPC.
Displayed with log numbers 1395, 1397 and 1398.
Effect: ML logs all of the above stated log messages showing the current totals for the indicated DPC.
Response: For information only.

Message-Number: 1396
Severity: 0 - Informational
Message-Text: Debit Credit Adjustments
Variables: N/A
Cause: AN NCS TOTALS command was received for the indicated DPC.
Displayed with log numbers 1395, 1397 and 1398.
Effect: ML logs all of the above stated log messages showing the current totals for the indicated DPC.
Response: For information only.

Message-Number: 1397
Severity: Count Amount Count Amount Count Amount
Variables: N/A
Cause: AN NCS TOTALS command was received for the indicated DPC.
Displayed with log numbers 1395, 1396 and 1398.
Effect: ML logs all of the above stated log messages showing the current totals for the indicated DPC.
Response: For information only.

Message-Number: 1398
Severity: 0 - Informational
Message-Text: \$\$\$\$\$\$ \\\\\$ \$\$\$\$\$\$ \\\\\$ \$\$\$\$\$\$ \\\\\$
Variables: \$\$\$\$\$\$ = Number Debit Trxns
\\\\$ = Total Debit Amount
\$\$\$\$\$\$ = Number Credit Trxns
\\\\$ = Total Credit Amount
\$\$\$\$\$\$ = Number Adjustment Trxns
\\\\$ = Total Adjustment Amount
Cause: AN NCS TOTALS command was received for the indicated DPC.
Displayed with log numbers 1395, 1396 and 1397.
Effect: ML logs all of the above stated log messages showing the current totals for the indicated DPC.
Response: For information only.

Message-Number: 1420
Severity: 0 - Informational
Message-Text: DPC \\\\: No KEYF record for DPC
Variables: \\\\: = DPC number
Cause: AN NCS MLNEWMACKEY command was received for the indicated DPC but no KEYF record exists for this DPC.
Effect: The MLNEWMACKEY cannot be accepted.
Response: This command can only be accepted if a valid KEYF record exists for the indicated DPC. Enter a valid KEYF record and regenerate the MAC keys with a NEWMACKEY command.

Message-Number: 1425
Severity: 0 - Informational
Message-Text: DPC \\\\: Issuer MAC Key \ updated
Variables: \\\\: = DPC number
\\ = MAC key index
Cause: A valid ISSUER key change request was processed for the indicated DPC due to an NCS MLNEWMACKEY command.
Effect: ML retrieves the key information stored in the KEYF file and begins processing with the new MAC key.
Response: For information only.

Message-Number: 1430
Severity: 0 - Informational
Message-Text: DPC \\\\: Acquirer MAC Key \ updated
Variables: \\\\: = DPC number
\\ = MAC key index
Cause: A valid ACQUIRER key change request was processed for the indicated DPC due to an NCS MLNEWMACKEY command.
Effect: ML retrieves the key information stored in the KEYF file and begins processing with the new MAC key.
Response: For information only.

Message-Number: 1435
Severity: 0 - Informational
Message-Text: Warmbooting ML process= \F
Variables: \F = ML process name
Cause: An NCS command was received and the warmboot processing is about to begin.
Effect: ML begins the warmboot process.
Response: Check subsequent log messages to determine if the warmboot completed successfully.

Message-Number: 1440
Severity: 2 - Error
Message-Text: WARMBOOT *failed* because of LCONF error
Variables: N/A
Cause: An NCS WARMBOOT command was received but the warmboot failed due to an error on the LCONF file.
Effect: ML cannot complete the warmboot and may be in an inconsistent state.
Response: Check previous log messages for GUARDIAN errors to determine the appropriate response. Repeat the warmboot or stop and start the ML.

Message-Number: 1445
Severity: 0 - Informational
Message-Text: WARMBOOT completed successfully -- New status implemented
Variables: N/A
Cause: An NCS WARMBOOT command was received and the warmboot was successfully completed.
Effect: ML continues processing with the new configuration.
Response: None required.

Message-Number: 1450
Severity: 2 - Error
Message-Text: WARMBOOT errors - correct and retry warmboot
Variables: N/A
Cause: An NCS WARMBOOT command was received but the warmboot operation failed.
Effect: ML cannot complete the warmboot and may be in an inconsistent state.
Response: Check previous log messages for GUARDIAN errors to determine the appropriate response. Repeat the warmboot or stop and start the ML.

Message-Number: 2000
Severity: 3 - Critical
Message-Text: ERROR: Cannot process following ML ***** Message-Text:"
Variables: ***** = Either ACQUIRER or ACCEPTOR will be displayed.
Cause: The transaction entered a dummy hooks procedure which is only used for compiling purposes. Displayed with critical log message 2010.
Effect: ML logs the incoming message (log error 2005) and drops it with no further processing.
Response: Verify that the correct ML interface object is being used.
Verify that the incoming message is formatted correctly for the ML interface object.
If problem continues, contact the ACI Help Desk.

Message-Number: 2002
Severity: 3 - Critical
Message-Text: Invalid ISO message format - #
Variables: # = DPC message format
Cause: An ISO message was received that was not in ML ISO or BOM ISO format.
Effect: ML drops the message with no further processing.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2004
Severity: 3 - Critical
Message-Text: Invalid ISO message format - #
Variables: # = DPC message format
Cause: An ISO message was received that was not in ML ISO or BOM ISO format.
Effect: ML drops the message with no further processing.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2010
Severity: 3 - Critical
Message-Text: Please contact your ACI Worldwide representative.
Variables: N/A
Cause: The transaction entered a dummy hooks procedure which is only used for compiling purposes. Displayed with critical log message 2000.
Effect: ML logs the incoming message (log error 2005) and drops it with no further processing.
Response: Contact ACI Help Desk.

Message-Number: 2010
Severity: 2 - Error
Message-Text: Invalid ISO Type \\\ received - dropped
Variables: \\\ = ISO type
Cause: An ISO message was received that could not be successfully converted into ML/SPDH format due to edit problems on the Bit Map number displayed.
Effect: ML logs the incoming message (log error 2030) and drops it with no further processing.
Response: Verify the incoming message format, particularly for the displayed Bit Map, against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2020
Severity: 2 - Error
Message-Text: ISO to ML conversion problems - Bit Map #
Variables: # = Bit map number
Cause: An ISO message was received that could not be successfully converted into ML/SPDH format due to edit problems on the Bit Map number displayed.
Effect: ML logs the incoming message (log error 2030) and drops it with no further processing.
Response: Verify the incoming message format, particularly for the displayed Bit Map, against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2040
Severity: 2 - Error
Message-Text: Invalid ISO Type \\\ received - dropped
Variables: \\\ = Message type
Cause: The message type on an incoming ISO message was received that is not one of those defined in the ISO message type set (see section 2.1.1)
Effect: ML logs the incoming message (log error 2050) and drops it with no further processing.
Response: Contact the entity (acquirer or acceptor) from which the message was received to correct the message type.

Message-Number: 2090
Severity: 2 - Error
Message-Text: ISO to DH conversion problems - Bit Map #
Variables: # = Bit map number
Cause: An edit error occurred while attempting to convert an incoming Bit Map to its corresponding FID(s).
Effect: ML drops the incoming message with no further processing.
Response: Contact the entity (acquirer or acceptor) from which the message was received to correct the displayed Bit Map.

Message-Number: 2100
Severity: 2 - Error
Message-Text: Invalid Tran Code \ From DPC \\\
Variables: \ = Transaction code
\\ = DPC number
Cause: The processing code received on an incoming ISO message is not one of those supported in the ISO message format (see Bit Map 3 - section 2.4.3).
Effect: ML drops the incoming message with no further processing.
Response: Contact the entity (acquirer or acceptor) from which the message was received to correct the processing code.

Message-Number: 2110
Severity: 2 - Error
Message-Text: Invalid Tran Code \ To DPC \\\
Variables: \ = SPDH transaction code
\\ = DPC number
Cause: The transaction code on the SPDH portion of an internal transaction request is not one of those supported in the ISO message format (see Bit Map 3 - section 2.4.3) and could not be converted to an ISO processing code.
Effect: ML drops the incoming message with no further processing.
Response: If the transaction code indicated should be supported under ISO, contact ACI Help Desk.

Message-Number: 2120
Severity: 2 - Error
Message-Text: DPC \\\ POS type \\\ found in EMF
Variables: \\\ = DPC number
\\ = Message type
Cause: The message type on an EMF record defined to this ML process is not one of those defined in the ISO message type set
EMF processing halts at this point, leaving required bit maps at their default values.
Effect: EMF processing halts at this point, leaving required bit maps at their default values.
Response: Correct the EMF record indicated and warmboot the ML process.

Message-Number: 2126
Severity: 3 - Critical
Message-Text: Programmatic error, end processing with format error
Variables: N/A
Cause: An ISO message was received that was not in ML ISO or BOM ISO format.
Effect: ML drops the incoming message with no further processing.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2128
Severity: 3 - Critical
Message-Text: Programmatic error, end processing with format error
Variables: N/A
Cause: An ISO message was received that was not in ML ISO or BOM ISO format.
Effect: ML drops the incoming message with no further processing.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2142
Severity: 3 - Critical
Message-Text: Programmatic error. Call ABEND to end processing.
Variables: N/A
Cause: The incoming ISO message type could not be converted from ASCII to integer.
Effect: Process abends.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2144
Severity: 3 - Critical
Message-Text: Programmatic error. Call ABEND to end processing.
Variables: N/A
Cause: The incoming ISO message type could not be converted from ASCII to integer.
Effect: Process abends.
Response: Verify the incoming message format against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number: 2150
Severity: 1 - Warning
Message-Text: Invalid ISO Type \\\ received - dropped
Variables: \\\ = Message type
Cause: The message type converted from the internal ML to ISO format has no corresponding tables for message conversion to ISO.
Effect: ML logs the incoming message (log error 2160) and drops it with no further processing.
Response: Contact ACI Help Desk.

Message-Number: 2170
Severity: 1 - Warning
Message-Text: Invalid ISO Msg conversion - dropped
Variables: N/A
Cause: An internal ISO message structure could not be collapsed into external format due to edit problems with the Bit Map displayed.
Displayed with log number 2180.
Effect: ML logs the outgoing external message (2190) and drops it with no further processing.
Response: Contact ACI Help Desk. If the outgoing message is a transaction reply, manual reconciliation may be required.

Message-Number: 2180
Severity: 2 - Error
Message-Text: ML to ISO conversion problems - Bit Map #
Variables: # = Bit map number
Cause: An internal ISO message structure could not be collapsed into external format due to edit problems with the Bit Map displayed.
Displayed with log number 2170.
Effect: ML logs the outgoing external message (2190) and drops it with no further processing.
Response: Contact ACI Help Desk. If the outgoing message is a transaction reply, manual reconciliation may be required.

Message-Number: 2200
Severity: 2 - Error
Message-Text: Invalid Tran Code \\ To DPC \\\\
Variables: \\ = transaction code
\\\ = DPC number
Cause: The transaction code received on an incoming ISO message is not one of those supported in the ISO message format.
Effect: ML logs the error and continues processing..
Response: Contact the entity (acquirer or acceptor) from which the message was received to correct the processing code.

Message-Number: 2210
Severity: 2 - Error
Message-Text: DH to ISO conversion problems - Bit Map #
Variables: # = Bit map number
Cause: An edit error occurred while converting an ML/SPDH format message into ISO format. ML drops the incoming message with no further processing. Displayed with log number 2220, 2230, 2240 and 2250.
Effect: ML drops the incoming message with no further processing.
Response: Evaluate the FID data against documented requirements for ISO conversion and correct it accordingly.

Message-Number: 2220
Severity: 1 - Warning
Message-Text: FID is not supported ***** dropped
Variables: ***** = FID data
Cause: An edit error occurred while converting an ML/SPDH format message into ISO format. ML drops the incoming message with no further processing. Displayed with log number 2210, 2230, 2240 and 2250.
Effect: ML drops the incoming message with no further processing.
Response: Evaluate the FID data against documented requirements for ISO conversion and correct it accordingly.

Message-Number: 2230
Severity: 1 - Warning
Message-Text: "
Variables: N/A
Cause: An edit error occurred while converting an ML/SPDH format message into ISO format. ML drops the incoming message with no further processing. Displayed with log number 2210, 2220, 2240 and 2250.
Effect: ML drops the incoming message with no further processing.
Response: Evaluate the FID data against documented requirements for ISO conversion and correct it accordingly.

Message-Number:	2240
Severity:	1 - Warning
Message-Text:	"
Variables:	N/A
Cause:	An edit error occurred while converting an ML/SPDH format message into ISO format. ML drops the incoming message with no further processing. Displayed with log number 2210, 2220, 2230 and 2250.
Effect:	ML drops the incoming message with no further processing.
Response:	Evaluate the FID data against documented requirements for ISO conversion and correct it accordingly.
Message-Number:	2250
Severity:	1 - Warning
Message-Text:	"
Variables:	N/A
Cause:	An edit error occurred while converting an ML/SPDH format message into ISO format. ML drops the incoming message with no further processing. Displayed with log number 2210, 2220, 2230 and 2240.
Effect:	ML drops the incoming message with no further processing.
Response:	Evaluate the FID data against documented requirements for ISO conversion and correct it accordingly.
Message-Number:	2260
Severity:	1 - Warning
Message-Text:	Required Bit Map not received # - dropped
Variables:	# = Bit map number
Cause:	A Bit Map defined as required for a given ISO message type (either as default or through the EMF) is not present on an incoming ISO message of the given type.
Effect:	ML drops the incoming message with no further processing.
Response:	Contact the entity (acquirer or acceptor) from which the message was received to include the Bit Map or correct the EMF to make that Bit Map optional. If the EMF is changed, warmboot the ML process to implement the modification.
Message-Number:	2310
Severity:	2 - Error
Message-Text:	Invalid ISO Msg received Src: \S – dropped
Variables:	\S = symbolic message source name
Cause:	An ISO message was received that could not be successfully converted into ML/SPDH format due to edit problems on the Bit Map number displayed. Displayed with log message number 2320.
Effect:	ML logs the incoming message (log error 2330) and drops it with no further processing
Response:	Verify the incoming message format, particularly for the displayed Bit Map, against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.

Message-Number:	2320
Severity:	2 - Error
Message-Text:	ISO to ML conversion problems – Bit Map #
Variables:	# = bitmap number
Cause:	An ISO message was received that could not be successfully converted into ML/SPDH format due to edit problems on the Bit Map number displayed. Displayed with log message number 2310.
Effect:	ML logs the incoming message (log error 2330) and drops it with no further processing
Response:	Verify the incoming message format, particularly for the displayed Bit Map, against documented values. Contact the entity (acquirer or acceptor) from which the message was received to correct the message format.
Message-Number:	2340
Severity:	2 - Error
Message-Text:	Invalid ISO Type \\\ received - dropped
Variables:	\\ = ISO message type
Cause:	The message type on an incoming ISO message was received that is not one of those defined in the ISO message type set
Effect:	ML logs the incoming message (log error 2350) and drops it with no further processing.
Response:	Contact the entity (acquirer or acceptor) from which the message was received to correct the message type.
Message-Number:	2400
Severity:	3 - Critical
Message-Text:	Error while attempting to get device message token
Variables:	N/A
Cause:	An address was out of bounds or a required parameter was missing while attempting to find token data.
Effect:	Process abends..
Response:	Contact ACI Help Desk
Message-Number:	2420
Severity:	1 - Warning
Message-Text:	Error while attempting to get device message from context /SAF – DPC \\\
Variables:	\\ = DPC number
Cause:	The ML process was attempting to get the device message from context but timed out.
Effect:	A dummy device handler header for a late response is built.
Response:	If the problem continues, this indicates an internal code problem. Contact ACI Help Desk. The ML process will automatically attempt to resend the SAF message after a predefined interval.

Message-Number: 2422
Severity: 1 - Warning
Message-Text: IO ERROR: ***** SAF File: \F Err: \E, cont. processing
Variables: ***** = KEYPOSITION
 \F = SAF filename
 \E = Guardian error number or if -1 is returned, then params are wrong
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
ML logs the error and continues.
Effect: A dummy device handler header for a late response is built.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 2424
Severity: 1 - Warning
Message-Text: IO ERROR: ***** SAF File: \F Err: \E, cont. processing
Variables: ***** = READ
 \F = SAF filename
 \E = Guardian error number or if -1 is returned, then params are wrong
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
ML logs the error and continues.
Effect: A dummy device handler header for a late response is built.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3000
Severity: 1 - Warning or 2
Message-Text: IO ERROR: ***** LCONF File:\F Err:\E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3015
Severity: 1 - Warning, 2 or 3
Message-Text: IO ERROR: ***** MLCF File:\F Err:\E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3045
Severity: 1 - Warning, 2 or 3
Message: IO ERROR: ***** KEYF File: \F Err: \E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3065
Severity: 1 - Warning, 2 or 3
Message-Text: IO ERROR: ***** MMF File: \F Err: \E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3070
Severity: 1 - Warning, 2 or 3
Message-Text: IO ERROR: ***** MTF File: \F Err: \E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 3170
Severity: 1 - Warning
Message-Text: IO ERROR: ***** SAF File: \F Err: \E
Variables: ***** = IO operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number:	3200
Severity:	1 - Warning
Message-Text:	WARNING: No SAF file available - ACCEPTOR PROCESSING ONLY
Variables:	N/A
Cause:	When the ML attempted to open the SAF file, either no assign exists for the SAF file or the open of the SAF file failed.
Effect:	In either of the above two cases the ML will continue to process as an acceptor only.
Response:	If acceptor processing only is desired then no response is required. If acquirer processing is required then add an LCONF assign for the ML SAF file or check the guardian error on the 3170 open error message logged previously.
Message-Number:	3225
Severity:	2 - Error
Message-Text:	"DPC \\\ SAF count #, EOF on file \F. DPC reset
Variables:	\\\ = DPC number # = Original SAF record count \F = File name
Cause:	When attempting to send the next SAF transaction, an End of File has been reached on the SAF file for the indicated DPC, even though the SAF count indicates that the number of records in the SAF file is greater than zero.
Effect:	If no manual modification has been made to the SAF, this may indicate a problem with the SAF file. The ML thinks it has an outstanding reversal in the SAF that is not available. SAF processing is disabled by setting the SAF count to zero.
Response:	Examine any previous file errors on the SAF and make sure that the SAF file is present and configured correctly.
Message-Number:	4005
Severity:	2 - Error
Message-Text:	PROC ERROR: ALLOCATESEGMENT Code #
Variables:	# = Negative allocatesegment error code
Cause:	An attempt to allocate an extended memory segment failed. The indicated error is the allocatesegment error between -1 and -10.
Effect:	ML cannot set up its internal tables.
Response:	Check the indicated allocatesegment error in the System Procedure Calls manual to determine the appropriate response. Warmboot or restart ML. If the problem continues, it may indicate an internal problem. Contact the ACI Help Desk.
Message-Number:	4010
Severity:	2 - Error
Message-Text:	IO ERROR: ALLOCATESEGMENT Err: \E
Variables:	\E = Guardian error code
Cause:	An attempt to allocate an extended memory segment failed. The indicated GUARDIAN error returned relates to the creation or open of the swap file.
Effect:	ML cannot set up its internal tables.
Response:	Check the indicated GUARDIAN error to determine the appropriate response. Warmboot or restart ML.

Message-Number: 4015
Severity: 2 - Error
Message-Text: PROC ERROR: USESEGMENT failure
Variables: N/A
Cause: An attempt to use an extended memory segment failed.
Effect: ML cannot set up its internal tables.
Response: This indicates an internal code problem. Contact the ACI Help Desk.

Message-Number: 4020
Severity: 2 - Error
Message-Text: PROC ERROR: DEFINEPOOL Result: #
Variables: # = Define pool error code
Cause: An attempt to define a pool in an extended memory segment failed.
Effect: ML cannot set up its internal tables.
Response: This indicates an internal code problem. Contact the ACI Help Desk.

Message-Number: 4025
Severity: 2 - Error
Message-Text: IO ERROR: ***** SAF File: \F Err: \E
Variables: ***** = I/O operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response.

Message-Number: 4030
Severity: 1 - Warning
Message-Text: DPC \\\: MACing is disabled for this DPC
Variables: \\\ = DPC number
Cause: No KEYF record was found for the indicated DPC.
Effect: MACing from the ML to the indicated DPC is disabled.
Response: Check for an I/O error on the KEYF file in a previous log message. The GUARDIAN error code indicated will determine the appropriate response.

Message-Number: 4305
Severity: 1 - Warning
Message-Text: WARNING: Unable to add station \S - Table full
Variables: \S = Symbolic station name
Cause: The internal station table is full and another station cannot be added.
Effect: ML cannot build a complete station table.
Response: Stop and start the ML process to reconfigure the internal station tables.

Message-Number:	4310
Severity:	3 - Critical
Message-Text:	ABEND ERROR: LOGGER initialization error
Variables:	N/A
Cause:	Initialization of the LOGGER failed.
Effect:	ML cannot write log messages.
Response:	Check for previous hometerm messages indicating a GUARDIAN error occurred on the LOGGER. Correct the LOGGER problem and restart ML.
Message-Number:	4315
Severity:	3 - Critical
Message-Text:	ABEND ERROR: ML process failed initialization
Variables:	N/A
Cause:	The ML process failed initialization.
Effect:	ML logs the error and stops processing.
Response:	Check the log messages that appear immediately before this to determine the cause of the initialization failure.
Message-Number:	4320
Severity:	0 - Informational
Message-Text:	Base-24 / Merchant Link Interchange - Copyright 1992 by ACI Worldwide (Canada)
Variables:	N/A
Cause:	ML successfully completed initialization of the LOGGER.
Effect:	ML logs the message and continues to initialize.
Response:	None required.
Message-Number:	4325
Severity:	0 - Informational
Message-Text:	Process initialized. Mode: \?
Variables:	\? = Test/production mode
Cause:	ML has completed it's initialization.
Effect:	ML continues normal processing and is now ready to begin processing transactions.
Response:	None required.
Message-Number:	4330
Severity:	3 - Critical
Message-Text:	ABEND ERROR: Required parameter not passed: ML^INIT
Variables:	N/A
Cause:	The ML^INIT procedure was called without the LCONF file number which is a required parameter.
Effect:	The ML process will fail initialization or a warmboot.
Response:	This indicates an internal error. Contact the ACI Help Desk.

Message-Number: 4335
Severity: 3 - Critical
Message-Text: ABEND ERROR: LCONF initialization failed
Variables: N/A
Cause: Initialization of the LCONF assigns or params failed.
Effect: ML cannot complete its initialization of file assigns and parameters.
Response: Check for previous log messages indicating a GUARDIAN error occurred on the LCONF file. Correct the file system problem and restart ML.

Message-Number: 4340
Severity: 1 - Warning
Message-Text: Warning: PIN-PAD mapping will not be supported
Variables: N/A
Cause: The ML process failed to open the MMF file.
Effect: PIN-PAD mapping will not be supported.
Response: If PIN-PAD mapping is not required then no response is required; otherwise, the cause of the MMF open failure will appear in the log message immediately preceding this one. Check the GUARDIAN error code associated with the previous message to determine the appropriate response.

Message-Number: 4350
Severity: 2 - Error
Message-Text: IO ERROR: ***** MLCF File: \F Err: \E
Variables: ***** = I/O operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 4351
Severity: 2 - Error
Message-Text: IO ERROR: ***** EMF File: \F Err: \E
Variables: ***** = I/O operation
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect: ML logs the error and continues.
Response: Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 4355
Severity: 0 - Informational
Message-Text: DPCs= #, Stations= #, MAX in= #, MAX out= #, Context= #
Variables: # = Number of DPCs
= Number of stations
= Maximum number of requests in
= Maximum number of requests out
= Number of context entries
Cause: The ML process has completed initialization of the MLCF file.
Effect: ML logs the message and continues.
Response: For information only.

Message-Number: 4360
Severity: 3 - Critical
Message-Text: No DPCs defined in MLCF \F
Variables: \F = File name
Cause: The ML did not read any DPC records in the MLCF file.
Effect: The ML process will fail initialization or a warmboot.
Response: Add DPC records to the MLCF file for this ML process and restart.

Message-Number: 4361
Severity: 3 - Critical
Message-Text: DPC \\\ no records in EMF \F
Variables: \\\ = DPC number
\F = File name
Cause: The ML did not find any EMF records defined for the displayed DPC number.
Effect: The default required Bit Maps will be used on inbound and outbound ISO messages.
Response: For information only.

Message-Number: 4362
Severity: 0 - Informational
Message-Text: DPC \\\ EMF records loaded #
Variables: \\\ = DPC number
= Number of EMF records
Cause: The ML retrieved the displayed number of EMF records for manual control of required Bit Maps.
Effect: None.
Response: For information only.

Message-Number: 4375
Severity: 1 - Warning
Message-Text: DPC \\\ not warmbooted - DPC not found in MLCF
Variables: \\\ = DPC number
Cause: The indicated DPC that previously existed in the MLCF was not found during a warmboot of the ML process.
Effect: The ML process will continue to use the previously retrieved information for the indicated DPC.
Response: Add the indicated DPC to the MLCF file for this ML process and re-execute the warmboot.

Message-Number: 4405
Severity: 2 - Error
Message-Text: INIT ERROR: Assign \?: Open: \F Err: \E
Variables: \? = Assign name
 \F = File name
 \E = Guardian error code
Cause: A GUARDIAN error occurred when attempting to open the specified template file.
Effect: ML cannot process the indicated assign and initialization fails.
Response: Check the GUARDIAN error code to determine the appropriate response. Restart or warmboot the ML.

Message-Number: 4415
Severity: 2 - Error
Message-Text: INIT ERROR: Assign \?:Missing
Variables: \? = Assign name
Cause: The indicated assign could not be read from the LCONF file.
Effect: ML cannot determine the physical file associated with the assign.
Response: Add the assign to the LCONF. Restart or warmboot the ML.

Message-Number: 4420
Severity: 2 - Error
Message-Text: INIT ERROR: Assign \?: Invalid File Name
Variables: \? = Assign name
Cause: The physical file name associated with the indicated assign is invalid.
Effect: ML cannot process the indicated assign.
Response: Fix the assign in the LCONF. Restart or warmboot the ML.

Message-Number: 4430
Severity: 2 - Error
Message-Text: INIT ERROR: Param \?: Missing
Variables: \? = Param name
Cause: The indicated parameter could not be read from the LCONF file and ML does not have a default value.
Effect: ML cannot determine the correct value for the program variable associated with the indicated parameter.
Response: Add the parameter to the LCONF file. Restart or warmboot the ML.

Message-Number: 4435
Severity: 0 - Informational
Message-Text: INIT: Param \?: Default Used
Variables: \? = Param name
Cause: The specified param could not be read from the LCONF file and a default value has used.
Effect: ML continues processing using the default value.
Response: Confirm that the param in LCONF is correct and restart or warmboot the ML.

Message-Number: 4440
Severity: 0 - Informational
Message-Text: INIT: Param \?: Ignored during WARMBOOT
Variables: \? = Param name
Cause: The indicated parameter was ignored during a warmboot.
Effect: ML ignores the indicated parameter so that its internal table sizes are not changed during a warmboot.
Response: If the indicated parameter must be changed, change the LCONF parameter and restart ML.

Message-Number: 4445
Severity: 0 - Informational
Message-Text: INIT ERROR: Param \?: Invalid value
Variables: \? = Param name
Cause: The value of the indicated parameter was invalid.
Effect: ML could not process the parameter.
Response: Fix the parameter in the LCONF file. Restart or warmboot ML.

Message-Number: 4445
Severity: 0 - Informational
Message-Text: Param \? will not be used.
Variables: \? = Parameter name
Cause: ML Threshold Alert param is less than or equal to zero, or greater than 99.
Effect: Default values will be used.
Response: Use default parameters or change LCONF parameter setting.

Message-Number: 5000
Severity: 2 - Error
Message-Text: IPC ERROR: Completion on \F Tag: # # Err: \E
Variables: \F = File name
= Tag words 1 and 2
\E = Guardian error code
Cause: The indicated error occurred on an I/O on the indicated process file.
Effect: ML could not process the I/O completion.
Response: Check the GUARDIAN file error indicated to determine the appropriate response.

Message-Number: 5015
Severity: 2 - Error
Message-Text: Station \S not found. Check MLCF
Variables: \S = Symbolic station name
Cause: An external message was received from the indicated station but no record exists in the MLCF file for this station on the DPC contained in the message.
Effect: ML logs the message (as message 5020) and does not process the message any further.
Response: Check the MLCF file and correct the DPC number or add a record for this station if it should be there. If it is not a valid station for this ML process then check the station's destination process in the NEFS.

Message-Number: 5030
Severity: 2 - Error
Message-Text: Failed administrative message dropped: \?
Variables: \? = Admin message
Cause: A failed message was returned to the ML which was only an administrative message.
Effect: ML logs the message contents as part of the log message. If we are the acquirer then the message is dropped. If we are the acceptor then we check why we couldn't send it to the Device Handler.
Response: Check the message failure code to determine the appropriate response. Correct the problem and resend the message.

Message-Number: 5045
Severity: 2 - Error
Message-Text: SNA control message dropped Src: \S
Variables: \S = Symbolic station name
Cause: A message was received from a station and it was an SNA control message (message type "DFH" or "DFS").
Effect: ML drops the message.
Response: Investigation should be done to determine why the SNA control message was sent to the ML process. Check the station and line configuration for the indicated station.

Message-Number: 5047
Severity: 1 - Warning
Message-Text: Invalid message received Src: \S - dropped
Variables: \S = Symbolic station name
Cause: An invalid message type was received from a station.
Effect: ML logs the message (log message 5048) and drops the message.
Response: Investigation should be done to determine why the invalid message was received from the indicated station.

Message-Number: 5050
Severity: 2 - Error
Message-Text: ACK message dropped Src: \S
Variables: \S = Symbolic station name
Cause: A message was received from a station and it was an ACK message (message type "%05").
Effect: ML drops the message.
Response: Investigation should be done to determine why the ACK message was sent to the ML process. Check the station and line configuration for the indicated station.

Message-Number: 5065
Severity: 2 - Error
Message-Text: PROC ERROR: Timer Type:# Subtype:#
Variables: # = Timer type
= Timer subtype
Cause: A time-out of unknown type expired.
Effect: ML cannot process the time-out.
Response: This indicates an internal code problem. Contact the ACI Help Desk.

Message-Number:	5085
Severity:	0 - Informational
Message-Text:	DPC \\\\: Maximum time-outs reached for station \S
Variables:	\\\\ = DPC number \S = Symbolic station name
Cause:	A network management message timed-out for the indicated station on the indicated DPC and the number of time outs has now reached the maximum allowed for this station.
Effect:	ML marks the station down, stops the Wait for Traffic timer, and starts an Extended Network Management timer to generate an echotest or mark the station up, depending on whether network management is supported.
Response:	The user should investigate why the station is not responding to messages.
Message-Number:	5090
Severity:	2 - Error
Message-Text:	DPC \\\\: TOTALS message time-out
Variables:	\\\\ = DPC number
Cause:	A TOTALS message timed-out waiting for a response from the indicated DPC.
Effect:	The TOTALS request is unsuccessful and the ML process does NOT automatically retry.
Response:	The user should investigate why the DPC is not responding to messages. The TOTALS message must be retried manually.
Message-Number:	5095
Severity:	2 - Error
Message-Text:	DPC \\\\: ***** timeout for station \S - Retry in # secs
Variables:	\\\\ = DPC number ***** = Network management message type \S = Symbolic station name # = Number of seconds before retry occurs
Cause:	The indicated network management message timed-out for the indicated station on the indicated DPC.
Effect:	The number of time-outs for this station is incremented and the extended network management timer is started. The station is still marked up and normal processing continues.
Response:	The user should investigate why the station is not responding to messages.
Message-Number:	5105
Severity:	2 - Error
Message-Text:	DPC \\\\: SAF Record deleted - max retries exhausted
Variables:	\\\\ = DPC number
Cause:	An outbound SAF message timed-out on the indicated DPC and the maximum number of retries has been exceeded.
Effect:	The message is sent to the logger (as message 5110) and the SAF record is deleted from the SAF file.
Response:	The user should investigate why the DPC is not responding to messages. The SAF message will have to be processed manually in order to balance properly.

Message-Number: 5135
Severity: 2 - Error
Message-Text: IPC ERROR: RECEIVE Event:# Tag:# # PID: \F Err: \E
Variables: # = Event type
= Tag words 1 and 2
\F = Process name
\E = Guardian error code
Cause: An I/O error occurred on \$RECEIVE.
Effect: ML logs the error and continues processing.
Response: Check the GUARDIAN error code and the process name indicated to determine specific nature of the error and take action accordingly.

Message-Number: 6002
Severity: 0 - Informational
Message-Text: Invalid message rcvd - type= \\\ subtype= \\
Variables: \\\ = ISO message type
\\ = ISO message subtype
Cause: A Network Management message was received by the ML process that is either contained an unknown DPC number in the header or the header identifier was not equal to "ML" or it was an invalid message type and subtype combination.
Effect: ML does not process the Network Management message.
Response: Run an audit trace to determine the message source. Correct the message contents and try again. Valid message types and subtypes are as follows: 0800,001; 0800,002; 0800,101; 0800,201; 0800,301 and the corresponding 0810 responses.

Message-Number: 6005
Severity: 2 - Error
Message-Text: DPC \\\: MAC KeyChange failed – Error \ - \?
Variables: \\\ = DPC number
\ = Response code
\? = Error message text
Cause: A MAC keychange request message was denied for the indicated reason.
Effect: The MAC key is not updated and a MAC keychange response is returned with the indicated response code.
Response: Inform the requesting DPC of the error and correct based on the error message text given in the log message.

Message-Number: 6010
Severity: 0 - Informational
Message-Text: DPC \\\: Issuer MAC key \ updated
Variables: \\\ = DPC number
\ = Key index
Cause: A valid ISSUER key change request was processed for the indicated DPC.
Effect: ML stores the key information in the KEYF file and begins processing with the new MAC key.
Response: For information only.

Message-Number: 6015
Severity: 2 - Error
Message-Text: DPC \\\\: Logon failed – Error: \\
Variables: \\\\: = DPC number
\\: = Response code returned
Cause: A LOGON response message was received that contained a non-zero response code.
Effect: The LOGON response is rejected and an extended network management timer is set so that the logon request can be retried. The indicated DPC remains LOGGED OFF.
Response: Check the response code being returned in the logon response. Correct the problem based on the response code. The ML process will automatically retry the logon request at a predefined interval. If the problem continues, it may indicate an internal problem, contact the ACI Help Desk.

Message-Number: 6020
Severity: 2 - Error
Message-Text: DPC \\\\: Logoff failed - Error: \\
Variables: \\\\: = DPC number
\\: = Response code returned
Cause: A LOGOFF response message was received that contained a non-zero response code.
Effect: The LOGOFF response is rejected and an extended network management timer is set so that the logoff request can be retried.
Response: Check the response code being returned in the logoff response. Correct the problem based on the response code. The ML process will automatically retry the logoff request at a predefined interval. If the problem continues, it may indicate an internal problem, contact the ACI Help Desk.

Message-Number: 6025
Severity: 2 - Error
Message-Text: DPC \\\\: Late response to Key Change received - dropped.
Variables: \\\\: = DPC number
Cause: A MAC keychange response message was received after the request had already timed-out.
Effect: The MAC keychange response message is ignored
Response: A manual keychange can be generated with the NCS NEWMACKEY command if necessary. The ML process will automatically retry the keychange request at a predefined interval. If the problem continues, it may be necessary to increase the keychange time-out value to allow more time for the response to return.

Message-Number: 6030
Severity: 2 - Error
Message-Text: DPC \\\\: KeyChange error - Resp:\
Variables: \\\\: = DPC number
\\: = Response code
Cause: A MAC keychange response message was received that contained a non-zero response code.
Effect: The MAC keychange response is rejected and an extended network management timer is set so that the keychange request can be retried.
Response: Check the response code being returned in the keychange response. Correct the problem based on the response code. The ML process will automatically retry the keychange request at a predefined interval. If the problem continues, it may indicate an internal problem, contact the ACI Help Desk.

Message-Number: 6060
Severity: 0 - Informational
Message-Text: DPC \\\ Acquirer MAC key \ updated
Variables: \\\ = DPC number
\\ = Key index
Cause: A valid ACQUIRER key change response was processed for the indicated DPC.
Effect: ML stores the key information in the KEYF file and begins processing with the new MAC key.
Response: For information only.

Message-Number: 6065
Severity: 0 - Informational
Message-Text: DPC \\\: Reconciliation balances - Resp:\\
Variables: \\\ = DPC number
\\ = Network management message response code
Cause: A valid TOTALS response was processed for the indicated DPC.
Effect: ML logs the TOTALS response record in the MTF file.
Response: For information only.

Message-Number: 6070
Severity: 0 - Informational
Message-Text: DPC \\\: Reconciliation out-of-balance - Resp:\\
Variables: \\\ = DPC number
\\ = Network management message response code
Cause: A TOTALS response message was received that contained a "13" response code.
Effect: The TOTALS response is rejected and logged to the MTF.
Response: Contact the DPC and Investigate. Manual tracing and settlement may be required to determine the reason for the out-of-balance.

Message-Number: 6075
Severity: 2 - Error
Message-Text: DPC \\\: Reconciliation error - Resp:\\
Variables: \\\ = DPC number
\\ = Response code
Cause: A TOTALS response message was received that contained a non-zero (and not-"13") response code.
Effect: The TOTALS response is rejected and logged to the MTF.
Response: Check the response code being returned in the TOTALS response. Correct the problem based on the response code and resend the totals to the DPC in question with an NCS TOTALS command. The ML process will not automatically retry the TOTALS request. If the problem continues, it may indicate an internal problem, contact the ACI Help Desk.

Message-Number:	6077
Severity:	1 - Warning
Message-Text:	DPC \\\\: Reconciliation totals received after time-out - dropped
Variables:	\\\\ = DPC number
Cause:	A TOTALS response message was received after the request had already timed-out.
Effect:	The TOTALS response message is ignored
Response:	A manual TOTALS message can be generated with the NCS TOTALS command if necessary. If the problem continues, it may be necessary to increase the TOTALS time-out value to allow more time for the response to return.
Message-Number:	6079
Severity:	2 - Error
Message-Text:	DPC \\\\: Resp: \\ Logon synchronization in progress
Variables:	\\\\ = DPC number \\ = NMM response code
Cause:	A ECHO TEST response message was received that contained a non-zero response code.
Effect:	The LOGON message will be sent to the DPC.
Response:	Check the response code being returned in the logon response. Correct the problem based on the response code. The ML process will automatically retry the logon request at a predefined interval. If the problem continues, it may indicate an internal problem, contact ACI Help Desk.
Message-Number:	7000
Severity:	0 - Informational
Message-Text:	DPC \\\\: Error generating new MAC key
Variables:	\\\\ = DPC number
Cause:	A Call to the Atalla box failed during creation of a new MAC key for the indicated DPC.
Effect:	ML cannot send the key exchange message to the indicated DPC.
Response:	This indicates an internal code problem. Contact the ACI Help Desk.
Message-Number:	7005
Severity:	0 - Informational
Message-Text:	DPC \\\\: Station \\S marked DOWN
Variables:	\\\\ = DPC number \\S = Symbolic station name
Cause:	The ML process has been notified that the indicated station is no longer available for transaction processing.
Effect:	ML cannot use this station for the sending and receiving of transactions for the indicated DPC.
Response:	Check the error log for previous messages as to why the station is unavailable. If necessary, correct the problem and restart the station.
Message-Number:	7010
Severity:	0 - Informational
Message-Text:	DPC \\\\: Link marked DOWN
Variables:	\\\\ = DPC number
Cause:	There are no longer any stations available for the indicated DPC.
Effect:	ML cannot send or receive transactions for the indicated DPC.
Response:	Check the error log for previous 7005 messages as to why the stations for this DPC are unavailable. If necessary, correct the problem and restart the stations.

Message-Number: 7015
Severity: 0 - Informational
Message-Text: DPC \\\\: Station \S marked UP
Variables: \\\\: = DPC number
 \S = Symbolic station name
Cause: The ML process has been notified that the indicated station is now available for transaction processing.
Effect: ML can now use this station for the sending and receiving of transactions for the indicated DPC.
Response: For information only.

Message-Number: 7020
Severity: 0 - Informational
Message-Text: DPC \\\\: Link marked UP
Variables: \\\\: = DPC number
Cause: There is now at least one station available for processing transactions for the indicated DPC.
Effect: ML can now send and receive transactions for the indicated DPC.
Response: For information only.

Message-Number: 7025
Severity: 0 - Informational
Message-Text: DPC \\\\: is \\\\: and logged ON
Variables: \\\\: = DPC number
 \\\: = Link status
Cause: This message is generated when a successful logon is generated for the indicated DPC.
Effect: The indicated DPC is now logged on. ML can now send and receive transactions.
Response: For information only.

Message-Number: 7030
Severity: 0 - Informational
Message-Text: DPC \\\\: is \\\\: and logged OFF
Variables: \\\\: = DPC number
 \\\: = Link status
Cause: This message is generated when a successful logoff is generated for the indicated DPC.
Effect: The indicated DPC is now logged off. ML can no longer send and receive transactions.
Response: If this was the expected outcome, then no response is necessary, otherwise enter a LOGON command for this DPC.

Message-Number: 7053
Severity: 2 - Error
Message-Text: Internal Error - TOTALS could not be sent
Variables: N/A
Cause: The ML process encountered an error while trying to send a TOTALS message - no context entry is.
Effect: The TOTALS message cannot be sent.
Response: This indicates an internal code problem. Contact ACI Help Desk.

Message-Number: 7054
Severity: 2 - Error
Message-Text: Internal Error - TOTALS could not be sent
Variables: N/A
Cause: The ML process encountered an error while trying to send a TOTALS message - it was unable to start a message timer.
Effect: The TOTALS message cannot be sent.
Response: This indicates an internal code problem. Contact ACI Help Desk.

Message-Number: 7068
Severity: 2 - Error
Message-Text: ML to ISO conversion problems: DPC \\\\
Variables: \\\\
= DPC number
Cause: An internal ISO message structure could not be converted into external format.
Effect: Unable to send the Network Management Message.
Response: Contact ACI Help Desk.

Message-Number: 7108
Severity: 2 - Error
Message-Text: ML to ISO conversion problems: DPC \\\\
Variables: \\\\
= DPC number
Cause: An internal ISO message structure could not be converted into external format.
Effect: ML drops the message with no further processing.
Response: Contact ACI Help Desk. If the outgoing message is a transaction reply, manual reconciliation may be required.

Message-Number: 7070
Severity: 2 - Error
Message-Text: PROC ERROR: NETWRITE failure # Err: \E
Variables: # = Message failure flag
\E = Message failure code
Cause: A write to the nucleus failed.
Effect: ML cannot send a message to a destination process.
Response: Check the status of the nucleus. If no problems, this indicates an internal code problem. Contact ACI Help Desk.

Message-Number: 7077
Severity: 2 - Error
Message-Text: Process info error = #, initialization failed.
Variables: # = Error code
Cause: An error occurred at startup on the call to system procedure process_getinfo_
Effect: The process will abend.
Response: Contact ACI Help Desk.

Message-Number:	7078
Severity:	2 - Error
Message-Text:	Process info error = #, initialization failed.
Variables:	# = Error code
Cause:	An error occurred at startup on the call to system procedure processhandle_decompose_
Effect:	The process will abend.
Response:	Contact ACI Help Desk.
Message-Number:	7080
Severity:	0 - Informational
Message-Text:	WARNING: No available stations for SAF, DPC \\\
Variables:	\\ = DPC number
Cause:	The ML process was attempting to send a SAF message to the indicated DPC which does not currently have any stations up.
Effect:	The SAF message cannot be sent.
Response:	Start a station for the indicated DPC. The ML process will automatically attempt to resend the SAF message after a predefined interval.
Message-Number:	7085
Severity:	0 - Informational
Message-Text:	WARNING: No available timer for SAF, DPC \\\
Variables:	\\ = DPC number
Cause:	The ML process was attempting to send a SAF message to the indicated DPC but an error occurred when trying to start a message timer.
Effect:	The SAF message cannot be sent.
Response:	If the problem continues, this indicates an internal code problem. Contact the ACI Help Desk. The ML process will automatically attempt to resend the SAF message after a predefined interval.
Message-Number:	7090
Severity:	0 - Informational
Message-Text:	SECURE-DEV-TYP in LCONF is not set to TSS, failed.
Variables:	None
Cause:	The ML process is not configured to use TSS. The release 6.0 ML process requires TSS if MACing is to be used.
Effect:	The process will abend.
Response:	If MACing is required configure the ML to use TSS.
Message-Number:	7110
Severity:	2 - Error
Message-Text:	IO ERROR: ***** MTF File: \F Err: \E
Variables:	***** = I/O operation \F = File name \E = Guardian error code
Cause:	A GUARDIAN error occurred on the indicated file for the indicated I/O operation.
Effect:	ML logs the error and continues.
Response:	Check the GUARDIAN error code indicated to determine the appropriate response. If the error occurred during startup or warmbooting, the operation must be repeated.

Message-Number: 7120
Severity: 1 - Warning
Message-Text: Invalid ***** in Merchant Link message - dropped
Variables: ***** = ML header field name
Cause: A data check failed on the Merchant Link header.
Effect: ML logs the message (log error 7125) and drops the message.
Response: Investigation should be done to determine why the invalid message was received from the external message source.

Message-Number: 7130
Severity: 1 - Warning
Message-Text: Invalid ***** in SPDH format message - dropped
Variables: ***** = Device handler header field name
Cause: A data check failed on the Device Handler message portion of the Merchant Link message.
Effect: ML logs the message (log error 7135) and drops the message.
Response: Investigation should be done to determine why the invalid message was received from the external message source.

Message-Number: 7140
Severity: 3 - Critical
Message-Text: ** WARNING ** ML-SUSP-NOTIFY-PERCENT ## HAS BEEN REACHED.
Variables: ## = Parameter percentage set in LCONF
Cause: The number of suspense records held in memory is equal to or greater than the number specified by the LCONF parameter ML-SUSP-NOTIFY-PERCENT.
Effect: None.
Response: Increase the LCONF param ML-MAX-SUSPENSE.

Message-Number: 8005
Severity: 1 - Warning
Message-Text: ACCEPTOR Error: DPC \\\ is not logged on
Variables: \\\ = DPC number
Cause: An external message was received from the indicated DPC that was NOT logged on.
Effect: ML logs the error and declines the transaction with ISO response code "91" and BASE24 response code "074".
Response: Perform an NCS LOGON command for the indicated DPC. This error could also indicate a security problem. Check the source of the message to make sure it came from a valid location.

Message-Number:	8010
Severity:	2 - Error
Message-Text:	ACCEPTOR Error: DPC \\\\\ maximum inbound requests reached
Variables:	\\\\ = DPC number
Cause:	An external message was received from the indicated DPC which has already reached the maximum number of outstanding requests.
Effect:	ML logs the error and declines the transaction with ISO response code "91" and BASE24 response code "100".
Response:	This error message indicates a possible link or performance problem. If it continues, the user should check the appropriate responder and verify that the link is still functioning properly. The LCONF parameter ML-MAX-SUSPENSE should be checked and possibly increased to improve this situation.
Message-Number:	8020
Severity:	2 - Error
Message-Text:	SPAN ERROR: ACCEPTOR (ext) Message Failure: # Src: \\S
Variables:	# = Message failure code \\S = Symbolic process name
Cause:	The nucleus returned a message failure code from the indicated external message source to the acceptor side of the ML.
Effect:	ML logs the error and continues.
Response:	Check the nucleus message failure code indicated to determine the appropriate response.
Message-Number:	8027
Severity:	1 - Warning
Message-Text:	Invalid Reconciliation entity \ - totals not stored
Variables:	\ = Entered reconciliation entity value
Cause:	An internal message was received that contained an invalid value in the ML reconciliation entity field. Valid values are "0" through "5". 0 Totals not kept 1 Blanks 2 Retailer ID 3 Retailer Group 4 SPDH Terminal ID 5 Clerk ID
Effect:	Reconciliation Totals are not kept for this financial transaction.
Response:	This error indicates that the PIN PAD identifier for this transaction, defined on the PTDF, has an invalid reconciliation entity value. Correct the value.
Message-Number:	8035
Severity:	0 - Informational
Message-Text:	SPAN ERROR: ACCEPTOR (int) Message Failure:# Src: \\S
Variables:	# = Message failure code \\S = Symbolic process name
Cause:	The nucleus returned a message failure code from the indicated internal message source to the acceptor side of the ML.
Effect:	ML logs the error and continues.
Response:	Check the nucleus message failure code indicated to determine the appropriate response.

Message-Number:	8040
Severity:	1 - Warning
Message-Text:	WARNING: ACCEPTOR Reversal message lost
Variables:	N/A
Cause:	A failed message was returned that was a reversal (request subtype "C", "D" or "R").
Effect:	ML logs the reversal message (log message 8043) and drops the message.
Response:	Check the nucleus message failure code indicated to determine the appropriate response. Manual reconciliation of the reversal may be required.
Message-Number:	8050
Severity:	0 - Informational
Message-Text:	No DH header info present (Token X0)
Variables:	N/A
Cause:	An address was out of bounds or a required parameter was missing while attempting to find token data.
Effect:	ML logs error and drops the message..
Response:	Contact ACI Help Desk
Message-Number:	8070
Severity:	0 - Informational
Message-Text:	Only BASE24 release 6 or above is supported now.
Variables:	N/A
Cause:	If the LCONF parameter BASE24-REL is not set to 6.0.
Effect:	ML logs error and abends
Response:	Set BASE24-REL parameter to 60
Message-Number:	8071
Severity:	0 - Informational
Message-Text:	Only BASE24 release 6 or above is supported now.
Variables:	N/A
Cause:	If the LCONF parameter BASE24-REL is not set to 6.0.
Effect:	ML logs error and abends
Response:	Set BASE24-REL parameter to 60
Message-Number:	8072
Severity:	0 - Informational
Message-Text:	Only BASE24 release 6 or above is supported now.
Variables:	N/A
Cause:	If the LCONF parameter BASE24-REL is not set to 6.0.
Effect:	ML logs error and abends
Response:	Set BASE24-REL parameter to 60

Message-Number: 8073
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8074
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8075
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8076
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8077
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8078
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8079
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 8080
Severity: 0 - Informational
Message-Text: Only BASE24 release 6 or above is supported now.
Variables: N/A
Cause: If the LCONF parameter BASE24-REL is not set to 6.0.
Effect: ML logs error and abends
Response: Set BASE24-REL parameter to 60

Message-Number: 9005
Severity: 2 - Error
Message-Text: SAF Request Dropped for DPC \\\\
Variables: \\\\ = DPC number
Cause: An attempt to add a reversal request message to the SAF file failed for the indicated DPC.
Effect: ML logs the reversal message (log message 9007) and drops the message.
Response: Check the I/O error that occurred on the SAF file logged previously. The reversal message must be processed manually.

Message-Number: 9015
Severity: 2 - Error
Message-Text: No timer for SAF Response - DPC \\\\
Variables: \\\\ = DPC number
Cause: A SAF response message was received from the indicated DPC, but the corresponding request message had already timed-out.
Effect: ML logs the error message and drops the SAF response message. The corresponding SAF request message will be resent.
Response: None.

Message-Number: 9016
Severity: 3 - Critical
Message-Text: Error while attempting to get device message token.
Variables: N/A
Cause: An address was out of bounds or a required parameter was missing while attempting to find token data.
Effect: Process abends..
Response: Contact ACI Help Desk

Message-Number: 9017
Severity: 3 - Critical
Message-Text: Error while attempting to update device msg token.
Variables: N/A
Cause: An address was out of bounds or a required parameter was missing while attempting to find token data.
Effect: Process abends.
Response: Contact ACI Help Desk

Message-Number: 9018
Severity: 1 - Warning
Message-Text: DPC \\\\: Failed to add fid 'q' to device message token.
Variables: \\\\: = DPC number
Cause: Fid 'q' could not be added for 0420 reversal request..
Effect: ML logs the error and drops the message.
Response: If this problem continues, this could indicate an internal code problem. Contact ACI Help Desk.

Message-Number: 9020
Severity: 2 - Error
Message-Text: MAC Verify failed on SAF response for DPC \\\\: \\\\: = DPC number
Cause: A SAF response message was received from the indicated DPC, but the MAC key verification failed.
Effect: ML logs the error message and drops the SAF response message. The corresponding SAF request message will be resent at SAF timeout.
Response: If the MAC key appears correct then no response is required since the SAF request will be retried automatically; otherwise, verify the inbound MAC key for this DPC. If required, contact the DPC to generate a new working key to correct the MAC key problem.

Message-Number: 9025
Severity: 2 - Error
Message-Text: "Reversal Response Dropped for DPC \\\\: \\\\: = DPC number
Cause: An error occurred while trying to delete the reversal request message from the SAF file for the indicated DPC.
Effect: ML logs the reversal response message (log message 9027) and drops the message. The corresponding SAF request message will be resent.
Response: Check the I/O error that occurred on the SAF file logged previously.

Message-Number: 9040
Severity: 2 - Error
Message-Text: SPAN ERROR: ACQUIRER (ext) Message Failure # Src \S
Variables: # = Message failure code
 \S = Symbolic process name
Cause: The nucleus returned a message failure code from the indicated external message source to the acquirer side of the ML.
Effect: ML logs the error and continues.
Response: Check the nucleus message failure code indicated to determine the appropriate response.

Message-Number:	9045
Severity:	1 - Warning
Message-Text:	Reversal request dropped:
Variables:	N/A
Cause:	An internal message received by the acquirer ML that is being declined was found to be a reversal request.
Effect:	ML logs the reversal request message (log message 9047) and drops the message.
Response:	A manual adjustment of settlement totals for this PIN-PAD will be required.
Message-Number:	9049
Severity:	1 - Warning
Message-Text:	DPC \\\\: Completion is being SAFed
Variables:	\\ = DPC number
Cause:	An internal message was received by the acquirer ML from the indicated DPC, and it was found the declined condition.
Effect:	ML logs the event and stores the completion transaction in the SAF file.
Response:	Wait until the current SAF record has been sent and deleted.
Message-Number:	9051
Severity:	0 - Informational
Message-Text:	Force post request to BMO dropped
Variables:	N/A
Cause:	Enhancement to support BMO credit.
Effect:	ML logs the message (9052) and drops the transaction.
Response:	For information only.
Message-Number:	9055
Severity:	2 - Error
Message-Text:	No SAF available (decline)
Variables:	N/A
Cause:	An internal message was received by the acquirer ML but the ML does not have a SAF file open.
Effect:	ML logs the error and declines the transaction.
Response:	Add a SAF file assign to the LCONF for this process and WARMBOOT the ML.
Message-Number:	9060
Severity:	2 - Error
Message-Text:	DPC \\\\: Is not configured - Check MLCF (decline)
Variables:	\\ = DPC number
Cause:	An internal message was received by the acquirer ML but the DPC Number indicated was not found in the ML's internal DPC table.
Effect:	ML logs the error and declines the transaction.
Response:	Check the MLCF for the DPC Number indicated and add it if necessary. If this is NOT a valid DPC Number for this ML process then the BASE24 routing, particularly the IDF routing table, should be checked to find out why this request message was sent to this process.

Message-Number:	9065
Severity:	2 - Error
Message-Text:	DPC \\\\: pPad \\\\: Outstanding SAF (decline)
Variables:	\\\: = DPC number \\\: = PIN-PAD identifier
Cause:	An internal message was received by the acquirer ML but a SAF record already exists for the DPC Number and PIN-PAD indicated.
Effect:	ML logs the error and declines the transaction.
Response:	Wait until the current SAF record has been sent and deleted and then retry the transaction.
Message-Number:	9066
Severity:	0 - Informational
Message-Text:	Reversal request to BMO dropped.
Variables:	N/A
Cause:	Enhancement to support BMO credit.
Effect:	ML logs the message (9067) and then drops the transaction.
Response:	For information only.
Message-Number:	9070
Severity:	1 - Warning
Message-Text:	DPC \\\\: Is not logged ON (decline)
Variables:	\\\: = DPC number
Cause:	An internal message was received by the acquirer ML from the indicated DPC that was NOT logged on.
Effect:	ML logs the error and declines the transaction.
Response:	Perform an NCS LOGON command for the indicated DPC. This error could also indicate a security problem. Check the source of the message to make sure it came from a valid location.
Message-Number:	9075
Severity:	1 - Warning
Message-Text:	DPC \\\\: No stations are available (decline)
Variables:	\\\: = DPC number
Cause:	The acquirer ML process was attempting to send a message to the indicated DPC which does not currently have any stations up.
Effect:	ML logs the error and declines the transaction.
Response:	Start a station for the indicated DPC.
Message-Number:	9080
Severity:	2 - Error
Message-Text:	DPC \\\\: Maximum outbound requests exceeded (decline)
Variables:	\\\: = DPC number
Cause:	The acquirer ML process was unable to send a message to the indicated DPC because the maximum number of outstanding request messages has already been reached.
Effect:	ML logs the error and declines the transaction.
Response:	This error message indicates a possible link or performance problem. If it continues, the user should check the appropriate responder and verify that the link is still functioning properly. The LCONF parameter ML-MAX-SUSPENSE should be checked and possibly increased to improve this situation.

Message-Number: 9090
Severity: 2 - Error
Message-Text: SPAN ERROR: ACQUIRER (int) Message Failure:# Src:\S
Variables: # = Message failure code
 \S = Symbolic process name
Cause: The nucleus returned a message failure code from the indicated internal message source to the acquirer side of the ML.
Effect: ML logs the error and continues.
Response: Check the nucleus message failure code indicated to determine the appropriate response.