

Reference Manual

BASE24-from host maintenance[®]



© 2008 by ACI Worldwide, Inc. All rights reserved.

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, and the ACI product names used in this documentation are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	vii
1: Introduction	1-1
Processing	1-2
Files	1-4
Processes	1-5
Configuration Options	1-7
From Host Maintenance Process Options	1-7
ISO Host Interface Process Options	1-8
External Messages	1-9
Response Codes	1-10
Reporting	1-11
2: BASE24-from host maintenance Processing	2-1
From Host Maintenance Process	2-2
File and Table Usage	2-4
Process Configuration	2-10
Startup Logic	2-10
Host Interface Considerations	2-10
Routing	2-11
Event Messages	2-12
Reports	2-13
LCONF Assigns	2-13
LCONF Params	2-14
Required Assigns and Params	2-17
Initialization and Warmboot	2-19
Logging Records to the ULF	2-22
Logging Successful Updates	2-22
Logging Rejected Updates	2-23

BASE24-from host maintenance Processing *continued*

Message Flows	2-24
Message Routing Without an ISO Host Interface Process	2-25
Message Routing With an ISO Host Interface Process	2-27
Update Processing.	2-34
Add Request	2-34
Delete Request	2-36
Inquiry Request.	2-37
Change Request	2-38
Increment Request	2-40
Update Response Messages	2-41
 3: BASE24-from host maintenance Reporting	 3-1
Report Programs	3-2
File Usage	3-4
Report Types.	3-4
Starting the Report Program	3-4
Output Locations.	3-6
Report Errors.	3-7
Data Masking	3-7
Activity Reports	3-9
Cardholder Authorization File Activity Report	3-10
Cardholder Authorization File Accounts Segment Activity Report	3-29
Check Status File Activity Report	3-33
Corporate Check File Activity Report	3-37
Customer Table Activity Report	3-41
Customer/Account Relation Table Activity Report	3-48
Customer/Cardholder Information File Activity Report.	3-52
Customer/Cardholder Memo File Activity Report	3-61
Customer/Personal ID Relation Table Activity Report.	3-65
Negative Card File Activity Report	3-68
No Book File Activity Report.	3-72
Personal Information Table Activity Report.	3-77
Positive Balance File Activity Report.	3-82

BASE24-from host maintenance Reporting *continued*

Stop Payment File Activity Report	3-93
Warning/Hold/Float File Activity Report	3-97
Reject Reports.	3-101

4: Response Codes 4-1

BASE24-from host maintenance Response Codes	4-2
---	-----

Index Index-1

ACI Worldwide, Inc.

Preface

This manual provides an overview and technical description of the BASE24-from host maintenance product. This add-on product is designed for use with other BASE24 products and allows a customer to update BASE24 files and tables online from a host system.

Audience

ACI has prepared this publication for distribution to personnel responsible for the interface between BASE24-from host maintenance and a host system. This publication also provides an overview of the BASE24-from host maintenance system for those persons interested in gaining a general understanding of the system.

Prerequisites

Readers should be familiar with the other BASE24 products (e.g., BASE24-atm, BASE24-billpay, BASE24 Customer Service, BASE24-pos, BASE24-telebanking, or BASE24-teller) being used in conjunction with BASE24-from host maintenance. This knowledge allows readers to better understand functions of the various files described in this manual.

Additional Documentation

The BASE24 documentation set is arranged so that each BASE24 manual presents a topic or group of related topics in detail. When one BASE24 manual presents a topic that has already been covered in detail in another BASE24 manual, the topic is summarized and the reader is directed to the other manual for additional information. Information has been arranged in this manner to be more efficient for readers who do not need the additional detail and, at the same time, provide the source for readers who require the additional information.

This manual contains references to the following BASE24 publications:

- The ***BASE24 Base Files Maintenance Manual*** provides detailed descriptions of the fields in base files that can be updated using BASE24-from host maintenance.
- The ***BASE24 Core Files and Tables Maintenance Manual*** provides detailed descriptions of the BASE24-telebanking and BASE24-billpay tables that can be updated using BASE24-from host maintenance.
- The ***BASE24 Event Message Reference Manual*** provides detailed descriptions of the event messages generated by the From Host Maintenance process.
- The ***BASE24 External Message Manual*** describes the ISO-based external messages passed between BASE24-from host maintenance and the host processor.
- The ***BASE24 Logical Network Configuration File Manual*** provides detailed information about the assigns and params used by BASE24-from host maintenance.
- The ***BASE24-atm EMV Support Manual*** provides detailed information about Cardholder Authorization File (CAF) screen 13.
- The ***BASE24-card Reference Manual*** provides information about Cardholder Authorization File (CAF) screen 20.
- The ***BASE24-pos Address Verification Manual*** provides information about Cardholder Authorization File (CAF) screen 12.
- The ***BASE24-pos EMV Support Manual*** provides detailed information about Cardholder Authorization File (CAF) screen 13.
- The ***BASE24-teller Files Maintenance Manual*** provides detailed descriptions of the fields in BASE24-teller files that can be updated using BASE24-from host maintenance.
- Device-specific BASE24-atm self-service banking (SSB) manuals provide detailed descriptions of the fields specifically related to the BASE24-atm self-service banking application that can be updated using BASE24-from host maintenance.

This manual also contains references to the ***NET24-XPNET Network Control Command Reference Manual***, a NET24-XPNET publication that provides information on defining stations and lines in a network.

Software

This manual documents standard processing as of its publication date. Software that is not current and custom software modifications (CSMs) may result in processing that differs from the material presented in this manual. The customer is responsible for identifying and noting these changes.

Manual Summary

The *BASE24-from host maintenance Reference Manual* is divided into the following sections:

Section 1, “Introduction,” provides an introduction to BASE24-from host maintenance, including an overview of the BASE24 application files and tables that can be updated and the processes involved.

Section 2, “BASE24-from host maintenance Processing,” provides a more detailed look at BASE24-from host maintenance processing, including file and table usage, process configuration issues, initialization and warmboot processing, message flows, and the steps BASE24-from host maintenance follows as it performs each of the available update requests.

Section 3, “BASE24-from host maintenance Reporting,” describes the reports BASE24-from host maintenance provides. It also discusses the configuration options that determine what information will be available for reporting and extracting.

Section 4, “Response Codes,” provides the ISO response codes that can be returned by the From Host Maintenance process.

Publication Identification

Three entries appearing at the bottom of each page uniquely identify this BASE24 publication. The publication number (for example, FH-CM000-01 for the *BASE24-from host maintenance Reference Manual*) appears on every page to assist readers in identifying the manual from which a page of information was printed. The publication date (for example, 12/2008 for December 2008) indicates the issue of the manual. The software release information (for example, R6.0v9 for release 6.0, version 9) specifies the software that the manual describes. This information matches the document information on the copyright page of the manual.

ACI Worldwide, Inc.

1: Introduction

The BASE24-from host maintenance product enables users to make online updates to BASE24 application files and tables from a host computer. It is an add-on product designed for use in conjunction with BASE24-atm, BASE24-atm self-service banking, BASE24-billpay, BASE24 Customer Service, BASE24-pos, BASE24-telebanking, and BASE24-teller products.

The BASE24-billpay and BASE24-telebanking products are also known as BASE24 Remote Banking products.

This section provides an introduction to the BASE24-from host maintenance product.

Processing

The BASE24-from host maintenance product is designed to receive messages from a host and use these messages to update the following BASE24 application files and tables:


- Cardholder Authorization File (CAF)
- Check Status File (CSF), used by BASE24-atm self-service banking application only
- Corporate Check File (CCF), used by BASE24-atm self-service banking application only
- Customer Table (CSTT), used by BASE24 Remote Banking products only
- Customer/Account Relation Table (CACT), used by BASE24 Remote Banking products only
- Customer/Cardholder Information File (CCIF), used by the BASE24 Customer Service product only
- Customer/Cardholder Memo File (CCMF), used by the BASE24 Customer Service product only
- Customer/Personal ID Relation Table (CPIT), used by BASE24 Remote Banking products only
- Negative Card File (NEG)
- No Book File (NBF), used by BASE24-teller only
- Personal Information Table (PIT), used by BASE24 Remote Banking products only
- Positive Balance File (PBF)
- Stop Payment File (SPF)
- Warning/Hold/Float File (WHFF), used by the BASE24-teller product only

The BASE24-from host maintenance product supports five types of update actions. However, certain update actions can only be performed on a subset of the files and tables. The descriptions in section 2 indicate the update actions that can be performed on each BASE24 application file or table. The update actions are as follows:

- Add instructs the BASE24-from host maintenance product to add a record or row to the file or table.

- Delete instructs the BASE24-from host maintenance product to delete a record or row from the file or table.
- Inquiry instructs the BASE24-from host maintenance product to retrieve a record or row from the file or table and return the information to the host.
- Change instructs the BASE24-from host maintenance product to update an existing record or row with new information.
- Increment instructs the BASE24-from host maintenance product to increment or decrement the amount or limit fields in an existing record or row.

The following diagram illustrates the BASE24-from host maintenance product.



Files

The BASE24-from host maintenance product uses a number of files in addition to the application files and tables which it can update. The files used by the BASE24-from host maintenance product are listed below with a description of their use.

External Message File (EMF) — Contains records describing how ISO-based messages are formatted.

Institution Definition File (IDF) — Contains the names of all FIIDs, their active products, and the appropriate file names for each.

Log Message Configuration File (LMCF) — Stores each log message that has been altered by a network operator.

Logical Network Configuration File (LCONF) — Contains assigns and params used by BASE24-from host maintenance during transaction processing.

Store-and-Forward File (SAF) — When the BASE24-from host maintenance product is configured with an ISO Host Interface process, the ISO Host Interface process uses the SAF to store messages intended for the host computer while the host cannot be reached. The From Host Maintenance process does not use the SAF.

Update Log File (ULF) — Stores images of successful and attempted updates to BASE24 application files and tables.

Processes

Updates to application files and tables are performed when the host sends a message to BASE24-from host maintenance, which edits the information in the message, applies the requested change to the BASE24 database, logs a record to the Update Log File (ULF), and responds to the host with the action taken.

BASE24-from host maintenance is composed of one process and several report programs. Two additional processes may also be used in processing. They are the Host Interface and Super Extract processes. The paragraphs below describe how these processes and the report programs are used with BASE24-from host maintenance.

From Host Maintenance Process — This process allows application file or table updates to be performed from the host. The From Host Maintenance process receives an update message and applies the update to the appropriate BASE24 file or table. The From Host Maintenance process is also responsible for logging transactions to the Update Log File (ULF), changing over the ULF to the next business date at cutover, and starting the report program.

Report Programs — These programs create BASE24-from host maintenance reports from data stored in the ULF. The From Host Maintenance process is responsible for starting the report programs, based on parameters specified in the LCONF. Two separate reports are produced for each application file or table updated. One report details successful updates to the file or table and the other lists rejected updates and gives the reason for rejection.

ISO Host Interface Process — This process maintains the Store-and-Forward File (SAF), which stores messages intended for the host computer while the host cannot be reached. BASE24-from host maintenance can be configured with or without an ISO Host Interface process.

With BASE24-from host maintenance and an ISO Host Interface process, a single connection to the host can be used for carrying transaction information from BASE24 to the host and carrying file or table update information from the host to BASE24. When an ISO Host Interface process is configured, it receives requests from the host and forwards them to the From Host Maintenance process for processing. The From Host Maintenance process then returns the responses to the Host Interface, which sends them on to the host. If the connection to the host is down, the ISO Host Interface process stores responses in the SAF. When the connection with the host is restored, the ISO Host Interface process takes each of the accumulated responses from the SAF and sends it to the host.

When BASE24-from host maintenance is configured without an ISO Host Interface process, BASE24-from host maintenance uses its own connection to the host and there is no store-and-forward capability.

Super Extract Process — Reads all update records from the Update Log File (ULF) and places them on tape, which can be used by the host for reporting. The Super Extract process reads the Extract Configuration File (ECF) to determine which update records are to be extracted and when they are to be extracted.

Configuration Options

BASE24-from host maintenance offers configuration options based on the number of From Host Maintenance processes in the system and whether the system uses an ISO Host Interface process.

From Host Maintenance Process Options

A logical network can have one main and up to 16 secondary From Host Maintenance processes. The main and secondary From Host Maintenance processes share a single Update Log File (ULF) and are identical in terms of handling messages between the host and BASE24. The main From Host Maintenance process has the added responsibility for certain aspects of cutover processing and report generation.

Main From Host Maintenance Process

One main From Host Maintenance process must be defined for each logical network. A logical network cannot have more than one main From Host Maintenance process. The main From Host Maintenance process is responsible for the following tasks:

- Creating daily ULFs at logical network cutover and, when needed, at process startup.
- Creating and running report obey files when required.
- Purging old ULFs and report obey files when the retention periods expire.
- Sending cutover messages to all secondary From Host Maintenance processes notifying them to cut over to the new ULF.

Secondary From Host Maintenance Process

Up to 16 secondary From Host Maintenance processes can be defined for each logical network. However, no secondary From Host Maintenance processes need to be defined if the main From Host Maintenance process can handle the message activity. Each secondary From Host Maintenance process is responsible for the following tasks:

- Opening (but not creating) the current ULF at process startup.
- Processing cutover messages from the main From Host Maintenance process by closing the old ULF and opening (but not creating) the new ULF.

ISO Host Interface Process Options

The BASE24-from host maintenance product can be configured with or without an ISO Host Interface process.

With an ISO Host Interface Process

When the BASE24-from host maintenance product is configured with an ISO Host Interface process, messages from the host are sent to the ISO Host Interface process. The ISO Host Interface process then forwards the message to the From Host Maintenance process. Using the ISO Host Interface process allows a Store-and-Forward File (SAF) to be created when the BASE24-from host maintenance product is unable to communicate with the host computer. The SAF is used to store responses to file and table update requests that cannot be forwarded to the host because of lost communications. Once communications with the host are restored, the pending SAF records are forwarded to the host and purged from the file.

Without an ISO Host Interface Process

When the BASE24-from host maintenance product is configured without an ISO Host Interface process, messages from the host are sent directly to the From Host Maintenance process and the From Host Maintenance process returns messages directly to the host. Messages to the host are lost if the host is unavailable. However, depending on the settings that determine ULF logging, the information that would be returned to the host is logged to the ULF and included in the reports.

External Messages

BASE24-from host maintenance can send and receive messages from the host in two releases:

- Release 6.0 ISO-based format
- Release 5.x ISO-based format

The FHM-REL-IND param in the LCONF indicates if the current release format or the previous release format is supported. The valid values for this param are 01 (current) and 02 (previous).

The ISO-based format, which is patterned after the standard external message developed by the International Organization for Standardization (ISO), is described in the ***BASE24 External Message Manual***.

Response Codes

In every response to the host, there is a response code indicating what action was taken with the transaction. The response codes that can be sent by the From Host Maintenance process are described in section 4.

Reporting

The BASE24-from host maintenance report programs are responsible for reporting all information written to the Update Log File (ULF). The ULF contains records of accepted and rejected application file or table changes, additions, deletions, increments, and inquiries. The report programs report all information that was logged to the ULF, including information built or modified at the host, as well as who made the change, and the response to the message.

Two reports can be created for each file or table updated: a report showing successful transactions and a report showing rejected transactions.

For more information on reports, refer to section 3.

ACI Worldwide, Inc.

2: BASE24-from host maintenance Processing


This section describes BASE24-from host maintenance processing. It includes descriptions of the From Host Maintenance process, BASE24-from host maintenance message flows, and the processing done when an update message is received. This section also describes the options available for controlling the production of update response messages to the host and the logging of update information to the Update Log File (ULF).

From Host Maintenance Process

The From Host Maintenance process is responsible for updating BASE24 application files and tables. When an update message is received, the From Host Maintenance process edits the information in the message, applies the requested change to the database, and logs a message to the ULF.

The From Host Maintenance process consists of a base module and selected file and table modules. The base module used determines which messages are exchanged with the DPC. The base module also determines which BASE24 application files can be updated. However, there is a separate file or table module for each application file or table that can be updated, and the module for each application file or table the financial institution wants to update must be bound in with the base module before the From Host Maintenance process can update the file or table.

The illustration on the following page depicts BASE24-from host maintenance processing.



File and Table Usage

Descriptions of the files and tables the From Host Maintenance process uses in its processing are provided below. Each description includes how the file or table is used, when the file or table is used, what the From Host Maintenance process does with the information it reads from the file or table, and where the From Host Maintenance process gets the information it writes to the file or table.

Cardholder Authorization File (CAF) — The CAF is a shared file that contains one record for each cardholder whose card-issuing institution uses the Positive, Positive Balance, or Parametric Authorization method. The From Host Maintenance process is responsible for updating the CAF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The CAF is a segmented file, so the processing that can be performed by the From Host Maintenance process on CAF records depends on the segment being updated, as shown in the following table.

Record Segment	Type of Update				
	Add	Delete	Inquire	Change	Increment
Base	✓	✓	✓	✓	✓
ATM	✓	*	✓	✓	✓
POS	✓	*	✓	✓	✓
Account	✓	*	✓	✓	
Address Verification	✓	*	✓	✓	
Preauthorized Hold	✓	*	✓	✓	
Enhanced Preauthorized Hold	✓	*	✓	✓	
SSB Base	✓	*	✓	✓	
SSB Check	✓	*	✓	✓	✓
EMV	✓	*	✓	✓	✓

Record Segment	Type of Update				
	Add	Delete	Inquire	Change	Increment
NCD	✓	*	✓	✓	✓
Card	✓	*	✓	✓	

* The entire record is deleted by deleting the Base segment.

Note: BASE24-from host maintenance provides the option of updating the entire CAF record or updating the Accounts segment plus a limited amount of information in the Base segment of the CAF record. Data element S-101 (File Name) in the ISO-based external message identifies whether a message is for an entire CAF record or just the Accounts segment. Messages updating the entire CAF record appear on BASE24-from host maintenance activity and reject reports for the CAF, while messages updating only the CAF Accounts segment appear on activity and reject reports for the CAF Accounts segment.

Check Status File (CSF) — The CSF contains a record for each check registered by a cardholder and a record for each preapproved or predeclined check defined by an institution using the BASE24-atm self-service banking (SSB) Enhanced Check Application. The From Host Maintenance process is responsible for updating the CSF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Corporate Check File (CCF) — The CCF, which is used with the BASE24-atm self-service banking (SSB) Enhanced Check Application, contains information regarding corporations or entities with which an SSB terminal owner has previously established a check processing agreement. The From Host Maintenance process is responsible for updating the CCF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Customer Table (CSTT) — The CSTT is a core table that contains one row for each customer allowed to perform BASE24 Remote Banking product services. This row contains authorization parameters and usage accumulation information for the specified customer. The From Host Maintenance process is responsible for updating the CSTT when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Customer/Account Relation Table (CACT) — The CACT is a core table that contains one row for each account that is associated with a customer ID. This table is used in conjunction with the Positive Customer with Accounts Authorization method and Positive Customer with Balances/History Authorization method. The From Host Maintenance process is responsible for updating the CACT when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Customer/Cardholder Information File (CCIF) — The CCIF, which is used with the BASE24 Customer Service product, contains information about a customer or cardholder that cannot be found elsewhere in the BASE24 system. This information includes the cardholder's primary and secondary addresses, telephone numbers, and government number (for example, a social security number). The From Host Maintenance process is responsible for updating the CCIF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Customer/Cardholder Memo File (CCMF) — The CCMF, which is used with the BASE24 Customer Service product, contains information about lost or stolen cards and memo information entered by a customer service representative. The From Host Maintenance process is responsible for updating the CCMF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Customer/Personal ID Relation Table (CPIT) — The CPIT is a core table that contains one row for every valid customer/cardholder and personal ID combination. It allows multiple customer/cardholder (for example, CSTT) rows to be associated with a single Personal Information Table (PIT) row and also allows multiple PIT rows to be associated with a single customer/cardholder. The use of the CPIT is optional in BASE24 Remote Banking. The From Host Maintenance process is responsible for updating the CPIT when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

External Message File (EMF) — During initialization, the From Host Maintenance process retrieves the EMF records for 0300 and 0310 message types, if they exist. These records describe how ISO-based messages are formatted. If no EMF exists or the EMF does not contain records for the 0300 and 0310 message types, the From Host Maintenance process uses hard-coded defaults to format ISO-based messages.

Institution Definition File (IDF) — The IDF contains one record for each institution participating in the logical network and defines processing for each institution. The From Host Maintenance process uses the IDF to build an internal table containing the FIIDs of all institutions using BASE24-from host maintenance, their active products, and the appropriate file names for each. At initialization, the From Host Maintenance process reads the IDF sequentially from beginning to end. Using the information from the file, the From Host Maintenance process builds a table containing the names of the application files it can update.

Log Message Configuration File (LMCF) — The LMCF contains one record for each log message that has been altered by a network operator. At initialization, the From Host Maintenance process reads the LMCF for any changes in the event messages it uses.

Logical Network Configuration File (LCONF) — The LCONF contains the assigns and params needed to define BASE24 processing for a logical network. During initialization, the From Host Maintenance process reads the LCONF and retrieves the appropriate assigns and params it requires for processing. If any required assign or param is missing, the process generates a log message and is unable to continue until the assign or param is added to the LCONF.

Negative Authorization File (NEG) — The NEG is a shared file that contains one record for each special-status card whose card issuer uses the Negative with Usage Accumulation or Negative without Usage Accumulation Authorization method. The From Host Maintenance process is responsible for updating the NEG when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The NEG is a segmented file, so the processing that can be performed by the From Host Maintenance process on NEG records depends on the segment being updated, as shown in the following table.

Record Segment	Type of Update				
	Add	Delete	Inquire	Change	Increment
Base	✓	✓	✓	✓	
SSB Base	✓	*	✓	✓	
SSB Check	✓	*	✓	✓	

* The entire record is deleted by deleting the Base segment.

No Book File (NBF) — The NBF is a BASE24-teller file that contains one record for each passbook transaction. The From Host Maintenance process is responsible for updating the NBF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The From Host Maintenance process can perform the following updates to NBF records: add, delete, or inquire.

Personal Information Table (PIT) — The PIT is a core table that contains personal information about the customer that can be used by the customer service representative (CSR) for customer verification processing. This table can be linked to the Customer Table (CSTT) directly by the personal ID and indirectly by the Customer/Personal ID Relation Table (CPIT). The PIT and CPIT are optional in BASE24 Remote Banking. The From Host Maintenance process is responsible for updating the PIT when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information.

Positive Balance File (PBF) — The PBF is a shared file that contains one record for each account belonging to a BASE24-atm, BASE24-pos, or BASE24-teller customer whose card issuer uses the Positive Balance or Parametric Authorization method. The BASE24-teller product also enables an institution's customers to access PBF accounts without plastic cards. The PBF also contains one record for each account belonging to a BASE24 Remote Banking customer whose account issuer uses the Positive Customer with Balances/History Authorization method. With the BASE24 Customer Service product, the PBF also contains account history and status information for each BASE24-atm or BASE24-pos account tied to a card number whose issuer uses the Positive Balance or Parametric Authorization method.

The From Host Maintenance process is responsible for updating the PBF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The PBF is a segmented file, so the processing that can be performed by the From Host Maintenance process on PBF records depends on the segment being updated, as shown in the following table.

Record Segment	Type of Update				
	Add	Delete	Inquire	Change	Increment
Base	✓	✓	✓	✓	✓
POS	✓	*	✓	✓	✓

Record Segment	Type of Update				
	Add	Delete	Inquire	Change	Increment
Telebanking	✓	*	✓	✓	✓
Teller	✓	*	✓	✓	✓
Credit Line		*	✓	✓	✓
Preauthorized Hold	✓	*	✓	✓	
Short Name	✓	*	✓	✓	
Customer Service	✓	*	✓	✓	

* The entire record is deleted by deleting the Base segment.

Stop Payment File (SPF) — The SPF is a shared file that contains one record for each customer- or institution-initiated stop pay item. The SPF is used by BASE24-teller and the BASE24-atm add-on self-service banking Application. The From Host Maintenance process is responsible for updating the SPF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The From Host Maintenance process can perform the following updates to SPF records: add, delete, or inquire.

Update Log File (ULF) — The From Host Maintenance process uses the ULF to store records of successful and rejected updates to the application files. The From Host Maintenance process adds a before image of the record to the ULF each time a deletion is made. An after image of the record is logged for additions. Both before and after images are added for changes and increments. Rejected updates are also logged, with a response code indicating why the update was rejected.

Warning/Hold/Float File (WHFF) — The WHFF is a BASE24-teller file that contains one record for each customer- or institution-initiated warning, hold, or deposit float item. The From Host Maintenance process is responsible for updating the WHFF when update messages are received from the host. The update message indicates the type of update to be performed and provides all of the necessary information. The From Host Maintenance process can perform the following updates to WHFF records: add, delete, or inquire.

Process Configuration

This section contains information on how the From Host Maintenance process is configured. It provides information on the startup logic of the From Host Maintenance process, how an ISO Host Interface process can be used with BASE24-from host maintenance, and how the From Host Maintenance process sends and receives messages. This section also contains information on how BASE24-from host maintenance event messages are logged and reports are started. Logical Network Configuration File (LCONF) assigns and params play an important role in configuring the From Host Maintenance process. These assigns and params are summarized in this section.

Startup Logic

The From Host Maintenance process is assigned a startup logic of demand in the XPNET system. Demand indicates that the process is not automatically initialized at system startup but rather it is started when the first message destined for the process is received.

Note: When secondary From Host Maintenance processes are configured, the main From Host Maintenance process must be started before any secondary processes are started because only the main process can create an Update Log File (ULF). Secondary processes abend if they are started when the ULF does not exist.

Host Interface Considerations

BASE24-from host maintenance can be configured with an ISO Host Interface process, or no Host Interface process. If BASE24-from host maintenance is configured without a Host Interface process, messages are sent directly to the From Host Maintenance process and are returned directly to the host.

If BASE24-from host maintenance is configured with a Host Interface process, messages are sent to the Host Interface process and the Host Interface process forwards the messages to the From Host Maintenance process. The From Host Maintenance process processes the message and sends its response to the Host Interface process, which sends the message on to the host. When communications between the host and the From Host Maintenance process are down, the Host Interface process is responsible for storing messages in the Store-and-Forward File (SAF).

The main advantage of using a Host Interface process is that it allows a SAF to be created when BASE24-from host maintenance is unable to communicate with the host computer. The SAF is used to store completed transactions directed to the host from BASE24 during periods when the communications link is down between the host and BASE24. Once communications with the host are restored, each pending SAF record is forwarded to the host and purged from the file. The SAF does not contain requests directed to BASE24 from the host.

The ISO Host Interface process receives and sends ISO-based external messages. In addition, the ISO Host Interface process verifies that the correct bit maps and mandatory and conditional fields are present in the message. The ISO-based external message is described in detail in the ***BASE24 External Message Manual***.

The same Host Interface process can be set up to process host messages for multiple BASE24 products. If an institution purchases multiple BASE24 products, the appropriate product code is bound into the Host Interface process to allow it to recognize and process transaction messages for different products. Thus, the product code for the BASE24-from host maintenance Host Interface would be bound in with the code for the product-specific Host Interface process.

Another advantage of using a Host Interface process is the ability for BASE24-from host maintenance and other BASE24 products to share the same line or lines when communicating with the host computer. Without a Host Interface process, BASE24-from host maintenance requires its own communication lines for communicating with the host computer.

Routing

The From Host Maintenance process is linked to the other BASE24 processes with which it communicates using definitions in the XPNET system and file settings in the Host Configuration File (HCF).

All hosts are defined to the BASE24 system as stations. Stations provide the means by which communication takes place between BASE24 and a host. All messages received from a host are actually received from stations.

The XPNET process controls BASE24 interaction with its stations. The XPNET process receives inbound transactions and routes them to the appropriate processes. The XPNET process determines which process to send a message to using a station table in memory, which it builds at startup from station definitions.

Each station definition contains a **DESTINATION** attribute, which identifies the process to which all messages from the station are to be sent. For configurations without a Host Interface, the **DESTINATION** attribute should specify a From Host Maintenance process. For configurations with a Host Interface, the **DESTINATION** attribute should specify an ISO Host Interface process. Using the **DESTINATION** attribute, the **XPNET** process forwards messages to the designated process.

If a ISO Host Interface process is involved, it determines the name of the From Host Maintenance process to which to send update requests from the **FHM UPDATE PROCESS** field on HCF screen 13. When a Host Interface process is involved, each From Host Maintenance process must be defined in the HCF.

For more information on defining stations and lines to a network, refer to the ***NET24-XPNET Network Control Command Reference Manual***.

Event Messages

The From Host Maintenance process generates event messages to assist network operators in performing their daily tasks. Event messages provide information regarding the internal condition of the system. They are a network operator's primary link to what is actually occurring in the system. Event messages provide operators with information ranging from system status, such as the completion of a procedure, to more serious circumstances requiring operator intervention.

ACI has developed a method that allows customers to access log message documentation electronically. Log message descriptions are contained in files on a designated subvolume. Each file contains event messages for a specific BASE24 process. The files are organized according to product module ID (PMID). One PMID exists for each BASE24 process. PMIDs identify a specific process in the BASE24 system (for example, FHM identifies the From Host Maintenance process). Providing log message documentation in files on the Tandem computer gives customers greater flexibility by allowing them to view and print log message documentation as needed at their location.

The From Host Maintenance process sends all its event messages to the network logging facility using a standard routing code of 8, which indicates that they came from a BASE24-from host maintenance process. Documentation is available in file form for the event messages generated by the From Host Maintenance process. It is located on the **BAXxLOGM**, where *xx* is the number of the current release, subvolume in a file named **FHM**. For a complete explanation of log message documentation, refer to the ***BASE24 Event Message Reference Manual***.

Reports

The main From Host Maintenance process is responsible for starting the BASE24-from host maintenance reports. It does so by creating an obey file to start the report programs and then running the obey file at the appropriate time.

At the time specified in the LCONF param FHM-LN-CUTOVER, the From Host Maintenance process creates an obey file containing the commands necessary to run the report programs from a Tandem TACL prompt. Using the LCONF param FHM-RPT-STARTUP, the From Host Maintenance process sets a timer to expire when the reports are to be run. When the timer expires, the From Host Maintenance process runs the obey file created at cutover.

Refer to section 3 for report formats.

LCONF Assigns

The From Host Maintenance process reads the Logical Network Configuration File (LCONF), whenever it is initialized or reinitialized, for the assigns needed during processing. The assigns used by the From Host Maintenance process are listed below. Refer to the *BASE24 Logical Network Configuration Manual* for additional information regarding these assigns.

EMF — The physical file name of the External Message File.

CCIF*identifier* — The physical file name of the Customer/Cardholder Information File, where *identifier* is the name of the refresh group.

CCMF*identifier* — The physical file name of the Customer/Cardholder Memo File, where *identifier* is the name of the refresh group.

FHM-CSFC-RPT-PROG-NAME — The name of the From Host Maintenance Report program for the BASE24 Customer Service report group.

FHM-CUST-RPT-PROG-NAME — The name of the From Host Maintenance Report program for the Customer ID report group.

FHM-PSNL-RPT-PROG-NAME — The name of the From Host Maintenance Report program for the Personal ID report group.

FHM-RPT-CMD-FILE — The spooler location for event messages the From Host Maintenance process generates while creating reports.

FHM-RPT-OBEY-FILE — The name to give the template for the From Host Maintenance report obey file.

FHM-RPT-PROG-NAME — The name of the From Host Maintenance Report program for the Base report group, which includes base, BASE24-atm self-service banking, and BASE24-teller reports.

IDF — The physical file name of the Institution Definition File.

LMCF — The physical file name of the Log Message Configuration File.

SSB-CCF — The physical file name of the Corporate Check File.

SSB-CSF — The physical file name of the Check Status File.

ULF — The physical file name of the Update Log File.

LCONF Params

The From Host Maintenance process reads the LCONF, whenever it is initialized or reinitialized, for the params needed during processing. The params used by the From Host Maintenance process are listed below. Refer to the ***BASE24 Logical Network Configuration Manual*** for additional information, including valid values and default values, for these params.

ACCT-NUM-TYP — Indicates whether account numbers are stored in binary or decimal form. The binary form, which is not currently supported, allows the account number to be up to 28 digits in length. The decimal form allows the account number to be up to 19 digits.

FHM-CSFC-RPT — Indicates whether the From Host Maintenance process is to include the BASE24 Customer Service reports for the customer service files (that is, the Customer/Cardholder Information File and Customer/Cardholder Memo File) when the BASE24-from host maintenance reports are generated.

FHM-CUST-RPT — Indicates whether the From Host Maintenance process is to include the BASE24-telebanking reports for the customer tables (that is, Customer Table and Customer/Account Relation Table) when the BASE24-from host maintenance reports are generated.

FHM-ISO-FIXED-LENGTH — Indicates whether certain variable-length fields in the ISO-based external message should be treated as fixed length. The BASE24-from host maintenance data elements affected by this option include the following:

- P-2 Primary Account Number
- P-48 BASE24-from host maintenance Additional Data
- P-60 BASE24-from host maintenance Data
- P-61 BASE24-from host maintenance User Data
- S-101 File Name
- S-126 BASE24-from host maintenance Application File and Table Information

Note: The BASE24-from host maintenance Miscellaneous Information element (S-126) can be treated only as a fixed-length field when the File Name element (S-101) contains the value CA (Accounts segment in the CAF).

FHM-LN-CUTOVER — Indicates the time of day (hh:mm) the From Host Maintenance process cuts over to a new business date.

FHM-MASTER — Indicates which From Host Maintenance process is the main when more than one copy of the From Host Maintenance process is running. The main From Host Maintenance process is responsible for running the BASE24-from host maintenance reports.

FHM-MAX-NUM-FILE-ENTRIES — Specifies the maximum number of entries allowed in the file table. The file table is built from the Institution Definition File (IDF) and contains all FIIDs, their products, and file names. The file table is used by the From Host Maintenance process. The range of valid values is 0–2340.

FHM-PSNL-RPT — Indicates whether the From Host Maintenance process is to include the BASE24-telebanking reports for the personal information tables (that is, Personal Information Table and Customer/Personal ID Relation Table) when the BASE24-from host maintenance reports are generated.

FHM-REL-IND — Indicates whether the current (6.0) or previous (5.x) release of BASE24-from host maintenance message is being used.

FHM-RPT — Indicates whether the From Host Maintenance process is to include the base reports when the BASE24-from host maintenance reports are generated.

FHM-RPT-CPU — Specifies the number of the processor (CPU) where reports are run.

FHM-RPT-FILE-RETENTION — Indicates the number of days to retain BASE24-from host maintenance report obey files. After the specified number of days has passed, the files are automatically purged by the From Host Maintenance process.

FHM-RPT-PRI — Indicates the execution priority at which the reports are run.

FHM-RPT-STARTUP — Indicates the time the From Host Maintenance process should run the reports. If the FHM-RPT-STARTUP param is missing or invalid, reports are started at cutover.

FHM-SLAVE-NOTIFY*identifier* — The symbolic name of a secondary From Host Maintenance process to which the main From Host Maintenance process must send a 9502 message at cutover. The main From Host Maintenance process uses this param when multiple From Host Maintenance processes are configured in a single logical network. A maximum of 16 processes can be notified.

Each FHM-SLAVE-NOTIFY param contains the name of one process. When multiple processes must be notified, this param can include an optional *identifier* to specify params used for different processes in the same logical network. The optional *identifier* is usually a number but can be any unique set of characters that has not already been declared by another FHM-SLAVE-NOTIFY param.

FHM-ULF-AUDIT — Controls the extent of record logging to the ULF. The following options are available:

Do not log to the ULF
Log ULF header and record image
Log ULF header only

FHM-ULF-FILE-RETENTION — Indicates the number of days to retain ULFs. After the specified number of days has passed, the ULF is automatically purged by the From Host Maintenance process.

FHM-ULF-NOTIFY-INTERVAL — Indicates the number of writes made to the ULF between calculating the percentage of file full.

FHM-ULF-NOTIFY-PERCENTAGE — Indicates the percentage of used file space at which the From Host Maintenance process logs a message indicating that the ULF is becoming full. The From Host Maintenance process continues to event messages at the interval indicated in the FHM-ULF-NOTIFY-INTERVAL param until more file space is made available for the ULF.

FHM-ULF-REJECTS — Controls whether rejected updates are logged to the ULF.

LOGICAL-NET — The name of the logical network in which this From Host Maintenance process is running.

PIT-NAM-ALGO — Identifies whether a name generation algorithm, such as the Soundex algorithm, is used to perform name searches on the Personal Information Table (PIT).

REF-NOTIFY*identifier* — The symbolic name of a process that the Refresh process must notify after new files are generated during a full-file refresh.

Note: The From Host Maintenance process does not use this param. However, a REF-NOTIFY*identifier* param must be established for each main and secondary From Host Maintenance process so the Refresh process notifies it following a full-file refresh.

Required Assigns and Params

The From Host Maintenance process abends at initialization if any of the following assigns or params are missing:

- EMF (Required for ISO external messages.)
- FHM-LN-CUTOVER
- FHM-MASTER

- IDF
- LMCF
- LOGICAL-NET
- ULF

The From Host Maintenance process also abends at initialization if the FHM-LN-CUTOVER param is invalid.

Initialization and Warmboot

The following steps are taken by each From Host Maintenance process when it is first started and when it is warmbooted. Except where noted, each main and secondary From Host Maintenance process performs all of these steps. Each main and secondary process must be initialized or warmbooted individually.

To initialize or warmboot, the From Host Maintenance process performs the following steps:

1. Reads the name of its LCONF. The startup or warmboot message from the XPNET process contains the name of the LCONF. This name allows the From Host Maintenance process to access the LCONF for the assigns and params it needs for processing.
2. Opens the LCONF.
3. Retrieves the assigns and params it requires from the LCONF. These assigns and params have been described earlier in this section.
4. Builds the secondary From Host Maintenance process notify list from the FHM-SLAVE-NOTIFY*identifier* params in the LCONF.

Only the main From Host Maintenance process performs this step. If no secondary From Host Maintenance processes are defined in the system, the main From Host Maintenance process does not build a secondary From Host Maintenance process notify list.

5. Closes the LCONF.
6. Opens the logging facility for writing event messages.
7. Reads the LMCF for its modified event messages. The LMCF contains a record for each modified log message in the system. The From Host Maintenance process opens the LMCF, retrieves its modified event messages, and closes the LMCF. Whenever the From Host Maintenance process generates a log message, it checks the LMCF records in memory to determine whether the message needs to be modified.
8. Opens the IDF.
 - a. Calculates the amount of extended memory needed to build the IDF table.
 - b. Initializes the extended memory.
 - c. Positions the record pointer at the beginning of the IDF using the primary key of FIID.

- d. Reads the file sequentially by the primary key until the end of file is reached. For each IDF record found, the From Host Maintenance process performs the following steps:
 - 1) Creates an entry in the extended memory IDF table. Each entry contains the following information:
 - FIID
 - NEG name
 - NBF name
 - CAF name
 - DDA PBF name
 - SAV PBF name
 - CCD PBF name
 - SPF name
 - WHFF name
 - CCMF name
 - CCIF name
 - 2) Creates a segment map for each financial institution showing the proper segments to create when records are added to segmented application files (CAF, NEG, and PBF). For example, the PBF can contain Base, BASE24-pos, BASE24-telebanking, BASE24-teller, Credit Line, Short Name, BASE24 Customer Service, and Preauthorized Hold segments. The From Host Maintenance process uses the FIID-SEG-MAP in the Institution Definition File (IDF) to determine which segments are used. If BASE24-teller is not used by a particular financial institution, the BASE24-teller, Credit Line, and Short Name segments are not created when a record is added to that financial institution's PBF.
 - 3) Opens the authorization files (NEG, CAF, PBF, SPF, NBF, WHFF, CCMF, and CCIF) and updates the financial institution's table index for those files.
9. Opens the Corporate Check File (CCF), if an assign for the CCF was found. The CCF is only used if the BASE24-atm self-service banking Enhanced Check Application is being used.
10. Opens the Check Status File (CSF), if an assign for the CSF was found. The CSF is only used if the BASE24-atm self-service banking Enhanced Check Application is being used.

11. Builds the bitmap table for ISO-based external messages. Using the EMF name found in the LCONF, the From Host Maintenance process opens the EMF and retrieves the record structure for 0300 and 0310 messages. If the record structures for 0300 and 0310 messages are not in the EMF, the From Host Maintenance process loads the default bitmaps into the table. Refer to the *BASE24 External Message Manual* for default bitmaps.
12. Starts a report timer if the reports are scheduled to be run before the next cutover and any of the following LCONF params are set to Y:
 - FHM-RPT
 - FHM-CSFC-RPT
 - FHM-CUST-RPT
 - FHM-PSNL-RPT

The From Host Maintenance process also creates an obey file containing the commands necessary to run the reports. If all of the params are set to N, the From Host Maintenance process generates an event message indicating that no reports are run.

Only the main From Host Maintenance process performs this step.

13. Determines the processing date by comparing the current time to the cutover time specified in the LCONF. Using this date, the From Host Maintenance process determines whether a ULF for the current date exists. If a ULF for the current date exists, the From Host maintenance process opens the file.

If a ULF for the current date does not exist, the main From Host Maintenance process creates and opens the file. A secondary From Host Maintenance process abends if a ULF for the current date does not exist because only main From Host Maintenance processes can create a ULF.

14. Using the LCONF param FHM-LN-CUTOVER, sets a timer to expire when cutover is to occur.

Only the main From Host Maintenance process performs this step.

Logging Records to the ULF

Logging records to the ULF is controlled by two LCONF params and a message header field. These controls are described in the paragraphs that follow:

Logging Successful Updates

The LCONF param FHM-ULF-AUDIT controls how much information is logged to the ULF. There are three valid settings:

- 0 = Do not log to the ULF
- 1 = Log message header and record image
- 2 = Log message header only

In addition to determining how much information is logged to the ULF, this param affects the information shown in BASE24-from host maintenance reports.

Because the reports use the ULF as a source, they can report only as much information as is logged to the ULF. If the FHM-ULF-AUDIT param is set to 0, there is no information to include in the reports. If the FHM-ULF-AUDIT param is set to 2, only the message header information appears on the reports. If the FHM-ULF-AUDIT param is set to 1, the reports contain both the message header and record or row image information.

The LOG-IND field in the message header determines on a message-by-message basis whether the message is logged to the ULF. In addition, the LOG-IND field can be used to override the FHM-ULF-AUDIT to a certain extent. The LOG-IND field has three valid values:

- Y = Yes, log the message to the ULF.
- N = No, do not log the message to the ULF.
- Any other value = Do not override FHM-ULF-AUDIT.

The following table indicates how the LOG-IND field and FHM-ULF-AUDIT param together determine what is logged to the ULF.

LOG-IND Setting	FHM-ULF-AUDIT Setting	ULF Logging
Y	0 or 1	Message header and record or row image
Y	2	Message header

LOG-IND Setting	FHM-ULF-AUDIT Setting	ULF Logging
N	0, 1, or 2	No information is logged
Any other value	0	No information is logged
Any other value	1	Message header and record or row image
Any other value	2	Message header

Logging Rejected Updates

The LCONF param FHM-ULF-REJECTS controls whether rejected updates are logged to the ULF. In addition, the FHM-ULF-REJECTS param can be used to override the FHM-ULF-AUDIT param to a certain extent. The FHM-ULF-REJECTS param has three valid values:

Y = Yes, log the message to the ULF.
 N = No, do not log the message to the ULF.
 Any other value = Do not override FHM-ULF-AUDIT.

The table below indicates how the FHM-ULF-REJECTS param and FHM-ULF-AUDIT param together determine what information is logged to the ULF for each rejected update.


FHM-ULF-REJECTS	FHM-ULF-AUDIT Setting	ULF Logging
Y	0 or 1	Message header and record or row image
Y	2	Message header
N	0, 1, or 2	No information is logged
Any other value	0	No information is logged
Any other value	1	Message header and record or row image
Any other value	2	Message header

Message Flows

Update transactions from the host to BASE24-from host maintenance generate a series of request and response messages. This subsection describes BASE24-from host maintenance message flows.

Message Routing Without an ISO Host Interface Process

BASE24-from host maintenance can be configured with or without an ISO Host Interface process. The following diagram illustrates message routing when BASE24-from host maintenance is configured without a Host Interface process.



The steps itemized below describe the processing involved in the illustration:

Step Processing


- 1, 2 The update request message, initiated by the host, is routed directly to the From Host Maintenance process through the XPNET process.
- 3 The From Host Maintenance process accesses the appropriate application file or table, updating it if necessary.
- 4 Request information is logged to the ULF, if the logging indicator in the message header is set to a value of Y. If the logging indicator is set to N, no information is logged to the ULF. Logging to the ULF is controlled by the LCONF param FHM-ULF-AUDIT and the LOG-IND message header field.
- 5, 6 If the COMPL-REQ field in the message header is set to a value of Y, a 0310 update response message is routed back to the host through the XPNET process. If the COMPL-REQ field is set to a value of N, no response is sent to the host.

Message Routing With an ISO Host Interface Process

When BASE24-from host maintenance is configured with an ISO Host Interface process, there are several possible message flows. In the normal message flow, update messages are sent to the ISO Host Interface, which sends them on to the From Host Maintenance process. When the communications link to the host is down, responses are sent to the SAF instead of being returned to the host. Once the communications link is restored, the stored responses are sent to the host.

Normal Message Flow

The normal message routing when BASE24-from host maintenance is configured with an ISO Host Interface process is illustrated below. Under this configuration, messages are routed through the Host Interface process, thereby providing store-and-forward capability.




The steps below describe the processing shown in the diagram:

Step Processing

- 1, 2 The update request message is routed to the ISO Host Interface process.
- 3, 4 The update request message is routed from the ISO Host Interface process to the From Host Maintenance process.
- 5 The From Host Maintenance process accesses the appropriate application file or table, updating it if necessary.
- 6 Request information is logged to the ULF if the logging indicator in the message header is set to a value of Y. If the logging indicator is set to a value of N, no information is logged to the ULF. Logging to the ULF is controlled by the LCONF param FHM-ULF-AUDIT and the LOG-IND message header field.
- 7, 8 If the COMPL-REQ field in the message header is set to a value of Y, a 0310 update response message is routed to the ISO Host Interface process. If the COMPL-REQ field is set to a value of N, no response is sent to the Host Interface process.
- 9, 10 The update response message is routed from the ISO Host Interface to the host.

Host Unavailable for Response — Response to SAF

The processing involved with a ISO Host Interface process when the host is unavailable and the response is sent to the Store-and-Forward File (SAF) is illustrated below. Because the SAF is only used to store 0310 messages when the connection to the host is down, this message flow occurs only if the COMPL-REQ field in the message header is set to Y. If the COMPL-REQ field is set to N, no 0310 message is sent to the host.




The steps below describe the processing shown in the diagram:

Step Processing

- 1, 2 The update request message is routed to the ISO Host Interface process.
- 3, 4 The update request message is routed from the ISO Host Interface process to the From Host Maintenance process.
- 5 The From Host Maintenance process accesses the appropriate application file or table, updating it if necessary.
- 6 Request information is logged to the ULF if the logging indicator in the message header is set to Y. If the logging indicator is set to N, no information is logged to the ULF. Logging to the ULF is controlled by the LCONF param FHM-ULF-AUDIT and the LOG-IND message header field.
- 7, 8 A 0310 update response message is routed to the ISO Host Interface process.
- 9, 10 The update response message is routed from the ISO Host Interface process to the host. When the link is down, the XPNET process is unable to deliver the message to the host.
- 11 The ISO Host Interface process writes the message to the SAF.

Host Becomes Available — Process Responses from SAF

The illustration below shows the processing involved with an ISO Host Interface process when the host becomes available and messages are sent from the SAF to the host.



The steps below describe the processing shown in the diagram.

Step Processing

- 1 The host becomes available and the ISO Host Interface process reads the SAF.
- 2, 3 The store-and-forward update response message is sent to the host.
- 4 The XPNET process sends a logical acknowledgment to the ISO Host Interface process indicating that the host has received the store-and-forward message.

Update Processing

The From Host Maintenance process receives five types of messages from the host: add, delete, inquire, change, and increment. These requests are described below.

Add Request

Add requests instruct the From Host Maintenance process to add a record or row to the CACT, CAF, CCF, CCIF, CCMF, CPIT, CSF, CSTT, NBF, NEG, PBF, PIT, SPF, or WHFF. When the From Host Maintenance process receives an add request, it performs the following steps:

1. Checks the key fields in the request message for valid input. If any key field is invalid, a message is logged and the request is rejected.
2. For additions to the NBF or WHFF, checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged and the request is rejected.
3. For additions to the NBF, verifies that the PASSBOOK-IND field in the PBF is set to a value of Y. If the passbook indicator is not set to a value of Y, a message is logged and the request is rejected. For additions to the CSTT, CACT, CPIT, or PIT processing skips to step 5. Processing for all other files continues with step 4.
4. Checks for an existing record with the same key. If a record with the same key exists, a message is logged and the request is rejected.
5. Validates the remaining fields in the message and creates a new record or row using the validated information. If any field contains invalid data, a message is logged and the request is rejected.
6. Updates name token information in the PIT, if necessary. If BASE24 Remote Banking products are in use and an addition is made to the PIT, the From Host Maintenance process checks the PIT-NAM-ALGO param in the LCONF. If the param is set to a value of Y or not present and the family name token is blank in the request, a family name token is generated.
7. Adds the record to the file or adds the row to the table.

8. Updates the associated PBF record, if necessary.

For additions to the SPF, checks the FIID-SEG-MAP in the IDF to determine whether the BASE24-teller product is in use. If the BASE24-teller product is in use, the From Host Maintenance process checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged, but the request is not rejected.

For additions to the SPF when the BASE24-teller product is in use or additions of warning records to the WHFF, updates the SP-STAT field in the PBF record and writes the PBF record. If the PBF record cannot be written, a message is logged, but the request is not rejected.

For additions of deposit float records to the WHFF, updates the AVAIL-BAL field in the PBF record and writes the PBF record. If the PBF record cannot be written, the WHFF record added in step 7 is deleted, a message is logged, and the request is rejected.

For additions of hold records to the WHFF, updates the AVAIL-BAL and AMT-ON-HLD fields in the PBF record and writes the PBF record. If the PBF record cannot be written, the WHFF record added in step 7 is deleted, a message is logged, and the request is rejected.

For additions to the NBF, updates the NBF-REC-CNT field in the PBF record and writes the PBF record. If the NBF-REC-CNT field cannot be updated or the PBF record cannot be written, the NBF record added in step 7 is deleted, a message is logged, and the request is rejected.

For additions to the CSTT, CACT, CPIT, or PIT, checks to see if a row with the same key exists. If a row with the same key exists, a message is logged, and the request is rejected.

9. Logs an image of the record, row, or rejected request to the ULF, if applicable. The value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF control whether a record is logged to the ULF for a successful addition. Settings of the FHM-ULF-AUDIT and FHM-ULF-REJECTS params in the LCONF control whether a rejected request is logged to the ULF.
10. If the COMPL-REQ field in the message header is set to a value of Y, returns a 0310 message to the host indicating the disposition of the add request. If the COMPL-REQ field is set to N, no response is returned to the host.

The From Host Maintenance process performs the same processing for an add request to the CAF Accounts segment as for a change request to the CAF. In addition, the following checks are made for a CAF Accounts segment add request:

- None of the new accounts can already exist.
- The total number of accounts after the new accounts are added cannot exceed 16.
- The total number of accounts with the same account type after the new accounts are added cannot exceed 5.
- All fields for all accounts must contain valid data.
- The card type cannot be ST (super teller) or SP (special purpose).

If any of these checks fail, none of the new accounts are added.

Delete Request

Delete requests instruct the From Host Maintenance process to delete a record or row from the CACT, CAF, CCF, CCIF, CCMF, CPIT, CSF, CSTT, NBF, NEG, PBF, PIT, SPF, or WHFF. When the From Host Maintenance process receives a delete request, it performs the following steps:

1. Checks the key fields in the request message for valid input. If any key field is invalid, a message is logged and the request is rejected.
2. Reads the record or row using the key fields. For deletions from the CCIF, CCMF, CSTT, CACT, CPIT, or PIT, processing skips to step 4. Processing for all other files continues with step 3.
3. Compares the FIID in the message against the FIID in the record. If the FIIDs do not match, a message is logged and the request is rejected.
4. Logs an image of the record, row, or rejected request to the ULF, if applicable. The value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF control whether a record is logged to the ULF for a successful deletion. Settings of the FHM-ULF-AUDIT and FHM-ULF-REJECTS params in the LCONF control whether a rejected request is logged to the ULF.
5. Deletes the record from the file or the row from the table.
6. Updates the associated PBF record, if necessary.

For deletions from the SPF, checks the FIID-SEG-MAP in the IDF to determine whether the BASE24-teller product is in use. If the BASE24-teller product is in use, the BASE24-from host maintenance process checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged, but the request is not rejected.

For deletions from the NBF or WHFF, checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged, but the request is not rejected.

For deletions of any records from the SPF or of warning records from the WHFF, updates the SP-STAT field in the PBF record and writes the PBF record. If the PBF record cannot be written, a message is logged, but the request is not rejected.

For deletions of deposit float records from the WHFF, updates the AVAIL-BAL field in the PBF record and writes the PBF record. If the PBF record cannot be written, a message is logged, but the request is not rejected.

For deletions of hold records from the WHFF, updates the AVAIL-BAL and AMT-ON-HLD fields in the PBF record and writes the PBF record. If the PBF record cannot be written, a message is logged, but the request is not rejected.

For deletions from the NBF, verifies that the PASSBOOK-IND field in the PBF is set to Y. If the passbook indicator is not set to Y, a message is logged, but the request is not rejected.

For deletions from the NBF, updates the NBF-REC-CNT field in the PBF record. If the no-book record count cannot be updated or the updated PBF record cannot be written, a message is logged, but the request is not rejected.

7. If the COMPL-REQ field in the message header is set to Y, returns a 0310 message to the host indicating the disposition of the delete request. If the COMPL-REQ field is set to N, no response is sent to the host.

Inquiry Request

Inquiry requests instruct the From Host Maintenance process to get a record or row from the CACT, CAF, CCF, CCIF, CCMF, CPIT, CSF, CSTT, NBF, NEG, PBF, PIT, SPF, or WHFF. Successful inquiries are not logged to the ULF. Unsuccessful inquiries can be logged to the ULF, depending on the settings of the FHM-ULF-AUDIT and FHM-ULF-REJECTS params in the LCONF.

When the From Host Maintenance process receives an inquiry request, it performs the following steps:

1. Checks the key fields in the request message for valid input. If any key field is invalid, a message is logged and the request is rejected.
2. Reads the record or row using the key fields. For inquiries to the CCIF, CCMF, CSTT, CACT, CPIT, or PIT, processing skips to step 4. Processing for all other files continues with step 3.
3. Compares the FIID in the message against the FIID in the record. If the FIIDs do not match, a message is logged and the request is rejected.
4. Reads the associated PBF record, if necessary.

For inquiries to the SPF, checks the FIID-SEG-MAP in the IDF to determine whether the BASE24-teller product is in use. If the BASE24-teller product is in use, the From Host Maintenance process checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged, but the request is not rejected.

For inquiries to the NBF or WHFF, checks for an existing PBF record for this FIID, account number, and account type. If no PBF record is found, a message is logged, but the request is not rejected.

For inquiries to the NBF, verifies that the PASSBOOK-IND field in the PBF is set to Y. If the passbook indicator is not set to Y, a message is logged, but the request is not rejected.

5. If the COMPL-REQ field in the message header is set to Y, returns a 0310 message to the host with the information from the requested record or row. If the COMPL-REQ field is set to N, no response is returned to the host.

Change Request

Change requests instruct the From Host Maintenance process to change a record or row in the CACT, CAF, CCF, CCIF, CCMF, CPIT, CSF, CSTT, NEG, PBF, or PIT. Change requests can be initiated in two ways. For the first method, an inquiry request for the record to be changed must be sent. The operator changes the fields to be updated in the inquiry response, and sends the message back to the From Host Maintenance process as a change request. For the second method, the operator sends a change request without performing an inquiry first. When the second method is used, the operator must fill the timestamp fields with zeros. If the timestamp fields are filled with zeros, the From Host Maintenance process does not check to ensure that the record has not been updated since the last inquiry.

This could cause any information that changed since the last inquiry to be overwritten (that is, lost). When the From Host Maintenance process receives a change request, it performs the following steps:

1. Checks the key fields in the request message for valid input. If any key field is invalid, a message is logged and the request is rejected.
2. Reads the record or row using the key fields. For changes to the CCIF, CCMF, CSTT, CACT, CPIT, or PIT processing skips to step 4. Processing for all other files continues with step 3.
3. Compares the FIID in the message against the FIID in the record. If the FIIDs do not match, a message is logged and the request is rejected.
4. If the timestamps are not zero-filled, compares the last files maintenance and last transaction timestamps in the change request message with the timestamps in the record or row to ensure that the record or row has not been updated since the inquiry was performed. If the timestamps do not match, a message is logged and the request is rejected.
5. Logs a before image of the record or row or an image of the rejected request to the ULF, if applicable. The value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF control whether a record is logged to the ULF for a successful request. Settings of the FHM-ULF-AUDIT and FHM-ULF-REJECTS params in the LCONF control whether a rejected request is logged to the ULF.
6. Updates name token information in the PIT, if necessary. If BASE24 Remote Banking products are in use and an addition is made to the PIT, the From Host Maintenance process checks the PIT-NAM-ALGO param in the LCONF. If the param is set to Y or not present and the family name token is blank in the request, a family name token is generated.
7. Updates the record or row with the information from the change request.
8. Logs an after image of the record or row to the ULF, based on the value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF.
9. If the COMPL-REQ field in the message header is set to Y, returns a 0310 message to the host indicating the disposition of the change request. If the COMPL-REQ field is set to N, no response is returned to the host.

For CAF changes, the From Host Maintenance process changes all CAF Account segment fields (including the ACCT.TYP and ACCT.NUM fields) as long as the FIID and CAF record key (PAN and MBR-NUM) fields in the request message match the existing CAF record.

For CAF Account segment changes, the From Host Maintenance process uses the FIID and CAF record key fields to locate the existing CAF record, then compares the ACCT.TYP and ACCT.NUM fields in the request message to the existing CAF record before changing any values in the remaining CAF Account segment fields. If these values do not match existing CAF Account segment entries, a message is logged and the request is rejected.

Increment Request

Increment requests instruct the From Host Maintenance process to increase (or decrease) an amount or limit field in the CAF, CCF, CSF, CSTT, or PBF. When the From Host Maintenance process receives an increment request, it performs the following steps:

1. Checks the key fields in the request message for valid input. If any key field is invalid, a message is logged and the request is rejected.
2. Reads the record or row using the key fields. For increments to the CSTT, processing skips to step 4.
3. Compares the FIID in the message against the FIID in the record. If the FIIDs do not match, a message is logged and the request is rejected.
4. Logs a before image of the record or row or an image of the rejected request to the ULF, if applicable. The value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF control whether a record is logged to the ULF for a successful request. Settings of the FHM-ULF-AUDIT and FHM-ULF-REJECTS params in the LCONF control whether a rejected request is logged to the ULF.
5. Adds the values in the message amount and limit fields to the amount and limit fields in the record or row. Message fields with positive values increase the value of the fields in the record or columns in the row. Message fields with negative values are subtracted from the fields in the record or columns in the row.
6. Logs an after image of the record or row to the ULF, based on the value in the LOG-IND field in the message header and the setting of the FHM-ULF-AUDIT param in the LCONF.
7. If the COMPL-REQ field in the message header is set to Y, returns a 0310 message to the host indicating the disposition of the increment request. If the COMPL-REQ field is set to N, no response is returned to the host.

Update Response Messages

The 0310 message contains the key fields identifying the record or row acted upon and the response code indicating the outcome of the update message. The 0310 message is also used to return inquiry responses to the host. It is the only message sent to the host indicating the success or failure of an update message. If desired, the 0310 message can be suppressed by setting the COMPL-REQ field in the message header to N.

The value in the USER-DATA-LGTH field in the message header identifies the length of data contained in the USER-DATA field in the 0310 message. For messages other than inquiries, the value in the USER-DATA-LGTH field controls how much information in the USER-DATA field is used. If the From Host Maintenance process receives a 0300 message with 50 characters in the USER-DATA field and a value of 30 in the USER-DATA-LGTH field, the first 30 characters are used in the 0300 message and echoed in the 0310 message.

For inquiries, however, the From Host Maintenance process determines how much information is in the USER-DATA field of the 0310 message and sets the value in the USER-DATA-LGTH field accordingly. If the From Host Maintenance process receives a 0300 message with a value of 30 in the USER-DATA-LGTH field and 50 characters are returned in the 0310 message, the From Host Maintenance process changes the value in the USER-DATA-LGTH field from 30 to 50.

ACI Worldwide, Inc.

3: BASE24-from host maintenance Reporting

The BASE24-from host maintenance reports provide detailed information about the updates attempted and performed through BASE24-from host maintenance. This section describes the report programs and the reports produced by BASE24-from host maintenance.

Report Programs

There are 15 pairs of reports provided by BASE24-from host maintenance. These reports are divided into four groups, with a separate report program for each group, as follows:


Report Group	Files and Tables
Base*	CAF, CCF, CSF, NBF, NEG, PBF, SPF, WHFF
Customer ID	CSTT, CACT
Customer Service	CCIF, CCMF
Personal ID	CPIT, PIT

* The Base report group includes base, BASE24-atm self-service banking, and BASE24-teller reports.

BASE24-from host maintenance report programs are not defined as processes in the XPNET system, nor do they run continuously. The report programs are started each day by the main From Host Maintenance process, and once started, simply produce their reports and stop.

The report programs are responsible for reporting all information written to the Update Log File (ULF). Depending on settings in the LCONF and message header, the ULF contains accepted and rejected application file and table changes, increments, additions, deletions, and inquiries. The report programs report all information that was logged to the ULF, including information sent from the host, as well as who made the change, and the response to the message.

The illustration on the following page provides an overview of how each report program works.



File Usage

Descriptions of the files the report programs use during processing are provided below. Each description includes how the file is used, when the file is used and what the report program does with the information it reads from the file.

Institution Definition File (IDF) — At initialization, each report program reads the IDF sequentially from beginning to end. Using the information from the file, it builds a table containing the names of the financial institutions and their FIIDs. This information is used in the report headings.

Update Log File (ULF) — Each report program reads the ULF to retrieve the records of successful and rejected updates to the application files and tables.

Report Types

The BASE24-from host maintenance report programs produce 15 pairs of reports. Each pair of reports can be divided into two types: an activity report and a reject report. The activity report shows all of the successful updates made to a file or table. The reject report contains the information supplied in the original request, as well as the response code that identifies the reason for rejection.

Starting the Report Program

The main From Host Maintenance process is responsible for starting the BASE24-from host maintenance reports. It does so by creating an obey file to start the report program and then running the obey file at the appropriate time. Secondary From Host Maintenance processes cannot start the reports.

Two assigns in the LCONF control whether any report programs run, and each report group has one assign and one param in the LCONF controlling whether the report program for that group runs. If the FHM-RPT-OBEY-FILE assign or FHM-RPT-CMD-FILE assign is missing, no report programs run.

The following table shows the assign and param required for each report group. The assign identifies the name of the report program and the param contains a value of Y or N to identify whether the report program should run.

Group	Assign	Param
Base	FHM-RPT-PROG-NAME	FHM-RPT
Customer ID	FHM-CUST-RPT-PROG-NAME	FHM-CUST-RPT
Customer Service	FHM-CSFC-RPT-PROG-NAME	FHM-CSFC-RPT
Personal ID	FHM-PSNL-RPT-PROG-NAME	FHM-PSNL-RPT

At the time specified in the LCONF param FHM-LN-CUTOVER, the main From Host Maintenance process creates an obey file containing the commands necessary to run the report programs from the Tandem command interpreter. Using the LCONF param FHM-RPT-STARTUP, the main From Host Maintenance process sets a timer to expire when the reports are to be run. When the timer expires, the main From Host Maintenance process runs the obey file created at cutover.

The CPU in which the report programs are to run and the priority at which they are to run can be specified using the FHM-RPT-CPU and FHM-RPT-PRI params in the LCONF. Both of these params are passed to the report programs in the obey file that starts them. If these params are not included in the LCONF, the main From Host Maintenance process places its own CPU and priority assignments in the obey file. If using the priority assignment of the main From Host Maintenance process causes an error, an attempt is made to run the report programs at an execution priority of 100.

Under normal circumstances, the report programs start and stop without operator intervention. However, if the main From Host Maintenance process does not start the programs, they can be started manually from a TACL prompt by running the report obey file created by the main From Host Maintenance process.

If a report program abends or fails, it can be restarted in the same way.

For more information about LCONF params, refer to the *BASE24 Logical Network Configuration Manual*.

Output Locations

The report programs create the BASE24-from host maintenance reports and send them to a Tandem spooler location. The spooler locations are different for each report, as shown in the following table:

Spooler Location	Report Name
\$\$.#CAFRPT	Cardholder Authorization File (CAF) Report
\$\$.#CAFREJ	Cardholder Authorization File (CAF) Reject Report
\$\$.#CAFIRPT	Cardholder Authorization File (CAF) Accounts Report
\$\$.#CAFIREJ	Cardholder Authorization File (CAF) Accounts Reject Report
\$\$.#CSFRPT	Check Status File (CSF) Report
\$\$.#CSFREJ	Check Status File (CSF) Reject Report
\$\$.#CCFRPT	Corporate Check File (CCF) Report
\$\$.#CCFREJ	Corporate Check File (CCF) Reject Report
\$\$.#CSTTRPT	Customer Table (CSTT) Report
\$\$.#CSTTREJ	Customer Table (CSTT) Reject Report
\$\$.#CACTRPT	Customer/Account Relation Table (CACT) Report
\$\$.#CACTREJ	Customer/Account Relation Table (CACT) Reject Report
\$\$.#CCIFRPT	Customer/Cardholder Information File (CCIF) Report
\$\$.#CCIFREJ	Customer/Cardholder Information File (CCIF) Reject Report
\$\$.#CCMFRPT	Customer/Cardholder Memo File (CCMF) Report
\$\$.#CCMFREJ	Customer/Cardholder Memo File (CCMF) Reject Report
\$\$.#CPITRPT	Customer/Personal ID Relation Table (CPIT) Report
\$\$.#CPITREJ	Customer/Personal ID Relation Table (CPIT) Reject Report

Spooler Location	Report Name
\$\$.#NEGRPT	Negative Card File (NEG) Report
\$\$.#NEGREJ	Negative Card File (NEG) Reject Report
\$\$.#NBF RPT	No Book File (NBF) Report
\$\$.#NBFREJ	No Book File (NBF) Reject Report
\$\$.#PITRPT	Personal Information Table (PIT) Report
\$\$.#PITREJ	Personal Information Table (PIT) Reject Report
\$\$.#PBF RPT	Positive Balance File (PBF) Report
\$\$.#PBFREJ	Positive Balance File (PBF) Reject Report
\$\$.#SPFRPT	Stop Payment File (SPF) Report
\$\$.#SPFREJ	Stop Payment File (SPF) Reject Report
\$\$.#WHFRPT	Warning/Hold/Float File (WHFF) Report
\$\$.#WHFREJ	Warning/Hold/Float File (WHFF) Reject Report

Report Errors

The report programs send all error messages to the spooler location \$\$.#BASEERR.

Data Masking

BASE24-from host maintenance provides the option of masking sensitive data in accordance with Payment Card Industry (PCI) standards for account data protection. PCI standards define sensitive data as the primary account number, cardholder name, service code, and expiration date. Sensitive data masking is optional, based on settings in the Institution Definition File (IDF).

The primary account number is the only sensitive data field currently displayed on BASE24-fhm reports that is partially masked. Any other sensitive data fields are masked completely if the primary account number is masked.

According to PCI standards, the first 6 digits and last 4 digits are the maximum number of primary account number digits that can be displayed. The user can define the actual masking format. This definition includes the maximum number of left-most characters to display as unmasked, the specific number of right-most characters to display as unmasked, and the minimum number of digits to display as masked.

The PCI requirement for masking sensitive data does not apply to employees and other parties who have a specific need to display the full primary account number. When sensitive data is masked on BASE24-fhm reports, any personnel who needs to display it must have the proper security in their HP-NonStop logon to run the reports manually.

Activity Reports

An activity report shows all of the successful updates made to a file or table. For change or increment updates, the report shows the before-image as the first item of the report, taking however many lines may be required to report the information, and the after-image as the second item. This allows for easy comparisons between the two images. The addition and deletion transactions only require one item per transaction.

The fields included in each report correspond to the fields required in the update request message. Only specific fields from the standard ULF header are reported. However, all of the header information logged to the ULF is available by extracting the ULF.

There is one activity report for each file and table that can be updated. In addition, an activity report is produced that shows all updates to the Accounts segment of the CAF. The formats of the nine activity reports produced by BASE24-from host maintenance are illustrated and described on the following pages.

Note: The amount fields in these illustrations contain two decimal places for currencies such as U.S. dollars; however, other currencies are also supported.

Cardholder Authorization File Activity Report

The Cardholder Authorization File (CAF) Activity Report contains information about all the changes, additions, deletions, and increments made to the CAF.

The masking of cardholder primary account numbers (PANs) and administrative PANs on this report depends on the values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Refer to the following manuals for files maintenance screens and field descriptions:

CAF Screen	Manual
1–10	<i>BASE24 Base Files Maintenance Manual</i>
12	<i>BASE24-pos Address Verification Manual</i>
13	<i>BASE24-atm EMV Support Manual</i> <i>BASE24-pos EMV Support Manual</i>
14–16	Device-specific BASE24-atm self service banking (SSB) manuals
20	<i>BASE24-from host maintenance Reference Manual</i>

CARDHOLDER AUTHORIZATION FILE (CAF)														BNKA - BANK A				MM/DD/YY	PAGE	2
BASE24-FROM HOST MAINTENANCE ACTIVITY REPORT																				
-----NON-CURRENCY DISPENSE CAF EXTENSION-----																				
HOPR1			---TTL LMT CASH---			---OFFL LMT CASH---			-TTL LMT CCA CASH-			OFFL LMT CCA CASH			USE LMT					
HOPR2			---TTL LMT NCD1---			---OFFL LMT NCD1---			-TTL LMT CCA NCD1-			OFFL LMT CCA NCD1								
			---TTL LMT NCD2---			---OFFL LMT NCD2---			-TTL LMT CCA NCD2-			OFFL LMT CCA NCD2			0					
xx			0			0			0			0			0					
xx			0			0			0			0			0					
-----EMV CAF EXTENSION-----																				
SEND			SEND			SEND			SCPT			SCPT								
ATC			CRD			PUT			LWR			CNSC			PIN					
LIMIT			BLCK			DATA			OFFL			LMT			UBLK					
211			Y			Y			99			0			0					
			Y			Y			0			0			0					
			Y			Y			0			0			0					
-----PREFERRED TRANSACTION-----																				
ACCT			TRAN			FM			ACCT			TO			ACCT					
NUM			CODE			TYPE			TYPE			RCPT			AMOUNT					
123456			10			01			00			Y			100					
			CHANGES			0			INCREMENTS			0			DELETES					
ADDS			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL			0			TOTAL					
			1			CHANGES			0			INCREMENTS			0					
			TOTAL			0			TOTAL											

ACCOUNT NUMBER — The card number or primary account number (PAN) identifying the card. This value corresponds to the PAN field on CAF screen 1. Values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4 control masking of the value in this field.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
CHANGE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INCR = Increase or decrease amounts or counters in an existing record (9)
INVALID = The ULF record contains an invalid update type code

MEM NUM — The member number for the card. This value corresponds to the MEMBER field on CAF screen 1.

CARD TYPE — A code identifying the type of card associated with the PAN. This value corresponds to the CARD TYPE field on CAF screen 1.

CARD STAT — A code identifying the status of the card. This value corresponds to the CARD STATUS field on CAF screen 1.

WITHDRAWAL LIMITS

The following six fields contain the withdrawal limits for accounts associated with this card.

ON/A — The maximum aggregate amount, in whole currency units, of cash disbursements allowed against credit and noncredit accounts, plus purchases allowed against noncredit accounts. This value corresponds to the TOTAL AGGR field on CAF screen 1.

OFF/A — The maximum aggregate amount, in whole currency units, of cash disbursements allowed offline against credit and noncredit accounts, plus purchases allowed against noncredit accounts. This value corresponds to the OFFLINE AGGR field on CAF screen 1.

ON/C — The maximum amount, in whole currency units, of cash advances allowed against credit accounts. This value corresponds to the TOTAL CASH ADV field on the CAF screen 1.

OFF/C — The maximum amount, in whole currency units, of cash advances allowed offline against credit accounts. This value corresponds to the OFFLINE CASH ADV field on CAF screen 1.

ON — The maximum amount, in whole currency units, of purchases and cash withdrawals allowed against noncredit accounts. This value corresponds to the TOTAL CASH WDL field on CAF screen 1.

OFF — The maximum amount, in whole currency units, of purchases and cash withdrawals allowed offline against noncredit accounts. This value corresponds to the OFFLINE CASH WDL field on CAF screen 1.

EXPIR DATE — The expiration date (MM/YY) of the card. A transaction attempted after the month indicated is declined. This value corresponds to the EXPIRATION DATE field on CAF screen 2.

This field will be completely masked if the PAN is configured for masking.

AC CNT — The number of accounts contained in the Accounts segment of the CAF. This value corresponds to the NUMBER OF ACCOUNTS field on CAF screens 3 and 4.

RESP CODE — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

CRD2 STAT — A code identifying the status of the second card. This value corresponds to the CARD STATUS field on CAF screen 7.

CRD2 EXPIR — The expiration date (MM/YY) of the second card. A transaction attempted with the second card after the month indicated is declined. This value corresponds to the EXPIRATION DATE field on CAF screen 7.

This field will be completely masked if the PAN is configured for masking.

EXP POWER — The exponent used with total and offline limit amounts carried in the BASE24-from host maintenance external message. This exponent does not affect any other values shown on this report.

PIN CHECK — A value used in the PIN verification process. The value in this field is based on the type of PIN verification method used. This value corresponds to the POFST/PVV field on CAF screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This field corresponds to the ALTKEY.UPDT-TIM field in the ULF.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

ACCOUNT INFORMATION

The following fields can appear as many as 16 times, depending on the number of accounts in the Accounts segment of the CAF.

TY — A code identifying the type of account. This value corresponds to the TYPE field on CAF screens 3 and 4.

ACCOUNT NUMBER — The application account number. This value corresponds to the ACCOUNT NUMBER field on CAF screens 3 and 4.

S — A code identifying the current status of the application account. This value corresponds to the STATUS field on CAF screens 3 and 4.

DESC — The account issuer's routing and transit number or a free-text area for a description of the account, depending on the value in the ACH field. This value corresponds to the ACH RTTN/DESCRIPTION field on CAF screens 3 and 4.

ACH — A flag indicating whether the account is an Automated Clearing House (ACH) debit account. This value corresponds to the ACH-IND field on CAF screens 3 and 4.

ATM CAF EXTENSION

The following fields identify limits established for BASE24-atm transactions. These limits are contained in the BASE24-atm segment of the CAF.

ON/LIM — The maximum amount, in whole currency units, of cash withdrawals allowed against noncredit accounts using BASE24-atm. This value corresponds to the TOTAL CASH WDL field on CAF screen 8.

OFF/LIM — The maximum amount, in whole currency units, of cash withdrawals allowed offline against noncredit accounts using BASE24-atm. This value corresponds to the OFFLINE CASH WDL field on CAF screen 8.

ON/CLIM — The maximum amount, in whole currency units, of cash advances allowed against credit accounts using BASE24-atm. This value corresponds to the TOTAL CASH ADV field on CAF screen 8.

OFF/CLIM — The maximum amount, in whole currency units, of cash advances allowed offline against credit accounts using BASE24-atm. This value corresponds to the OFFLINE CASH ADV field on CAF screen 8.

DEP CR LIM — The maximum amount, in whole currency units, of deposit credit a cardholder is allowed for a single usage accumulation period. This value corresponds to the MAXIMUM DEPOSIT CREDIT AMT field on CAF screen 8.

USE TODAY — The maximum number of times the card can be used to withdraw cash using BASE24-atm in a single usage accumulation period. This value corresponds to the TIMES USED PER PERIOD LIMIT field on CAF screen 8.

POS CAF EXTENSION

The following fields identify limits established for BASE24-pos transactions. These limits are contained in the BASE24-pos segment of the CAF.

ON/PLIM — The maximum amount, in whole currency units, of purchases allowed against credit accounts using BASE24-pos. This value corresponds to the TOTAL PURCHASE field on CAF screen 10.

OFF/PLIM — The maximum amount, in whole currency units, of purchases allowed offline against credit accounts using BASE24-pos. This value corresponds to the OFFLINE PURCHASE field on CAF screen 10.

ON/CLIM — The maximum amount, in whole currency units, of cash advances allowed against credit accounts using BASE24-pos. This value corresponds to the TOTAL CASH ADV field on CAF screen 10.

OFF/CLIM — The maximum amount, in whole currency units, of cash advances allowed offline against credit accounts using BASE24-pos. This value corresponds to the OFFLINE CASH ADV field on CAF screen 10.

ON/WLIM — The maximum amount, in whole currency units, of purchases and cash withdrawals allowed against noncredit accounts using BASE24-pos. This value corresponds to the TOTAL CASH WDL field on CAF screen 10.

OFF/WLIM — The maximum amount, in whole currency units, of purchases and cash withdrawals allowed offline against noncredit accounts using BASE24-pos. This value corresponds to the OFFLINE CASH WDL field on CAF screen 10.

ON/RLIM — The maximum amount, in whole currency units, of refunds allowed against credit and noncredit accounts using BASE24-pos. This value corresponds to the TOTAL REFUND field on CAF screen 10.

OFF/RLIM — The maximum amount, in whole currency units, of refunds allowed offline against credit and noncredit accounts using BASE24-pos. This value corresponds to the OFFLINE REFUND field on CAF screen 10.

USED TODAY — The maximum number of times the card can be used using BASE24-pos in a single usage accumulation period. This value corresponds to the TIMES USED PER PERIOD LIMIT field on CAF screen 10.

CAF ADDRESS

The following fields contain customer address information contained in the Address Verification segment of the CAF.

ADDRESS — The street portion of the customer mailing address. This information is used when the BASE24-pos add-on Address Verification module has been installed. This value corresponds to the ADDRESS field on CAF screen 12.

ZIP CDE — The ZIP Code portion of the customer mailing address. This information is used when the BASE24-pos add-on Address Verification module has been installed. Corresponds to the ZIP CODE field on CAF screen 12.

SUPER TELLER TERMINALS

This field, which can appear as many as 10 times, identifies the terminals associated with a Super Teller card. This field only appears when an institution is using the BASE24-atm self-service banking Base Application. The teller IDs associated with a Super Teller card cannot be updated individually. All teller IDs associated with a Super Teller card must be updated at the same time. This value corresponds to the SUPER TELLER TERMINAL ID field on CAF screen 14.

SELF SERVICE BANKING CHECK

The following fields associate the holder of a check cashing card with a specific corporation and identify activity limits used when checks are cashed with a check cashing card. These fields are only displayed when an institution is using the BASE24-atm self-service banking Enhanced Check Application.

CORP NUM — The corporation number already assigned in the Corporate Check File (CCF) to identify a business that issues check cashing cards to its employees. These cards enable employees to cash checks at the financial institution even though they do not have an account with the financial institution. This value corresponds to the CORPORATION NUMBER field on CAF screen 15.

CSF CHK USE LMT — The maximum number of times a card can be used for check-related transactions that have a matching Check Status File (CSF) record. This value corresponds to the CSF CHECKS ALLOWED PER PERIOD field on CAF screen 16.

TOTAL CHK LMT — The maximum amount, in whole currency units, of cash disbursements allowed for check-related transactions allowed by BASE24-atm self-service banking Enhanced Check Application when a matching Check Status File (CSF) record cannot be located. This value corresponds to the TOTAL CHECK field on CAF screen 15.

OFFLINE CHK LMT — The maximum amount, in whole currency units, of cash disbursements allowed for check-related transactions allowed by stand-in authorization with the BASE24-atm self-service banking Enhanced Check Application when a matching Check Status File (CSF) record cannot be located. This value corresponds to the OFFLINE CHECK field on CAF screen 15.

TOTAL CSF CHK LMT — The maximum amount, in whole currency units, of cash disbursements allowed for check-related transactions allowed by the BASE24-atm self-service banking Enhanced Check Application when a matching Check Status File (CSF) record is located. This value corresponds to the TOTAL CSF CHECK field on CAF screen 16.

OFFLINE CSF CHK LMT — The maximum amount, in whole currency units, of cash disbursements allowed for check-related transactions allowed by stand-in authorization with the BASE24-atm self-service banking Enhanced Check Application when a matching Check Status File (CSF) record is located. This value corresponds to the OFFLINE CSF CHECK field on CAF screen 16.

CARD CAF EXTENSION

The following fields contain card management data for the BASE24-card product. They describe information about the cardholder and the cards issued to this cardholder.

BRANCH NUM — The branch identification of the institution issuing the plastic. This field can be embossed on the card. This value corresponds to the BRANCH NUM field on CAF screen 20.

DEPT NUM — The department identification of the department issuing the plastic. This field can be embossed on the card. This value corresponds to the DEPARTMENT NUMBER field on CAF screen 20.

PIN MAILER — A flag indicating whether the Plastic Card Generation Server (SVPCGEN) should create a PIN mailer for this cardholder. This value corresponds to the PIN MAILER REQUIRED field on CAF screen 20.

CARD CARRIER — A flag indicating whether the Plastic Card Generation Server (SVPCGEN) should create a plastic or card carrier for this cardholder. This value corresponds to the PLASTIC/CARD CARRIER OPTIONS field on CAF screen 20.

ISS STAT — The issue status for this cardholder record This field is used to determine whether a plastic card is to be produced for this cardholder account. This value corresponds to the ISSUE STATUS field on CAF screen 20.

CARDS TO ISSUE — This field contains the number of cards to be embossed for this cardholder account during the next plastic card generation run. This value corresponds to the CARDS TO ISSUE field on CAF screen 20.

CARDS RETURNED — The total number of plastic cards returned to the institution for this cardholder account. This value corresponds to the CARDS RETURNED field on CAF screen 20.

SERVICE CODE — The ISO standard service code used to generate the card verification digits (CVD). This value corresponds to the SERVICE CODE field on CAF screen 20.

NAME LINE 1 — The name of the primary cardholder for this account. This field is required for processing. This value corresponds to the NAME LINE1 field on CAF screen 20.

ADDR LINE 1 — The first line of the cardholder's address. This field is required for card processing if PIN mailers or card carriers are to be created. This value corresponds to the ADDR LINE1 field on CAF screen 20.

NAME LINE 2 — The name of the secondary cardholder for this account. This field is not required for card processing. This value corresponds to the NAME LINE2 field on CAF screen 20.

ADDR LINE 2 — The second line of the cardholder's address. This value corresponds to the ADDR LINE2 field on CAF screen 20.

TITLE — The title of the cardholder. This value corresponds to the TITLE field on CAF screen 20.

CITY — The city of residence for the cardholder. This field is required for card processing if PIN mailers or card carriers are to be created. This value corresponds to the CITY field on CAF screen 20.

STATE — The state of residence for the cardholder. This field is required for card processing if PIN mailers or card carriers are to be created. This value corresponds to the STATE field on CAF screen 20.

ZIP — The postal code or ZIP code of residence for the cardholder. This field is required for card processing if PIN mailers or card carriers are to be created. This value corresponds to the ZIP CODE field on CAF screen 20.

COMMENTS — This field can be used by the institution for information about the cardholder account record. This value corresponds to the COMMENTS field on CAF screen 20.

COUNTRY CODE — The country of residence of the cardholder. This value corresponds to the COUNTRY field on CAF screen 20.

PRE-AUTH CAF EXTENSION

The following fields, which can occur as many as 10 times, identify preauthorized holds that have been placed on the cardholder accounts associated with the CAF record. These fields are contained in the Preauthorized Holds segment of the CAF. Fields in the Preauthorized Holds segment cannot be updated individually. All fields in the Preauthorized Holds segment of a CAF record must be updated at the same time.

SEQ NUM — The sequence number assigned to the hold by the issuer. This value corresponds to the TRAN NUM field on CAF screen 5.

HOLD AMOUNT — The transaction amount, in whole currency units, associated with the hold. This value corresponds to the AMOUNT field on CAF screen 5.

ACCOUNT NUMBER — The application account number associated with the hold. This value corresponds to the ACCOUNT NUMBER field on CAF screen 5.

ACCT TYPE — The type of account that has funds on hold. This value corresponds to the ACCT TYP field on CAF screen 5.

EXPIRE DATE — The date and time the hold amount is cleared and no longer taken into consideration during BASE24 Authorization processing. This value corresponds to the HOLD STATUS field on CAF screen 5.

ENHANCED PRE-AUTH CAF EXTENSION

The following fields, which can occur as many as 10 times, identify enhanced preauthorized holds that have been placed on the cardholder accounts associated with the CAF record. These fields are contained in the Enhanced Preauthorized Holds segment of the CAF.

SEQ NUM — The sequence number of the preauthorized hold transaction. This value is used to associate a preauthorized purchase completion transaction with the proper preauthorized purchase transaction.

HOLD AMOUNT — The transaction amount, in whole and fractional currency units, associated with this preauthorized hold.

TERM-ID — The ID of the terminal that issued the preauthorized hold.

APPROVAL CODE — The approval code value used to associate a preauthorized purchase completion transaction with the proper preauthorized purchase transaction.

EXPIRE DATE — The date and time the hold amount is cleared and no longer taken into consideration during BASE24 Authorization processing.

ACCT TYPE — A code identifying the type of account that has funds on hold. This value corresponds to the TYPE field on CAF screens 4 and 5.

HOLD FLAG — Indicates if the hold is active and is used during BASE24 Authorization processing, or if the hold has timed out.

NON-CURRENCY DISPENSE CAF EXTENSION

The following fields describe Non-Currency Dispense transactions contained in the Non-Currency Dispense segment of the CAF.

TTL LMT CASH — The maximum amount of cash value transactions allowed against noncredit accounts. This value corresponds to the TOTAL CASH WDL field on CAF screen 9.

OFFL LMT CASH — The maximum amount of cash value transactions allowed offline against noncredit accounts. This value corresponds to the OFFLINE CASH WDL field on CAF screen 9.

TTL LMT CCA CASH — The maximum amount of cash value transactions allowed against credit accounts. This value corresponds to the TOTAL CREDIT WDL field on CAF screen 9.

OFFL LMT CCA CASH — The maximum amount of cash value transactions allowed offline against credit accounts. This value corresponds to the OFFLINE CREDIT WDL field on CAF screen 9.

USE LMT — The maximum number of times the card can be used for cash value transactions in a single usage accumulation period. This value corresponds to the TIMES USED PER PERIOD LIMIT on CAF screen 9.

HOPR1 — Identifies the hopper contents to which the following limit fields pertain. This value corresponds to the CTNT CDE 1 field on CAF screen 9.

TTL LMT NCD1 — The maximum amount of transactions allowed against noncredit accounts for the item type identified by the HOPR1 field. This value corresponds to the TOTAL CASH WDL field for the first content code on CAF screen 9.

OFFL LMT NCD1 — The maximum amount of transactions allowed offline against noncredit accounts for the item type identified by the HOPR1 field. This value corresponds to the OFFLINE CASH WDL field for the first content code on CAF screen 9.

TTL LMT CCA NCD1 — The maximum amount of transactions allowed against credit accounts for the item type identified by the HOPR1 field. This value corresponds to the TOTAL CREDIT WDL field for the first content code on CAF screen 9.

OFFL LMT CCA NCD1 — The maximum amount of transactions allowed offline against credit accounts for the item type identified by the HOPR1 field. This value corresponds to the OFFLINE CREDIT WDL field for the first content code on CAF screen 9.

HOPR2 — Identifies the hopper contents to which the following limit fields pertain. This value corresponds to the CTNT CDE 2 field on CAF screen 9.

TTL LMT NCD2 — The maximum amount of transactions allowed against noncredit accounts for the item type identified by the HOPR2 field. This value corresponds to the TOTAL CASH WDL field for the second content code on CAF screen 9.

OFFL LMT NCD2 — The maximum amount of transactions allowed offline against noncredit accounts for the item type identified by the HOPR2 field. This value corresponds to the OFFLINE CASH WDL field for the second content code on CAF screen 9.

TTL LMT CCA NCD2 — The maximum amount of transactions allowed against credit accounts for the item type identified by the HOPR2 field. This value corresponds to the TOTAL CREDIT WDL field for the second content code on CAF screen 9.

OFFL LMT CCA NCD2 — The maximum amount of transactions allowed offline against credit accounts for the item type identified by the HOPR2 field. This value corresponds to the OFFLINE CREDIT WDL field for the second content code on CAF screen 9.

EMV CAF EXTENSION

The following fields describe EMV transactions contained in the EMV segment of the CAF.

ATC LIMIT — Specifies the acceptable number of transactions that can be performed on the card before issuer authorization is required. The range of valid values is 0–9999. A value of zero disables the limit check. This value corresponds to the ATC LIMIT field on CAF screen 13.

SEND CRD BLCK — Determines whether a CARD BLOCK script command should be sent to the terminal to disable the microchip. This value corresponds to the SEND CARD BLOCK field on CAF screen 13.

SEND PUT DATA — Determines whether a PUT DATA script command should be sent to the terminal to update the microchip data (e.g., new limits data). This value corresponds to the SEND PUT DATA field on CAF screen 13.

LWR CONSEC OFFL LMT — Specifies the maximum number of consecutive transactions that can be performed on the card before an attempt must be made to obtain authorization from the issuer. This field is used by the BASE24-atm or BASE24-pos applications to generate the variable component of the PUT DATA script command, so that a card can have a new limit downloaded. The range of valid values is 0–255. This value corresponds to the LWR CONSEC LIMIT (LCOL) field on CAF screen 13.

SEND PIN UBLK — Specifies the circumstance under which a PIN change script command will be generated and returned by the BASE24-atm application. This value corresponds to the SEND PIN UNBLOCK field on CAF screen 13.

SEND PIN CHNG — Specifies whether synchronization of the online and offline PIN is required for the card. This value corresponds to the SEND PIN CHANGE field on CAF screen 13.

SCPT TPLT TAG — Specifies the template tag that will be used for the card. This value corresponds to the SCRIPT TEMPLATE TAG field on CAF screen 13.

SCPT MAC LGTH — Specifies the length of the Script MAC that will be used for the card. This value corresponds to the SCRIPT MAC LENGTH field on CAF screen 13.

PIN SYNC — Specifies whether synchronization of the online and offline PIN is required for the card. This value corresponds to the ONLINE/OFFLINE PIN SYNC field on CAF screen 13.

IAD FRMT — Specifies the format of the EMV Issuer Application Data (IAD) that will be used for the card. This value corresponds to the EMV IAD FORMAT field on CAF screen 13.

STAT CHK ACT INDX — Specifies which of the preset rules for status field processing are to be used for the card. This value corresponds to the STATUS CHECKING ACTION INDEX field on CAF screen 13.

BAD CAP TKN OVRD — Controls whether additional CAP Token validation attempts can be performed if the number of consecutive failed CAP Token validation errors specified in the BAD CAP TOKEN VALIDATION LIMIT field on Card Prefix File (CPF) screen 13 has been reached. This value corresponds to the BAD CAP TOKEN OVERRIDE FLAG field on CAF screen 13.

PRIMARY CARD DATA CAP APSN — Specifies the CAP application PAN sequence number (APSN) for the card identified by the values in the PAN and MEMBER fields on each CAF screen. The APSN identifies and differentiates cards with the same PAN. In EMV transactions, this field is generally sent to the BASE24 application as part of the transaction data. However, for CAP transactions, it may not be present, which means the value has to be configured in the database.

PRIMARY CARD DATA CAP DKI — Specifies the derivation key index (DKI) for the card identified by the values in the PAN and MEMBER fields on each CAF screen. The DKI identifies which set of master keys is to be used in the derivation of the authorization cryptogram for the card. In EMV transactions, this field is generally sent to the BASE24 application as part of the transaction data. However, for CAP transactions, it may not be present, which means the value has to be configured on the database.

SECONDARY CARD DATA CAP APSN — Specifies the CAP application PAN sequence number (APSN) for the secondary card identified by the values in the PAN and MEMBER fields on each CAF screen. The APSN identifies and differentiates cards with the same PAN. In EMV transactions, this field is generally sent to the BASE24 application as part of the transaction data. However, for CAP transactions, it may not be present, which means the value has to be configured in the database.

SECONDARY CARD DATA CAP DKI — Specifies the derivation key index (DKI) used for the secondary card identified by the values in the PAN and MEMBER fields on each CAF screen. The DKI identifies which set of master keys is to be used in the derivation of the authorization cryptogram for the card. In EMV transactions, this field is generally sent to the BASE24 application as part of the transaction data. However, for CAP transactions, it may not be present, which means the value has to be configured in the database.

PREFERRED TRANSACTION

The following fields provide cardholder limits and display a cardholder's activity during the usage accumulation period for the BASE24-atm product.

ACCT NUM — The account number associated with the cardholder's preferred transaction. This value corresponds to the ACCOUNT NUMBER field on CAF screen 21.

TRAN CODE — The transaction code for the cardholder's preferred transaction. This value corresponds to the TRAN CODE field on CAF screen 21.

FM ACCT TYPE — A code identifying the type of account from which the preferred transaction is originating. This value corresponds to the FROM ACCT TYPE field on CAF screen 21.

TO ACCT TYPE — A code identifying the type of destination account for the preferred transaction. This value corresponds to the TO ACCT TYPE field on CAF screen 21.

RCPT OPT — The receipt option for the cardholder's preferred transaction. This value corresponds to the RCPT OPTION field on CAF screen 21.

AMOUNT — The amount of the preferred transaction. This value corresponds to the AMOUNT field on CAF screen 21.

PRFL UPDT IND — A code indicating whether the preferred transaction profile can be updated by the cardholder at the terminal. This value corresponds to the PROFILE UPDATE IND field on CAF screen 21.

ADA IND — A code indicating whether the cardholder wishes to have American Disabilities Act (ADA) support at the terminal, if available. This value corresponds to the ADA IND field on CAF screen 21.

MARKET SEG IND — The market segment indicator for this cardholder. This value corresponds to the MARKET SEG IND field on CAF screen 21.

TOTALS

The number of CAF update records, by update type, included on the report. Update types include addition, change, increment, and deletion. The total number of CAF update records is also provided.

Cardholder Authorization File Accounts Segment Activity Report

The Cardholder Authorization File (CAF) Accounts Segment Activity Report contains information about all the changes and additions made to the Accounts segment of the CAF.

The masking of cardholder primary account numbers (PANs) and administrative PANs on this report depends on the values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the ***BASE24 Base Files Maintenance Manual*** for information on CAF screens and their field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT									
CARDHOLDER AUTHORIZATION FILE (CAF)	ACCOUNT INFORMATION	BNKA	- BANK A	MM/DD/YY	PAGE	1			
----- ACCOUNT NUMBER -----	MEM NUM	CARD TYPE	STAT	AC CNT	UPD DATE	UPD TIME	-----OPERATOR-----	RESP CODE	
-----ACCOUNT INFORMATION-----									
-----ACCOUNT INFORMATION-----									
ACH	TY	-----	ACCOUNT NUMBER	-----	S	---DESC---	ACH	TY	-----
							ACCOUNT NUMBER		S ---DESC---
XXXXXXXXXXXXXXXXXXXXXXXXXXXX	INQUIRY	111	C0	1	01	MM/DD/YY	HH:MM:SS		Q3
01	11111111111111111111111111111111	1	1111111111	A					
-----TOTALS-----									
ADDS	1	CHANGES	0	TOTAL	1				

ACCOUNT NUMBER — The card number or primary account number (PAN) identifying the card. This value corresponds to the PAN field on CAF screen 1. Values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4 controls the masking of the value in this field.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
UPDATE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INCR = Increase or decrease amounts or counters in an existing record (9)
INVALID = The ULF record contains an invalid update type code

MEM NUM — The member number for the card. This value corresponds to the MEMBER field on CAF screen 1.

CARD TYPE — A code identifying the type of card associated with the PAN. This value corresponds to the CARD TYPE field on CAF screen 1.

STAT — A code identifying the status of the card. This value corresponds to the CARD STATUS field on CAF screen 1.

AC CNT — The number of accounts contained in the Accounts segment of the CAF. This value corresponds to the NUMBER OF ACCOUNTS field on CAF screens 3 and 4.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

RESP CODE — A code identifying the result of the update request. Corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

ACCOUNT INFORMATION

The following fields can appear as many as 16 times, depending on the number of accounts in the Accounts segment of the CAF.

TY — A code identifying the type of account. This value corresponds to the TYPE field on CAF screens 3 and 4.

ACCOUNT NUMBER — The application account number. This value corresponds to the ACCOUNT NUMBER field on CAF screens 3 and 4.

S — A code identifying the current status of the application account. This value corresponds to the STATUS field on CAF screens 3 and 4.

DESC — The account issuer's routing and transit number or a free-text area for a description of the account, depending on the value in the ACH field. This value corresponds to the ACH RTTN/DESCRIPTION field on CAF screens 3 and 4.

ACH — A flag indicating whether the account is an Automated Clearing House (ACH) debit account. This value corresponds to the ACH-IND field on CAF screens 3 and 4.

TOTALS

The number of CAF Accounts segment update records, by update type, included on the report. Update types include addition and change. The total number of CAF Accounts segment update records is also provided.

Check Status File Activity Report

The Check Status File (CSF) Activity Report contains information about all the changes, additions, deletions, and increments made to the CSF.

The masking of cardholder primary account numbers (PANs) and administrative PANs on this report depends on the values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the device-specific BASE24-atm self-service banking (SSB) manuals for information on CSF screens and field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT												
CHECK STATUS FILE (CSF)			MEM			CHK		RET		UPD DATE		PAGE
INST ID NUM	ACCOUNT NUMBER	REGSTR PAN NUM	NUM	TYPE	STAT	STAT	STAT	STAT	STAT	MM/DD/YY	MM/DD/YY	1

1111111111	11111111111111111111	XXXXXXXXXXXXXXXXXXXX	111	ADD	0	0	0	0	0	MM/DD/YY	HH:MM:SS	Q3

-----TOTALS-----												
ADDS	1	CHANGES	0	INCREMENTS	0	DELETES	0	TOTAL	1			

INST ID NUM — The transit/routing number of the check-issuing institution or check-issuer identification number. This value corresponds to the INSTITUTION ID NUMBER field on CSF screen 1.

ACCOUNT NUMBER — The checking account number from the check MICR data. This value corresponds to the ACCOUNT NUMBER field on CSF screen 1.

REGSTR PAN NUM — The cardholder primary account number (PAN) from the Track 2 data in the BASE24-atm Standard Internal Message (STM). This value corresponds to the REGISTERED PAN NUMBER field on CSF screen 1. Values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4 control masking of the value in this field.

MEM NUM — The cardholder member number from the Track 2 data in the BASE24-atm Standard Internal Message (STM). This value corresponds to the REGISTERED MEMBER NUMBER field on CSF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD	= Add a new record (1)
CHANGE	= Update an existing record (2)
DELETE	= Delete an existing record (3)
INQUIRY	= Obtain information from an existing record (5)
INCR	= Increase or decrease amounts or counters in an existing record (9)
INVALID	= The ULF record contains an invalid update type code

CHK STAT — A code that specifies the disposition of a check with this institution and account. This value corresponds to the CHECK STATUS field on CSF screen 1.

RET STAT — A code that specifies the retention of a check with this institution and account. This value corresponds to the CHECK RETAIN FLAG field on CSF screen 1.

CHECK LIMIT — The maximum acceptable amount, in whole currency units, of a check with this institution and account. This value corresponds to the CHECK LIMIT field on CSF screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

RESP CODE — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

TOTALS

The number of CSF update records, by update type, included on the report. Update types include addition, change, increment, and deletion. The total number of CSF update records is also provided.

Corporate Check File Activity Report

The Corporate Check File (CCF) Activity Report contains information about all the changes, additions, deletions, and increments made to the CCF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the device-specific BASE24-atm self-service banking (SSB) manuals for information on CCF screens and field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT											
CORPORATE CHECK FILE (CCF)	CORP NUM	CORPORATION DESCRIPTION	TYPE	UPD DATE	UPD TIME	INST ID NUM	ACCOUNT NUMBER	STAT	MM/DD/YY	CHECK LIMIT	PAGE 1 RESP
	111111111	CORPORATION A	ADD	MM/DD/YY	HH:MM:SS	111111111	111111111111111111	0			Q3
						222222222	2222222222222222	0			0
						333333333	3333333333333333	0			0
						444444444	4444444444444444	0			0
						555555555	5555555555555555	0			0
-----TOTALS-----											
ADDS	1	CHANGES	0	INCREMENTS	0	DELETES	0	TOTAL			1

CORP NUM — The corporation identification number as specified in the CAF or NEG. This value corresponds to the CORPORATION NUMBER field on CCF screen 1.

CORPORATION DESCRIPTION — A description of the corporation. This value corresponds to the DESCRIPTION field on CCF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
CHANGE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INCR = Increase or decrease amounts or counters in an existing record (9)
INVALID = The ULF record contains an invalid update type code

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

INST ID NUM — The valid routing/transit numbers for checks issued by the corporation. There can be 1 through 16 routing/transit numbers for each corporation. This value corresponds to the INST ID NUM field on CCF screen 1.

ACCOUNT NUMBER — The valid account numbers for checks issued by the corporation. There can be 1 through 16 account numbers for each corporation. This value corresponds to the ACCOUNT NUMBER field on CCF screen 1.

STAT — A code identifying the processing to be performed on checks issued by the corporation. There can be 1 through 16 account status codes for each corporation. This value corresponds to the STATUS field on CCF screen 1.

CHECK LIMIT — The maximum amount, in whole currency units, that can be approved for checks issued by the corporation. There can be 1 through 16 check limits for each corporation. This value corresponds to the MAXIMUM AMOUNT field on CCF screen 1.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

TOTALS

The number of CCF update records, by update type, included on the report. Update types include addition, change, increment, and deletion. The total number of CCF update records is also provided.

Customer Table Activity Report

The Customer Table (CSTT) Activity Report contains information about all the changes, additions, deletions, and increments made to the CSTT.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a table maintenance screen. Refer to the ***BASE24 Core Files and Tables Maintenance Manual*** for information on the CSTT and field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT									
CUSTOMER TABLE (CSTT)					MM/DD/YY		PAGE		
-----CUSTOMER ID-----							1		
11111111111111111111111111111111	ADD	BRNA	BRNA	11111111	C	YYYYMMDD	SMITH		
-----PIN INFORMATION-----							111-22-3333		
-----PVD-----							-----BILLPAY BILLING INFORMATION-----		
0A0A0A0A0A0A0A	Y	YYYY-MM-DD:HH:MM:SS	1	Y	BP	BILL GRP	BP	BILL TYP	LAST BP BILL TYP
-----ACCOUNT INFORMATION-----							AA		
-----DFLT ACCT NUM-----							V		
11111111111111111111111111111111	00	DFLT ACCT TYP	SVC	FEE ACCT NUM	SVC	FEE ACCT TYP	VERFY	FLG	LAST VRFY FLG
-----PACKET INFORMATION-----							V		
-----PCKT STAT LAST PCKT STAT UPD-----							MAX HISTORY RECS		
0	Y	YYYY-MM-DD:HH:MM:SS	MARY JONES	(402)390-7600			1		
-----BEG DAT-----							UPD DATE		
1	Y	YYYY-MM-DD	YYYY-MM-DD	END DAT			MM/DD/YY		
-----TOTALS-----							1		
ADDS	1	CHANGES	0	INCREMENTS	0	DELETES	TOTAL		
							1		

CUSTOMER ID — The unique identification number assigned to a customer. The customer ID number can also be known as the primary account number (PAN). This value corresponds to the CUSTOMER ID field on CSTT screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new row (1)
CHANGE = Update an existing row (2)
DELETE = Delete an existing row (3)
INQUIRY = Obtain information from an existing row (5)
INCR = Increase or decrease amounts or counters in an existing row (9)
INVALID = The ULF record contains an invalid update type code

FIID — The FIID of the financial institution associated with the customer. This value corresponds to the FIID field on CSTT screen 1.

BRCH ID — The number for the main branch of the financial institution where the customer is serviced. This value corresponds to the BRANCH-ID field on CSTT screen 1.

PROFILE — An identifier used to group primary customer IDs together for transaction processing. This value corresponds to the PROFILE field on CSTT screen 1.

TYPE — A code identifying the type of customer associated with the customer ID. This value corresponds to the TYPE field on CSTT screen 1.

CUSTOMER INFORMATION — User-defined customer account information. This value contains three subfields of 20 characters each. In this example, the report uses a birth date, a government ID number (Social Security number), and a mother's maiden name. This value corresponds to the CUST INFO field on CSTT screen 1.

PIN INFORMATION

The following fields identify PIN information maintained in the CSTT.

PVD — The PIN offset value, PIN verification number (PVN), or PIN verification value (PVV) used in PIN verification processing. This value corresponds to the PIN VERIFICATION DIGITS field on CSTT screen 1.

LAST PVD UPD — The date and time (YYYY-MM-DD:hh:mm:ss) the PVD field was last updated. This value corresponds to the LAST UPDATE field located next to the PIN VERIFICATION DIGITS field on CSTT screen 1.

PVK-IDX — The location of the PIN verification value. This field is used with the Visa PVV PIN verification method. This value corresponds to the PIN VERIFICATION KEY INDEX on CSTT screen 1.

PIN CHNG REQ — A flag indicating whether a customer needs to initiate a PIN change transaction. This value corresponds to the PIN CHANGE REQUIRED field on CSTT screen 1.

BILLPAY BILLING INFORMATION

The following fields contain bill payment information.

BP BILL GRP — A four-character billing group assigned to the customer ID. This value corresponds to the BILLPAY BILLING GROUP field on CSTT screen 1.

BP BILL TYP — The user-defined billing type assigned to this customer ID for BASE24-billpay billing purposes. This value corresponds to the BILLPAY BILLING TYPE field on CSTT screen 1.

LAST BP BILL TYP UPD — The date and time (YYYY-MM-DD:hh:mm:ss) that the BP BILL TYP field was updated. This value corresponds to the LAST UPDATE field located next to the BILLPAY BILLING TYPE field on CSTT screen 1.

ACCOUNT INFORMATION

The following fields contain account information.

DFLT ACCT NUM — The number of the account for which balance information is returned to the customer with PIN verification transactions. This value corresponds to the DEFAULT ACCT NUM field on CSTT screen 1.

DFLT ACCT TYP — The default account type for which balance information is returned to the customer with PIN verification transaction. This value corresponds to the DEFAULT ACCT TYPE field on CSTT screen 1. Valid values are defined in the Account Type Table File (ATT).

SVC FEE ACCT NUM — The account number charged by the customer's financial institution using a payment transaction (online billing) for the billpay service. This value corresponds to the SERVICE FEE ACCT NUM field on CSTT screen 1.

SVC FEE ACCT TYP — The account type associated with the service fee account number for this customer ID. This value corresponds to the SERVICE FEE ACCT TYPE field on CSTT screen 1.

VERIFICATION STATUS

The following fields contain verification status information.

VRFY FLG — A code identifying the status of the customer relationship. This value corresponds to the VERIFY STATUS field on CSTT screen 1.

LAST VRFY FLG UPD — The date and time (YYYY-MM-DD:hh:mm:ss) the VRFY FLG field was updated for this customer. This value corresponds to the LAST UPDATE field located next to the VERIFY STATUS field on CSTT screen 1.

PACKET INFORMATION

The following two fields contains packet information.

PCKT STAT — A user-defined code indicating whether an informational packet explaining the billpay service has been sent to this customer ID. This value corresponds to the PACKET STATUS field on CSTT screen 1.

LAST PCKT STAT UPD — The date and time (YYYY-MM-DD:hh:mm:ss) that the PCKT STAT field was last updated. This value corresponds to the LAST UPDATE field located next to the PACKET STATUS field on CSTT screen 1.

ALT CONTACT — The name and telephone number of the alternate contact associated with this customer ID. This value corresponds to the ALTERNATE CONTACT field on CSTT screen 1.

MAX HISTORY RECS — The maximum number of Transaction History File (THF) records or BASE24-billpay History Table (HIST) rows that can be returned in a last *count* transaction history inquiry or a last *count* payments inquiry transaction to a remote banking device for this customer. This value corresponds to the MAX HISTORY RECORDS field on CSTT screen 1.

BP TXN LMT — The maximum amount, in whole currency units, that can be requested in an individual BASE24-billpay transfer or payment transaction for this customer. This value corresponds to the BILLPAY TRANSACTION LIMIT field on CSTT screen 1.

VER — The version of the row written to the CSTT. This value corresponds to the VER column in the CSTT row and does not appear on the CSTT screen.

BEG DAT — The date (YYYY-MM-DD) on which this customer ID becomes available for use in transaction processing. This value corresponds to the BEGIN DATE field on CSTT screen 1.

END DAT — The date (YYYY-MM-DD) on which this customer ID no longer is available for use in transaction processing. This value corresponds to the END DATE field on CSTT screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the HDR.ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the HDR.ALTKEY.UPDT-TIM field in the ULF.

TOTALS

The number of CSTT update records, by update type, included on the report. Update types include addition, change, increment, and deletion. The total number of CSTT update records is also provided.

Customer/Account Relation Table Activity Report

The Customer/Account Relation Table (CACT) Activity Report contains information about all the changes, additions, and deletions made to the CACT.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a table maintenance screen. CACT information is accessed using Customer Table (CSTT) screen 2. Refer to the ***BASE24 Core Files and Tables Maintenance Manual*** for more information about the CSTT screen and its field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT													
CUSTOMER/ACCOUNT RELATION TABLE (CACT)													
VER	CUSTOMER ID FIID	---BEG DAT---	-TYPE- ----	END DAT----	ACCOUNT ID TB DEBIT ALWD	BP	DEBIT ALWD	ACCOUNT TYPE CREDIT ALWD	ACCOUNT QUAL INQ ALWD	STATUS UPD DATE	DESCRIPTION UPD TIME	MM/DD/YY	PAGE
7777777777	1000	BNKA	ADD	888888 YYYYMMDD	Y	N	10	N	0101	A	THIS MESSAGE	MM/DD/YY HH:MM:SS	1
9999999999	1000	BNKA	ADD	1111111111 YYYYMMDD	Y	N	10	N	Y	A	THIS MESSAGE	MM/DD/YY HH:MM:SS	
44444	1000	BNKA	ADD	2222222222 YYYYMMDD	Y	N	20	N	1	A	THIS MESSAGE	MM/DD/YY HH:MM:SS	
6666666666	1000	BNKA	ADD	55555555 YYYYMMDD	Y	N	30	N	22	A	THIS MESSAGE	MM/DD/YY HH:MM:SS	
1111111111	1000	BNKA	CHANGE	3333333333 YYYYMMDD	Y	N		N	Y	A	NEW MESSAGE	MM/DD/YY HH:MM:SS	
5555555555	1000	BNKA	ADD	6666666666 YYYYMMDD	Y	N	20	N	4444	A	THIS MESSAGE	MM/DD/YY HH:MM:SS	
TOTALS													
ADDS	5	CHANGES	1	DELETES	0				6				

CUSTOMER ID — The unique identification number assigned to this BASE24 Remote Banking customer. An unlimited number of accounts can be associated with one customer ID number. This value corresponds to the CUSTOMER ID field on CSTT screen 2.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new row (1)
CHANGE = Update an existing row (2)
DELETE = Delete an existing row (3)
INQUIRY = Obtain information from an existing row (5)
INVALID = The ULF record contains an invalid update type code

ACCOUNT ID — The unique identification number assigned to this account. This value corresponds to the ACCOUNT NUMBER field on CSTT screen 2.

ACCOUNT TYPE — A code indicating the type of account. Valid values are defined in the Account Type Table File (ATT). This value corresponds to the TYPE field on CSTT screen 2.

ACCOUNT QUAL — A code that can be used in place of the account number and account type to identify this account. This value corresponds to the QUALIFIER field on CSTT screen 2.

STATUS — A code indicating the current status of the account and the action to be taken by the BASE24 Integrated Authorization Server process if this account status is encountered. This value corresponds to the STATUS field on CSTT screen 2.

DESCRIPTION — A text description for the account. This value corresponds to the DESCRIPTION field on CSTT screen 2.

VER — The version of the row written to the CACT. This value corresponds to the VER column in the CACT row and does not appear on the CSTT screen.

FIID — The FIID of the customer's financial institution for the account. This value corresponds to the FIID field on CSTT screen 2.

BEG DAT — The date (YYYY-MM-DD) on which the account becomes available for use in transaction processing. This value corresponds to the BEG DATE field on CSTT screen 2.

END DAT — The date (YYYY-MM-DD) on which the account no longer is available for use in transaction processing. This value corresponds to the END DATE field on CSTT screen 2.

TB DEBIT ALWD — A code indicating whether the customer can perform BASE24-telebanking debit transactions on the account. BASE24-telebanking debit transactions include transfers and payments from this account. This value corresponds to the TBDB field on CSTT screen 2.

BP DEBIT ALWD — A code indicating whether the customer can perform BASE24-billpay debit transactions on the account. BASE24-billpay debit transactions include payments from this account. This value corresponds to the BPDB field on CSTT screen 2.

CREDIT ALWD — A code indicating whether the customer can perform credit transactions on the account. Credit transactions include transfers to this account. This value corresponds to the CR field on CSTT screen 2.

INQ ALWD — A code indicating whether the customer can perform balance inquiry or history inquiry transactions on the account. This value corresponds to the INQ field on CSTT screen 2.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the HDR.ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the HDR.ALTKEY.UPDT-TIM field in the ULF.

TOTALS

The number of CACT update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of CACT update records is also provided.

Customer/Cardholder Information File Activity Report

The Customer/Cardholder Information File (CCIF) Activity Report contains information about all the changes, additions, deletions, and inquiries made to the CCIF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT					MM/YY/DD	PAGE
CUSTOMER/CARD INFORMATION FILE (CCIF)					BNKA - BANK A	1
ACCOUNT NUMBER	TYPE	MBR NUM	UPD DATE	UPD TIME	OPERATOR	
11111111111	ADD	000	MM/DD/YY	HH:MM:SS		
PRIMARY CARDHOLDER INFORMATION (SEGMENT ID 0000) -----						
VER: 1000	NAME: JOE CUSTOMER		GOVT ID: 111-22-3333		MAIDEN NAME: SMITH	BIRTHDATE: MM/DD/YY
ADDR1: 1234 MAIN ST.	CITY: ANYTOWN		STATE: NE		COUNTRY: USA	POSTAL CODE: 12345
HOME PHONE: (402) 555-1234	WORK PHONE: (402) 555-4567		ALT1 PHONE: (402) 555-5678		ALT1 DESCR: CELLULAR	
ADDITIONAL PRIMARY CARDHOLDER INFORMATION (SEGMENT ID 0001) -----						
VER: 1000	ADDR3:		ALT2 PHONE: (402) 555-9876		ALT2 DESCR: PAGER	
SECONDARY CARDHOLDER NAME INFORMATION (SEGMENT ID 0002) -----						
VER: 1000	NAME: MARY CUSTOMER		GOVT ID: 111-23-4567		MAIDEN NAME: JONES	
SECONDARY CARDHOLDER ADDRESS INFORMATION (SEGMENT ID 0003) -----						
VER: 1000	ADDR1: DORMITORY ROOM		ADDR2: COLLEGE NAME		CITY: COLLEGE TOWN	
STATE: NE		COUNTRY: USA		POSTAL CODE: 12222		
SECONDARY CARDHOLDER TELEPHONE INFORMATION (SEGMENT ID 0004) -----						
VER: 1000	HOME PHONE: (402) 555-1234		WORK PHONE: (402) 555-4567		ALT1 PHONE: (402) 555-1234	
ALT2 PHONE:		ALT2 DESCR: 2ND WORK				
GENERAL CARD INFORMATION (SEGMENT ID 0005) -----						
VER: 1000	SCORE: 100		RECENT REISSUE: Y		CVV: 111	NUM ISS: 02
DISCRETIONARY DATA (SEGMENT ID 0006) -----						
VER: 1000	<discretionary data>					
-----TOTALS-----						
ADDS	1	CHANGES	0	DELETES	0	TOTAL 1

ACCOUNT NUMBER — The card number or primary account number (PAN). This value corresponds to the CARD field on CCIF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
CHANGE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INVALID = The ULF record contains an invalid update type code

MBR NUM — The member number of the card. This value corresponds to the MEMBER NUM field on CCIF screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

PRIMARY CARDHOLDER INFORMATION (SEGMENT ID 0000)

The following fields identify primary cardholder name, address, and telephone information.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

NAME — The name of the primary cardholder. This value corresponds to the NAME field on CCIF screen 1.

GOVT ID — The government ID or taxpayer ID for the primary cardholder. This value corresponds to the GOV'T ID field on CCIF screen 1.

MAIDEN NAME — The maiden name of the primary cardholder's mother. This value corresponds to the MOTHER'S MAIDEN NAME field on CCIF screen 1.

BIRTHDATE — The date of birth (MM/DD/YY) of the primary cardholder. This value corresponds to the BIRTH DATE field on CCIF screen 1.

ADDR1 — The first line of the primary cardholder's street address. This value corresponds to the first line of the STREET ADDRESS field on CCIF screen 1.

ADDR2 — The second line of the primary cardholder's street address. This value corresponds to the second line of the STREET ADDRESS field on CCIF screen 1.

CITY — The primary cardholder's city of residence. This value corresponds to the CITY field on CCIF screen 1.

STATE — The two-letter abbreviation for the cardholder's state of residence. This value corresponds to the ST field on CCIF screen 1.

COUNTRY — The abbreviation for the cardholder's country of residence. This value corresponds to the COUNTRY field on CCIF screen 1.

POSTAL CODE — The postal code for the primary cardholder's residence. This value corresponds to the POSTAL CODE field on CCIF screen 1.

HOME PHONE — The primary cardholder's home telephone number. This value corresponds to the HOME PHONE field on CCIF screen 1.

WORK PHONE — The primary cardholder's work telephone number. This value corresponds to the WORK PHONE field on CCIF screen 1.

ALT1 PHONE — A third telephone number for the primary cardholder. This value corresponds to the OTHER PHONE #1 field on CCIF screen 1.

ALT1 DESCR — A description of the primary cardholder's third telephone number, such as a fax, cellular telephone, neighbor's telephone, or second work telephone number. This value corresponds to the OTHER PHN #1 DESCRIPTION field on CCIF screen 1.

ADDITIONAL PRIMARY CARDHOLDER INFORMATION (SEGMENT ID 0001)

The following fields provide additional information about the primary cardholder. This segment is present only when there is additional primary cardholder information associated with the card.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

ADDR3 — The third line of the cardholder's street address. This value corresponds to the third line of the STREET ADDRESS field on CCIF screen 1.

ALT2 PHONE — A fourth telephone number for the primary cardholder. This value corresponds to the OTHER PHONE #2 field on CCIF screen 1.

ALT2 DESCR — A description of the primary cardholder's fourth telephone number, such as a fax, cellular telephone, neighbor's telephone, or second work telephone number. This value corresponds to the OTHER PHN #2 DESCRIPTION field on CCIF screen 1.

SECONDARY CARDHOLDER NAME INFORMATION (SEGMENT ID 0002)

The following fields provides name information for a secondary cardholder. This segment is present only when there is a secondary cardholder associated with the card.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

NAME — The name of the secondary cardholder. This value corresponds to the NAME field on CCIF screen 2.

GOVT ID — The government ID or taxpayer ID for the secondary cardholder. This value corresponds to the GOV'T ID field on CCIF screen 2.

MAIDEN NAME — The maiden name of the secondary cardholder's mother. This value corresponds to the MOTHER'S MAIDEN NAME field on CCIF screen 2.

BIRTHDATE — The date of birth (MM/DD/YY) of the secondary cardholder. This value corresponds to the BIRTH DATE field on CCIF screen 2.

SECONDARY CARDHOLDER ADDRESS INFORMATION (SEGMENT ID 0003)

The following fields provide address information for a secondary cardholder. This segment is present only when the address for the secondary cardholder is different from that of the primary cardholder.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

ADDR1 — The first line of the secondary cardholder's street address. In this example, the secondary cardholder's address is a dormitory room number. This value corresponds to the first line of the STREET ADDRESS field on CCIF screen 2.

ADDR2 — The second line of the secondary cardholder's street address. In this example, the second line of the secondary cardholder's address is a college name. This value corresponds to the second line of the STREET ADDRESS field on CCIF screen 2.

CITY — The secondary cardholder's city of residence. This value corresponds to the CITY field on CCIF screen 2.

STATE — The two-letter abbreviation for the secondary cardholder's state of residence. This value corresponds to the ST field on CCIF screen 2.

COUNTRY — The abbreviation for the secondary cardholder's country of residence. This value corresponds to the COUNTRY field on CCIF screen 2.

POSTAL CODE — The postal code for the secondary cardholder's residence. This value corresponds to the POSTAL CODE field on CCIF screen 2.

SECONDARY CARDHOLDER TELEPHONE INFORMATION (SEGMENT ID 0004)

The following fields provide telephone information for a secondary cardholder. This segment is present only when the telephone information for the secondary cardholder is different from that of the primary cardholder.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

HOME PHONE — The secondary cardholder's home telephone number. This value corresponds to the HOME PHONE field on CCIF screen 2.

WORK PHONE — The secondary cardholder's work telephone number. This value corresponds to the WORK PHONE field on CCIF screen 2.

ALT1 PHONE — A third telephone number for the secondary cardholder. This value corresponds to the OTHER PHONE #1 field on CCIF screen 2.

ALT1 DESCR — A description of the secondary cardholder's third telephone number, such as a fax, cellular telephone, neighbor's telephone, or second work telephone number. This value corresponds to the OTHER PHN #1 DESCRIPTION field on CCIF screen 2.

ALT2 PHONE — A fourth telephone number for the secondary cardholder. This value corresponds to the OTHER PHONE #2 field on CCIF screen 2.

ALT2 DESCR — A description of the secondary cardholder's fourth telephone number, such as a fax, cellular telephone, neighbor's telephone, or second work telephone number. This value corresponds to the OTHER PHN #2 DESCRIPTION field on CCIF screen 2.

GENERAL CARD INFORMATION (SEGMENT ID 0005)

The following fields contain general information about the card. This segment is present only when general card information has been defined.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

SCORE — The behavioral score assigned to the card. Values for this field are user-defined. This value corresponds to the BEHAVIORAL SCORE field on CCIF screen 3.

RECENT REISSUE — A code indicating whether the card was recently reissued. This value corresponds to the RECENTLY REISSUED field on CCIF screen 3.

CVV — The card verification value. This value corresponds to the CARD VERIFICATION VALUE field on CCIF screen 3.

NUM ISS — The number of cards issued. This value corresponds to the NUMBER OF CARDS ISSUED field on CCIF screen 3.

DISCRETIONARY DATA (SEGMENT ID 0006)

The following fields contain discretionary data for the card. This segment is present only when discretionary data has been defined.

VER — The version number of the segment. This number is always 1000. This value corresponds to the VER field in the CCIF record and does not appear on the CCIF screen.

<discretionary data> — Discretionary data as defined in the DISCRETIONARY DATA field on CCIF screen 3. This data does not have a field label.

TOTALS

The number of CCIF update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of CCIF update records is also provided.

Customer/Cardholder Memo File Activity Report

The Customer/Cardholder Memo File (CCMF) Activity Report contains information about all the changes, additions, and deletions made to the CCMF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report.

BASE24-FROM HOST MAINTENANCE ACTIVITY REPORT									
CUSTOMER/CARD MEMO FILE (CCMF)				BNKA - BANK A				MM/DD/YY	PAGE
				MEM	DATE	DATE	L/S		
ACCOUNT NUMBER	TYPE	NUM	LOST	REPORTED	IND	VER	UPD DATE	UPD TIME	OPERATOR
11111111111	ADD	000	MM/DD/YY	MM/DD/YY	0	1000	MM/DD/YY		
MEMO: This card was lost or stolen									
memo line 2									
memo line 3									
-----TOTALS-----									
ADDS	1	CHANGES	0	DELETES	0	TOTAL	1		

ACCOUNT NUMBER — The card number. This value corresponds to the CARD field on Customer Information screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
CHANGE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INVALID = The ULF record contains an invalid update type code

MEM NUM — The member number of the card. This value corresponds to the MEMBER NUM field on Customer Information screen 1.

DATE LOST — The date the (MM/DD/YY) the card was actually lost or stolen. This value corresponds to the DATE LOST field on Customer Information screen 3.

DATE REPORTED — The date (MM/DD/YY) the card was reported lost or stolen. This value corresponds to the DATE REPORTED LOST field on Customer Information screen 3.

L/S IND — A user-defined indicator that identifies the circumstances by which this card was lost or stolen. This value corresponds to the HOW LOST/STOLEN field on Customer Information screen 3.

VER — The version of the record written to the CCMF. This value corresponds to the VER field in the CCMF record and does not appear on the Customer Information screens.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

MEMO — Free-format information about the card. This value corresponds to the ADDITIONAL DATA field on Customer Information screen 3.

TOTALS

The number of CCMF update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of CCMF update records is also provided.

Customer/Personal ID Relation Table Activity Report

The Customer/Personal ID Relation Table (CPIT) Activity Report contains information about all the changes, additions, and deletions made to the CPIT.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. The CPIT is accessed using Customer Table (CSTT) screen 3 and Personal Information Table screen 2. Refer to the ***BASE24 Core Files and Tables Maintenance Manual*** for information on these screens and their field descriptions.

BASE24 -FROM HOST MAINTENANCE ACTIVITY REPORT									
CUSTOMER/PERSONAL ID RELATION TABLE (CPIT)					MM/DD/YY		PAGE		1
CUSTOMER ID	PERSONAL ID	ID TYPE	-TYPE-	VER	UPD DATE	UPD TIME			
11111111111111111111111111111111	CUSTOMER A	CU	ADD	1	MM/DD/YY	HH:MM:SS			
-----					-----				
ADDS	1	CHANGES	0	DELETES	0	TOTAL	1		

CUSTOMER ID — The unique identification number assigned to this customer. This value corresponds to the CUSTOMER ID fields on CSTT screen 3 and the PAN field on PIT screen 2.

PERSONAL ID — A code identifying a personal ID. The personal ID associates a different person with access to the specified customer ID. This value corresponds to the PERSONAL ID fields on CSTT screen 3 and PIT screen 2.

ID TYPE — A code indicating the type of table to which the customer ID pertains. This value corresponds to the ID TYP field on PIT screen 2.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new row (1)
CHANGE = Update an existing row (2)
DELETE = Delete an existing row (3)
INQUIRY = Obtain information from an existing row (5)
INVALID = The ULF record contains an invalid update type code

VER — The version of the row written to the CPIT. This value corresponds to the VER column in the CPIT row and does not appear on the CSTT or PIT screen.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

TOTALS

The number of CPIT update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of CPIT update records is also provided.

Negative Card File Activity Report

The Negative Card File (NEG) Activity Report contains information about all the changes, additions, and deletions made to the NEG.

The masking of cardholder primary account numbers (PANs) and administrative PANs on this report depends on the values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the following manuals for files maintenance screens and field descriptions:

NEG Screen	Manual
1	<i>BASE24 Base Files Maintenance Manual</i>
3–4	Device-specific BASE24-atm self-service banking (SSB) manuals

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT															
NEGATIVE AUTHORIZATION FILE (NEG)				BNKA - BANK A				MM/DD/YY				PAGE			
ACCOUNT NUMBER		-TYPE-		MEM	CARD	REASON	CAPTURE	DATE	EXPIR	-----UPDATE-----		TIME		-----OPERATOR-----	
ADD		XXXXXXXXXXXXXXXXXXXX		111	C0	0	0	MM/DD/YY	MM/YY	MM/DD/YY	HH:MM:SS			Q3	
-----SUPER TELLER TERMINALS-----															
11111111111111				22222222222222				33333333333333				44444444444444			
66666666666666				77777777777777								55555555555555			
-----SELF SERVICE BANKING CHECK-----															
CORPORATION NUMBER															
1111111111															
-----TOTALS-----															
ADDS		1		CHANGES		0		DELETES		0		TOTAL		1	

ACCOUNT NUMBER — The card number or primary account number (PAN) identifying the card. This value corresponds to the PAN field on NEG screen 1. Values of the four REPORT DATA MASKING PARAMETER fields on Institution Definition File (IDF) screen 4 control masking of the value in this field.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
CHANGE = Update an existing record (2)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INVALID = The ULF record contains an invalid update type code

MEM NUM — The member number for the card. This value corresponds to the MEMBER field on NEG screen 1.

CARD TYPE — A code identifying the type of card associated with the PAN. This value corresponds to the CARD TYPE field on NEG screen 1.

REASON CODE — A code identifying the reason the card is in the NEG. This value corresponds to the REASON ON FILE field on NEG screen 1.

CAPTURE CODE — A code identifying whether the card should be captured when used. This value corresponds to the CAPTURE CODE field on NEG screen 1.

DATE ADDED — The date (MM/DD/YY) the card was added to the NEG. This value corresponds to the DATE ADDED TO FILE field on NEG screen 1.

EXPIR DATE — The expiration date (MM/YY) of the NEG record. After the indicated month begins, the NEG record no longer affects processing. This value corresponds to the EXPIRATION DATE field on NEG screen 1.

UPDATE DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPDATE TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

SUPER TELLER TERMINALS — This field, which can appear as many as 10 times, identifies the terminals associated with a Super Teller card. This field only appears when an institution is using the BASE24-atm self-service banking Base Application. The teller IDs associated with a Super Teller card cannot be updated individually. All teller IDs associated with a Super Teller card must be updated at the same time. This field corresponds to the SUPER TELLER TERMINAL ID field on NEG screen 3.

SELF SERVICE BANKING CHECK CORPORATION NUMBER — The corporation number already assigned in the Corporate Check File (CCF) to identify a business that issues check cashing cards to its employees. These cards enable employees to cash checks at the financial institution even though they do not have an account with the financial institution. This field corresponds to the CORPORATION NUMBER field on NEG screen 4.

TOTALS

The number of NEG update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of NEG update records is also provided.

No Book File Activity Report

The No Book File (NBF) Activity Report contains information about all the additions and deletions made to the NBF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the ***BASE24-teller Files Maintenance Manual*** for more information on the NBF screens and field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT														
PASSBOOK NO BOOK FILE (NBF)					BNKA - BANK A					MM/DD/YY PAGE 1				
ACCOUNT NUMBER	TELLER	TYPE	ACCT TYPE	TRAN DATE	REGION	POST CITY	DATE	NBF STAT	TRAN TYPE	B24	TRAN	DEV	TRAN	UPD DATE
OPERATOR	11111111111111111111111111111111	ADD	11	MM/DD/YY	RGNA	MM/DD/YY	HH:MM:SS	Y	D	100100	MM/DD/YY	HH:MM:SS	TRAN AMOUNT	PRINT BALANCE
	TELLER A				BRNA	CITY		A	Q3	111111			0.00	0.00
-----TOTALS-----														
ADDS	1	DELETES	0	TOTAL										

ACCOUNT NUMBER — The account number of the passbook account. This value corresponds to the ACCOUNT NUMBER field on NBF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
 DELETE = Delete an existing record (3)
 INQUIRY = Obtain information from an existing record (5)
 INVALID = The ULF record contains an invalid update type code

TRAN DATE — The calendar date (MM/DD/YY) the transaction occurred. This value corresponds to the DATE field on NBF screen 1.

REGION — The region of the terminal where the transaction was initiated. This value corresponds to the REGION field on NBF screen 1.

POST DATE — The date (MM/DD/YY) on which the transaction occurred. The posting date can be 00/00/00 when there is no corresponding record on the Teller Transaction Log File (TTLF) for the transaction. This value corresponds to the PO DAT field on NBF screen 2.

NBF STAT — A code indicating whether the transaction has been printed in the customer's passbook. This value corresponds to the PRNT field on NBF screen 2.

TRAN TYPE — A code indicating the general type of transaction. This value corresponds to the TYP field on NBF screen 2.

B24 TRAN — The transaction code that identifies the type of transaction. This value corresponds to the BASE24 TR CDE field on NBF screen 2.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

PRINT BALANCE — The passbook balance amount, in whole and fractional currency units, after the transaction carried in the NBF is printed in the passbook. This value corresponds to the PRINTED BAL field on NBF screen 2.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

TELLER — The identification number or value assigned to the teller who performed the transaction. This value corresponds to the TELLER ID field on NBF screen 1.

ACCT TYPE — A code identifying the type of account. This value corresponds to the ACCOUNT TYPE field on NBF screen 1.

TRAN TIME — The time (hh:mm:ss) the transaction occurred. This value corresponds to the TIME field on NBF screen 1.

BRANCH — The regional branch associated with the terminal where the transaction was initiated. This value corresponds to the BRANCH field on NBF screen 1.

CITY — The city in which the transaction was initiated. This value corresponds to the CITY field on NBF screen 1.

POST SYS — A code identifying the origin of the NBF record. This value corresponds to the RECORD ORIGINATING INDICATOR field on NBF screen 1.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

DEV TRAN — The teller device transaction code identifying the type of transaction performed. This value corresponds to the DEVICE TRANSACTION CODE field on NBF screen 1.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

TRAN AMOUNT — The amount, in whole and fractional currency units, of the transaction. This value corresponds to the TRANSACTION AMOUNT field on NBF screen 1.

TOTALS

The number of NBF update records, by update type, included on the report. Update types include addition and deletion. The total number of NBF update records is also provided.

Personal Information Table Activity Report

The Personal Information Table (PIT) Activity Report contains information about all the changes, additions, and deletions made to the PIT.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a table maintenance screen. Refer to the ***BASE24 Core Files and Tables Maintenance Manual*** for more information about the PIT screens and their field descriptions.

BASE24--FROM HOST MAINTENANCE ACTIVITY REPORT															
PERSONAL INFORMATION TABLE (PIT)													MM/DD/YY	PAGE	1
-----PERSONAL ID-----															
-TYPE-															
-----STREET ADDRESS-----															
CNTRY CDE	POSTAL CDE	LANG IND	FIID	FAMILY NAME	GIVEN NAME	MIDDLE INIT	TITLE	FAMILY NAME	TKN	GIVEN NAME	TKN	ST CDE	OTHER PHONE 1	DESCR	
VER	OTHER PHONE 2	OTHER PHONE 2	DESCR	HOME PHONE	MOTHER MAIDEN NAME	GOVT ID	BIRTHDATE	UPD DATE	UPD TIME	UPD DATE	UPD TIME	UPD DATE	UPD TIME	UPD DATE	
CUSTOMER A	ADD	BNKA	CUSTOMER	JOHN	COLLEGE	Q	MR.	1111111111111111	222222	222222	222222	NE	PAGER	HH:MM:SS	
ROOM 1234	12345-6789	1	(402)	390-7600	(402)	555-1234	(402)	555-5678	MM/DD/YY	MM/DD/YY	MM/DD/YY	MM/DD/YY	MM/DD/YY	MM/DD/YY	
840				SMITH		123-45-6789									
1000															
-----TOTALS-----															
ADDS	1	CHANGES	0	DELETES	0	TOTAL	1								

PERSONAL ID — The identifier associated with a customer. This value corresponds to the PERSONAL ID field on PIT screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new row (1)
CHANGE = Update an existing row (2)
DELETE = Delete an existing row (3)
INQUIRY = Obtain information from an existing row (5)
INVALID = The ULF record contains an invalid update type code

FIID — The FIID of the financial institution associated with the personal ID. This value corresponds to the FIID field on PIT screen 1.

FAMILY NAME — The family name or last name of the customer. This value corresponds to the FAMILY field on PIT screen 1.

GIVEN NAME — The given name or first name of the customer. This value corresponds to the GIVEN field on PIT screen 1.

MIDDLE INIT — The initial of the customer's middle name. This value corresponds to the M/I field on PIT screen 1.

TITLE — The social title (for example, Mr., Mrs., Ms., Dr., Rev.), civil and military title (for example, Gen., Gov., Prof.), or any other title used to address this customer. This value corresponds to the TITLE field on PIT screen 1.

FAMILY NAME TKN — The family name audio token generated by a name token generation algorithm. This value corresponds to the NAM_TKN_FMLY field in the PIT row and does not appear on the PIT screen.

GIVEN NAME TKN — The given name audio token generated by a name token generation algorithm. This value corresponds to the NAM_TKN_GIVEN field in the PIT row and does not appear on the PIT screen.

STREET ADDRESS — The customer's street or mailing address. In this sample, the customer's address contains three lines: a room number, a dormitory name, and a college name. This value corresponds to the ADDRESS 1, ADDRESS 2, and ADDRESS 3 fields on PIT screen 1.

CITY — The name of the city for this customer's residence or mailing address. This value corresponds to the CITY field on PIT screen 1.

ST CDE — The two-letter U.S. state or Canadian province abbreviation for this customer's residence or mailing address. This value corresponds to the STATE field on PIT screen 1.

CNTRY CDE — The country code associated with this customer's residence or mailing address. This value corresponds to the CNTRY field on PIT screen 1.

POSTAL CDE — The postal code of this customer's residence or mailing address. This value corresponds to the POSTAL CODE field on PIT screen 1.

LANG IND — A user-defined code indicating the primary language spoken by this customer. This value corresponds to the LANGUAGE IND field on PIT screen 1.

HOME PHONE — The home telephone number for this customer. This value corresponds to the HOME PHONE field on PIT screen 1.

WORK PHONE — The work telephone number for this customer. This value corresponds to the WORK PHONE field on PIT screen 1.

OTHER PHONE 1 — Any other telephone number (for example, cellular, paging, or fax) that can be used to reach this customer. This value corresponds to the first OTHER PHONE field on PIT screen 1.

OTHER PHONE 1 DESCR — A description of the telephone number provided in the OTHER PHONE 1 field. This value corresponds to the first DESCR field on PIT screen 1.

VER — The version of the record written to the PIT. This value corresponds to the VER field on the PIT row and does not appear on the PIT screen.

OTHER PHONE 2 — Any other telephone number that can be used to reach this customer. This value corresponds to the second OTHER PHONE field on PIT screen 1.

OTHER PHONE 2 DESCR — A description of the telephone number provided in the OTHER PHONE 2 field. This value corresponds to the second DESCR field on PIT screen 1.

MOTHER MAIDEN NAME — The maiden name of this customer's mother. This name can be used by customer service representatives to verify the identity of a calling customer. This value corresponds to the MOTHER'S MAIDEN NAME field on PIT screen 1.

GOVT ID — The government ID (for example, U.S. social security number) assigned to this customer. This value corresponds to the GOVERNMENT ID field on PIT screen 1.

BIRTHDATE — The birth date (YYYY-MM-DD) of this customer. This value corresponds to the BIRTH DATE field on PIT screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

TOTALS

The number of PIT update records, by update type, included on the report. Update types include addition, change, and deletion. The total number of PIT update records is also provided.

Positive Balance File Activity Report

The Positive Balance File (PBF) Activity Report contains information about all the changes, additions, deletions, and increments made to the PBF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the ***BASE24 Base Files Maintenance Manual*** for more information on the PBF screens and their field descriptions.

BASE24-FROM HOST MAINTENANCE ACTIVITY REPORT															MM/DD/YY	PAGE
POSITIVE BALANCE FILE (PBF)																1
-----ACCOUNT NUMBER-----TYPE-AT STAT																
UPD DATE UPD TIME																
HOLD AMT																
-----OPERATOR-----																
LEDGER BAL																
DATE																
AMOUNT																
ADD 01 1																
200.00																
800.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																
00/00/00																
1,000.00																
000.00																

ACCOUNT NUMBER — The account number of the application account whose information is contained in the PBF record. This value corresponds to the ACCOUNT NUMBER field on PBF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
 CHANGE = Update an existing record (2)
 DELETE = Delete an existing record (3)
 INQUIRY = Obtain information from an existing record (5)
 INCR = Increase or decrease amounts or counters in an existing record (9)
 INVALID = The ULF record contains an invalid update type code

AT — A code identifying the type of account. This value corresponds to the ACCOUNT TYPE field on PBF screen 1.

STAT — A code identifying the current status of the application account. This value corresponds to the ACCOUNT STATUS field on PBF screen 1.

AVAIL BAL — When the account associated with the PBF record is a savings or checking account, this field contains the available balance of the account. When the account associated with the PBF record is a credit account, this field contains the available credit of the account. This value corresponds to the AVAILABLE BALANCE/AVAILABLE CREDIT field on PBF screen 1.

LEDGER BAL — When the account associated with the PBF record is a savings or checking account, this field contains the current balance of the account. When the account associated with the PBF record is a credit account, this field contains the credit limit of the account. This value corresponds to the LEDGER BALANCE/CREDIT LIMIT field on PBF screen 1.

OD LIMIT — The amount available for overdraft on the account. This value corresponds to the OVERDRAFT LIMIT field on PBF screen 1.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

UPD DATE — The date the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

HOLD AMT — When the account associated with the PBF record is a savings or checking account, this field contains the amount on hold. When the account associated with the PBF record is a credit account, this field contains the credit balance of the account. This value corresponds to the AMOUNT ON HOLD/CREDIT BALANCE field on PBF screen 1.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

LAST DEPOSIT DATE — When the account associated with the PBF record is a savings or checking account, this field contains the date (MM/DD/YY) of the last BASE24-authorized deposit or transfer to the account. When the account associated with the PBF record is a credit account, this field contains the date of the last payment to the account. This value corresponds to the LAST DEPOSIT DATE field on PBF screen 1.

LAST DEPOSIT AMOUNT — When the account associated with the PBF record is a savings or checking account, this field contains the amount of the last BASE24-authorized deposit or transfer to the account. When the account associated with the PBF record is a credit account, this field contains the amount of the last payment to the account. This value corresponds to the LAST DEPOSIT AMOUNT field on PBF screen 1.

LAST WITHDRAWAL DATE — When the account associated with the PBF record is a savings or checking account, this field contains the date (MM/DD/YY) of the last BASE24-authorized withdrawal, payment, or transfer from the account. When the account associated with the PBF record is a credit account, this field contains the date of the last charge to the account. This value corresponds to the LAST WITHDRAWAL DATE field on PBF screen 1.

LAST WITHDRAWAL AMOUNT — When the account associated with the PBF record is a savings or checking account, this field contains the amount of the last BASE24-authorized withdrawal, payment, or transfer from the account. When the

account associated with the PBF record is a credit account, this field contains the amount of the last charge to the account. This value corresponds to the LAST WITHDRAWAL AMOUNT field on PBF screen 1.

CURRENCY CODE — A numeric ISO code indicating the currency in which this account is maintained. Valid values are listed in the ISO 4217:1995 standard, *Codes for the Representation of Currencies and Funds*. If no value is entered in this field, it defaults to the value of the first entry in the CURRENCY-CODE-TABLE in the COBNAMES file. This value corresponds to the CURRENCY CODE field on PBF screen 1.

SHORT NAME PBF EXTENSION/ CREDIT LINE PBF EXTENSION

The following fields contain information from the Short Name segment of the PBF and the Credit Line segment of the PBF.

SHORT NAME — The name of the customer. This value corresponds to the CUSTOMER SHORT NAME field on PBF screen 5.

CREDIT LINE ACCT — The account number of another PBF account being used as a credit line or backup account for the PBF account identified in the ACCOUNT NUMBER field. This value corresponds to the ACCOUNT NUMBER field on PBF screen 6.

CREDIT LINE ACCT TYP — A code identifying the type of PBF account being used as a credit line or backup account. This value corresponds to the ACCOUNT TYPE field on PBF screen 6.

TELLER PBF EXTENSION

The following fields identify status codes and limits contained in the BASE24-teller segment of the PBF.

PBF STAT — A code indicating the current status of the account and the action to be taken by the Authorization process if this account status is encountered. This value corresponds to the ACCOUNT STATUS field on PBF screen 1.

SPF STAT — A flag indicating whether stop payments or warnings have been placed on the account. This value corresponds to the STOP PAY/WARNING STATUS field on PBF screen 10.

CUST CLS — A code that determines how much cash is available to the customer after a check deposit. This value corresponds to the CUSTOMER CLASS field on PBF screen 10.

TOTAL DEPOSIT AMT — The total amount deposited to an account using BASE24-teller terminals during the current BASE24 processing day. This value corresponds to the TOTAL DEPOSIT AMOUNT field on PBF screen 10.

START BAL — The ledger balance, in whole and fractional currency units, of the account on the host as of the last time the account was updated by the Refresh process. This value corresponds to the STARTING BALANCE field on PBF screen 10.

SIGN LOC — The location of the signature card for the account. This value corresponds to the SIGNATURE CARD LOCATION field on PBF screen 10.

PB IND — A flag used by BASE24 to determine whether the account is a passbook account. This value corresponds to the PASSBOOK INDICATOR field on PBF screen 10.

NBF CNT — The number of entries in the NBF for the account. This value corresponds to the NBF RECORD COUNT field on PBF screen 10.

PASSBOOK BAL — The printed passbook balance, in whole and fractional currency units, of the account as of the last update of the passbook. This value corresponds to the PASSBOOK BALANCE field on PBF screen 10.

CASH IN LIMIT — The maximum amount of cash that can be deposited to the account using BASE24-teller during a BASE24 processing day. The value is represented in multiples of 1000. This value corresponds to the CASH IN LIMIT field on PBF screen 10.

CASH OUT LIMIT — The maximum amount of cash that can be disbursed from the account using BASE24-teller during a BASE24 processing day. The value is represented in multiples of 1000. This value corresponds to the CASH OUT LIMIT field on PBF screen 10.

ACCRUED INTEREST YTD — The total amount, in whole and fractional currency units, of year-to-date interest on the account. This value corresponds to the ACCRUED INTEREST YTD field on PBF screen 10.

POS PBF EXTENSION

The following fields present float information and parametric authorization data contained in the BASE24-pos segment of the PBF.

CURRENT FLOAT — The transaction amount authorized during the current accumulation period for the account. This value corresponds to the CURRENT FLOAT field on PBF screen 8.

TOTAL FLOAT — The balance of credit transactions associated with the account for which the paperwork has not been received. This value corresponds to the TOTAL FLOAT field on PBF screen 8.

DAYS DELINQUENT — The number of days the account has been delinquent. This value corresponds to the DAYS DELINQUENT field on PBF screen 8.

MONTHS ACTIVE — The number of months the account has been active. This value corresponds to the MONTHS ACTIVE field on PBF screen 8.

CYCLE 1 — The number of times the account has been delinquent for one cycle. This value corresponds to the # OF TIMES 1 CYCLE DELINQUENT field on PBF screen 8.

CYCLE 2 — The number of times the account has been delinquent for two cycles. This value corresponds to the # OF TIMES 2 CYCLE DELINQUENT field on PBF screen 8.

CYCLE 3 — The number of times the account has been delinquent for three cycles. This value corresponds to the # OF TIMES 3 CYCLE DELINQUENT field on PBF screen 8.

PRE-AUTH PBF EXTENSION

The following fields, which can occur as many as 10 times, identify preauthorized holds that have been placed on the PBF account. These fields are contained in the Preauthorized Holds segment of the PBF. Fields in the Preauthorized Holds segment cannot be updated individually. All fields in the Preauthorized Holds segment of a PBF record must be updated at the same time.

SEQ NUM — The sequence number assigned to the hold by the issuer. This value corresponds to the TRANSACTION NUMBER field on PBF screen 3.

HOLD AMOUNT — The transaction amount associated with the hold. This value corresponds to the AMOUNT field on PBF screen 3.

EXPIRE DATE — The date and time the hold amount is cleared and no longer taken into consideration during BASE24 Authorization processing. This value corresponds to the HOLD STATUS field on PBF screen 3.

TELEBANKING EXTENSION

The following fields identify the limits contained in the BASE24-telebanking segment of the PBF.

CASH ADVANCE MINIMUM — The minimum cash advance amount, in whole currency units (for example, U.S. dollars), allowed for transfer or payment transactions that withdraw funds from a credit account. This value corresponds to the MINIMUM CASH ADVANCE AMOUNT field on PBF screen 11.

CASH ADVANCE INCR — The standard increment amount, in whole currency units (for example, U.S. dollars), used to determine the amount of transfer or payment transactions that withdraw funds from a credit account. This value corresponds to the CASH ADVANCE INCREMENT field on PBF screen 11.

PERIOD TRANSFER LMT

The following fields identify the transfer or payment limits for the usage accumulation period.

AMOUNT — The maximum amount, in whole currency units (for example, U.S. dollars), of funds withdrawn from an account by transfer and payment transactions during a single usage accumulation period. This value corresponds to the PERIODIC LIMIT AMOUNT field on PBF screen 11.

COUNT — The maximum number of withdrawals from an account by transfer and payment transactions during a single usage accumulation period. This value corresponds to the PERIODIC LIMIT COUNT field on PBF screen 11.

CYCLE TRANSFER LMT

The following fields identify the transfer or payment limits for the usage accumulation period.

AMOUNT — The maximum amount, in whole currency units (for example, U.S. dollars), of funds withdrawn from an account by transfer and payment transactions during a single usage accumulation period. This value corresponds to the CYCLIC LIMIT AMOUNT field on PBF screen 11.

COUNT — The maximum number of withdrawals from an account by transfer and payment transactions during a single usage accumulation period. This value corresponds to the CYCLIC LIMIT COUNT field on PBF screen 11.

CSFC PBF EXTENSION

The following fields present BASE24 Customer Service information maintained in the PBF.

PRIOR YTD INTEREST — The prior year-to-date interest. If the account is a credit account, this value represents the amount of interest charged. If the account is a debit account, this value represents the amount of interest earned. This value corresponds to the PRIOR YEAR TO DATE INTEREST field on PBF screen 13.

CURRENT INT RATE — The current interest rate. If the account is a credit account, this value represents the rate of interest charged. If the account is a debit account, this value represents the rate of interest earned. This value corresponds to the CURRENT INTEREST RATE field on PBF screen 13. If a value is present, the first digit indicates the scale (that is, the number of digits to the right of the decimal point).

CASH ADV INT RATE — The cash advance interest rate for a credit account. This value corresponds to the CASH ADVANCE INTEREST RATE field on PBF screen 13. If a value is present, the first digit indicates the scale (that is, the number of digits to the right of the decimal point).

MIN AMOUNT DUE — The minimum payment amount, in whole and fractional currency units, due for the credit account. This value corresponds to the MINIMUM AMT DUE field on PBF screen 13.

PAYMENT DUE DATE — The date (YY/MM/DD) the next payment is due on a credit account. This value corresponds to the NEXT PAYMENT DUE DATE field on PBF screen 13.

CRED LMT CHG DATE — The date (YY/MM/DD) the credit (for a credit account) or overdraft (for a noncredit account) limit was changed. This value corresponds to the LAST CREDIT LIMIT CHANGE DATE field on PBF screen 13.

CYCLE COUNT — The number of cycles present in this record. This example shows four cycles. This value corresponds to the CYC-CNT field in the PBF record and is not present on the PBF screens.

NSF/DELINQ COUNT — The number of times a noncredit account did not have sufficient funds or the number of times a credit account payment was delinquent during this particular cycle. If the account is a noncredit account, this value corresponds to the NSF field on PBF screen 14. If the account is a credit account, this value corresponds to the DELINQ field on PBF screen 14.

OVERDRAWN OVER LIMIT — The number of times a noncredit account was overdrawn or the number of times a credit limit was exceeded during this particular cycle. If the account is a noncredit account, this value corresponds to the OVERDRAFT field on PBF screen 14. If the account is a credit account, this value corresponds to the OVERLIMIT field on PBF screen 14.

ACCOUNT BALANCE — The account balance for the particular cycle. This value corresponds to the BALANCE field on PBF screen 14.

ACCT STAT — A code identifying the account status for the particular cycle. This value corresponds to the STATUS field on PBF screen 14.

TOTALS

The number of PBF update records, by update type, included on the report. Update types include addition, change, increment, and deletion. The total number of PBF update records is also provided.

Stop Payment File Activity Report

The Stop Payment File (SPF) Activity Report contains information about all the additions and deletions made to the SPF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the ***BASE24 Base Files Maintenance Manual*** for more information about the SPF screens and field descriptions.

BASE24-FROM HOST MAINTENANCE ACTIVITY REPORT									
STOP PAYMENT FILE (SPF)					BNKA - BANK A				
ACCOUNT NUMBER		ACCT TYPE	HIGH CHECK NUM	LOW CHECK NUM	DATE	TIME	EXP DATE	UPD DATE	PAGE
-----		----	-----	-----	----	----	----	----	1
-----OPERATOR-----									
11111111111111111111111111111111		ADD	01	1001	1001	MM/DD/YY	HH:SS:MM	MM/DD/YY	
					0.00	CHECK TO RETAILER A			
-----TOTALS-----									
ADDS	1	DELETES	0	TOTAL	1				

ACCOUNT NUMBER — The account number of the account that has a stop payment on a check. This value corresponds to the ACCOUNT NUMBER field on SPF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INVALID = The ULF record contains an invalid update type code

ACCT TYPE — A code identifying the type of customer account specified in the ACCOUNT NUMBER field. This value corresponds to the ACCOUNT TYPE field on SPF screen 1.

HIGH CHECK NUM — The check number of the check on which the stop payment order is being placed. If the stop payment order is being placed on a single check, this field contains the check number. If the stop payment order is being placed on a series of checks, this field contains the high (that is, ending) check number. This value corresponds to the CHECK NUMBER/HIGH CHECK NUMBER field on SPF screen 1.

LOW CHECK NUM — The check number of the check on which the stop payment order is being placed. If the stop payment order is being placed on a single check, this field contains blanks. If the stop payment order is being placed on a series of checks, this field contains the low (that is, starting) check number. This value corresponds to the LOW CHECK NUMBER field on SPF screen 1.

DATE — The date (MM/DD/YY) that the stop payment order was entered. This value corresponds to the DAT field on SPF screen 1.

TIME — The time (hh:mm:ss:tt) that the stop payment order was entered. This value corresponds to the TIM field on SPF screen 1.

EXP DATE — The date (YY/MM/DD) that the stop payment order expires. This value corresponds to the EXPIRATION DATE field on SPF screen 1.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

AMOUNT — The amount of the stop payment order placed on a single check. This value corresponds to the AMOUNT field on SPF screen 1.

DESCRIPTION — An information-only field for entering a message regarding the stop payment order. This value corresponds to the DESCRIPTION field on SPF screen 1.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

TOTALS

The number of SPF update records, by update type, included on the report. Update types include addition and deletion. The total number of SPF update records is also provided.

Warning/Hold/Float File Activity Report

The Warning/Hold/Float File (WHFF) Activity Report contains information about all the additions and deletions made to the WHFF.

A sample of the report format is shown on the next page followed by descriptions of the fields that appear on the report. Each field description includes the name of the corresponding field on a files maintenance screen. Refer to the ***BASE24-teller Files Maintenance Manual*** for more information on the WHFF screens and field descriptions.

[illegible]

ACCOUNT NUMBER — The account number of the customer's account that has a warning, hold, or deposit float record. This value corresponds to the ACCOUNT NUMBER field on WHFF screen 1.

TYPE — The type of update requested. Update types are obtained from the FILE-CDE field in the ULF. Values for the FILE-CDE field are shown in parentheses. Valid values are as follows:

ADD = Add a new record (1)
DELETE = Delete an existing record (3)
INQUIRY = Obtain information from an existing record (5)
INVALID = The ULF record contains an invalid update type code

ACCT TYPE — A code identifying the type of customer account specified in the ACCOUNT NUMBER field. This value corresponds to the ACCOUNT TYPE field on WHFF screen 1.

RECORD TYPE — The type of WHFF record. Record types are obtained from the RECORD TYPE field on WHFF screen 1. Values for the WHFF RECORD TYPE field are shown in parentheses.

DATE — The date (MM/DD/YY) that the record was added to the WHFF. This value corresponds to the DATE field on WHFF screen 1.

TIME — The date (hh:mm:ss:tt) that the record was added to the WHFF. This value corresponds to the TIME field on WHFF screen 1.

EXP DATE — The expiration date (MM/DD/YY) for the WHFF record. This value corresponds to the EXPIRATION DATE field on WHFF screen 1.

OPERATOR — The operator that sent the update message. This field is reserved for future use.

AMOUNT — The amount, in whole and fractional currency units, of the WHFF record. This value corresponds to the AMOUNT field on WHFF screen 2.

DESCRIPTION — An information-only field for entering a message regarding the WHFF record. This value corresponds to the DESCRIPTION field on WHFF screen 2.

UPD DATE — The date (MM/DD/YY) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-DAT field in the ULF.

UPD TIME — The time (hh:mm:ss) the change was logged to the ULF. This value corresponds to the ALTKEY.UPDT-TIM field in the ULF.

RESP — A code identifying the result of the update request. This value corresponds to the RESP-CDE field in the ULF. Refer to section 4 for valid values.

TOTALS

The number of WHFF update records, by update type, included on the report. Update types include addition and deletion. The total number of WHFF update records is also provided.

Reject Reports

The reject report contains the information supplied in the original request, as well as the response code that identifies the reason for rejection.

The fields included in each report correspond to the fields required in the update request message. Only specific fields from the standard ULF header are reported. However, all of the header information is available by extracting the ULF to tape.

There is one reject report for each file or table that can be updated. In addition, a reject report is produced that shows all rejected updates to the CAF Accounts segment. The reject reports produced by BASE24-from host maintenance are listed below, followed by a sample CAF Reject Report. The reject report for each file or table uses the same format as the activity report. Refer to the activity report illustrations and field descriptions.

CAF Reject Report — The CAF Reject Report contains information about all the updates that were attempted to be made to the CAF, but failed. The report also indicates why the messages failed.

CAF Accounts Reject Report — The CAF Accounts Reject Report contains information about all the updates that were attempted to be made to the CAF Accounts segment, but failed. The report also indicates why the messages failed.

CSF Reject Report — The CSF Reject Report contains information about all the updates that were attempted to be made to the CSF, but failed. The report also indicates why the messages failed.

CCF Reject Report — The CCF Reject Report contains information about all the updates that were attempted to be made to the CCF, but failed. The report also indicates why the messages failed.

CSTT Reject Report — The CSTT Reject Report contains information about updates that were attempted to be made to the CSTT, but failed. The report also indicates why the messages failed.

CACT Reject Report — The CACT Reject Report contains information about updates that were attempted to be made to the CACT, but failed. The report also indicates why the messages failed.

CCIF Reject Report — The CCIF Reject Report contains information about all the updates that were attempted to be made to the CCIF, but failed. The report also indicates why the messages failed.

CCMF Reject Report — The CCMF Reject Report contains information about all the updates that were attempted to be made to the CCMF, but failed. The report also indicates why the messages failed.

CPIT Reject Report — The CPIT Reject Report contains information about updates that were attempted to be made to the CPIT, but failed. The report also indicates why the messages failed.

NEG Reject Report — The NEG Reject Report contains information about all the updates that were attempted to be made to the NEG, but failed. The report also indicates why the messages failed.

NBF Reject Report — The NBF Reject Report contains information about all the updates that were attempted to be made to the NBF, but failed. The report also indicates why the messages failed.

PIT Reject Report — The PIT Reject Report contains information about updates that were attempted to be made to the PIT, but failed. The report also indicates why the messages failed.

PBF Reject Report — The PBF Reject Report contains information about all the updates that were attempted to be made to the PBF, but failed. The report also indicates why the messages failed.

SPF Reject Report — The SPF Reject Report contains information about all the updates that were attempted to be made to the SPF, but failed. The report also indicates why the messages failed.

WHFF Reject Report — The WHFF Reject Report contains information about all the updates that were attempted to be made to the WHFF, but failed. The report also indicates why the messages failed.

CARDHOLDER AUTHORIZATION FILE (CAF)										BASE24-FROM HOST MAINTENANCE REJECT REPORT									
										BNKA - BANK A									
										MM/DD/YY PAGE 1									
MEM CARD										WITHDRAWAL LIMITS									
-TYPE- NUM TYPE STAT ON/A OFF/A ON/C OFF										EXPIR DATE AC CNT CODE									
CRD2 STAT EXPIR EXP POWER ---PIN CHECK---										UPD DATE UPD TIME ---OPERATOR---									
---ACCOUNT INFORMATION---										---ACCOUNT INFORMATION---									
TY --- ACCOUNT NUMBER ---S ---DESC---ACH TY --- ACCOUNT NUMBER ---S ---DESC---ACH																			
11111111111111111111111111111111 ADD 111 C0 1 0 0 0 0 0 0 0 0 MM/YY 2 Q3																			
01 11111111111111111111111111111111 1 1111111111 A 01 222222222222222222222222222222 1 XMAS CLUB																			
---ATM CAF EXTENSION---																			
ON/LIM OFF/LIM ON/CLIM OFF/CLIM DEP CR LIM USE TODAY																			
0 0 0 0 0 0 0 0 0 0																			
---POS CAF EXTENSION---																			
ON/PLIM OFF/PLIM ON/CLIM OFF/CLIM ON/WLIM OFF/WLIM ON/RLIM OFF/RLIM USED TODAY																			
0 0 0 0 0 0 0 0 0 0																			
ADDRESS: STREET ADDRESS ZIP CDE: ZIP																			
1111111111111111 2222222222222222 3333333333333333 44444444444444 5555555555555555																			
6666666666666666 7777777777777777																			
---SELF SERVICE BANKING CHECK---																			
CORP NUM CSF CHK USE LMT TOTAL CHK LMT OFFLINE CHK LMT TOTAL CSF CHK LMT OFFLINE CSF CHK LMT																			
1111111111 0 0 0 0 0 0 0 0 0 0																			
---CARD CAF EXTENSION---																			
BRANCH NUM DEPT NUM PIN MAILER CARD CARRIER ISS STAT CARDS TO ISSUE CARDS RETURNED SERVICE CODE																			
1234 00 0 0 01 1																			
NAME LINE 1 : NAME ADDR LINE 1 : STREET ADDRESS																			
NAME LINE 2 : NAME ADDR LINE 2 : STREET ADDRESS																			
TITLE : 2 CITY : CITY																			
COMMENTS :										STATE : ST ZIP : 000000000 COUNTRY CODE : 840									
---PRE-AUTH CAF EXTENSION---																			
SEQ NUM HOLD AMOUNT 0.00 ACCOUNT NUMBER 1111111111111111 ACCT TYPE 01 EXPIRE DATE YYMMDD HH:MM:SS:TT																			
000000000001																			
---ENHANCED PRE-AUTH CAF EXTENSION---																			
SEQ NUM HOLD AMOUNT TERM-ID TERM1 OK1 YYMMDD HH:MM:SS:TT ACCT TYPE FLAG																			
000000000002 111.11 TERM1 OK1 YYMMDD HH:MM:SS:TT 10 Y																			

BASE24-FROM HOST MAINTENANCE REJECT REPORT										MM/DD/YY	PAGE
CARDHOLDER AUTHORIZATION FILE (CAF)											2
BNKA - BANK A											
-----NON-CURRENCY DISPENSE CAP EXTENSION-----											
---TTL LMT CASH--- --OFFL LMT CASH-- -TTL LMT CCA CASH- OFFL LMT CCA CASH USE LMT											
HOPR1 ---TTL LMT NCD1--- --OFFL LMT NCD1-- -TTL LMT CCA NCD1- OFFL LMT CCA NCD1											
HOPR2 ---TTL LMT NCD2--- --OFFL LMT NCD2-- -TTL LMT CCA NCD2- OFFL LMT CCA NCD2											
0 0 0 0 0 0 0 0 0 0											
xx 0 0 0 0 0 0 0 0 0											
xx 0 0 0 0 0 0 0 0 0											
-----EMV CAF EXTENSION-----											
SEND SEND SEND SCPT SCPT											
ATC CRD PUT LWR CNSC PIN PIN IAD STAT CHK BAD CAP PRIMARY CARD DATA SECNDRY CARD DATA											
LIMIT BLCK DATA OFFL LMT UBLK CHNG TAG LGTH SYNC FRMT ACT INDX TKN OVRD CAP APSN CAP DKI CAP APSN CAP DKI											
211 Y Y 99 0 0 0 0 0 0 0 0 Y XX 99 XX 99											
-----PREFERRED TRANSACTION-----											
ACCT TRAN FM ACCT TO ACCT RCPT AMOUNT											
NUM TYPE TYPE TYPE OPT											
123456 10 01 00 0 Y 100 Y N AA											
-----TOTALS-----											
ADDS 1 CHANGES 0 INCREMENTS 0 DELETES 0 TOTAL 1											

4: Response Codes

This section contains a table of the response codes returned to the host. Depending on the files updated, some of the response codes in the table are not seen by a host. The response codes generated depend on which files an institution chooses to update.

BASE24-from host maintenance Response Codes

The table below shows the response codes for ISO-based external messages and gives a brief description of what the response code means. In the table, the term application file is used to refer to one of the files or tables the BASE24-from host maintenance product is updating. Application files and tables and their acronyms are as follows:

- Cardholder Authorization File (CAF)
- Check Status File (CSF)
- Corporate Check File (CCF)
- Customer Table (CSTT)
- Customer/Account Relation Table (CACT)
- Customer/Cardholder Information File (CCIF)
- Customer/Cardholder Memo File (CCMF)
- Customer/Personal ID Relation Table (CPIT)
- Negative Card File (NEG)
- No Book File (NBF)
- Personal Information Table (PIT)
- Positive Balance File (PBF)
- Stop Payment File (SPF)
- Warning/Hold/Float File (WHFF)

ISO	Description
00	A BASE24-from host maintenance message was accepted and the update was applied.
24	Request message rejected. A request was received from the host with an invalid update code.
25	Request message rejected. The record or row that was to be deleted could not be found on the file or table.
27	Request message rejected. A request was received from the host, but an error occurred when the From Host Maintenance process tried to convert the fields into internal format and was not able to select the appropriate row.

ISO	Description
27	Request message rejected. A request was received from the host, but an error occurred when the From Host Maintenance process tried to convert the fields into internal format.
96	TMF Abort transaction error. An error occurred while trying to abort a TMF transaction on an audited file or table.
96	TMF Begin transaction error. An error occurred when trying to begin a TMF transaction on an audited file or table.
96	TMF End transaction error. An error occurred when trying to end a TMF transaction on an audited file or table.
N1	Request message rejected. A request was received to access an application file or table, but the current system configuration does not include this file or table.
N2	Request message rejected. An error occurred during the opening of an application file or table.
N3	Request message rejected. An error occurred during the read of an application file or table.
N4	Request message rejected. A request was received to add a record or row to an application file or table, but the record or row already exists.
N5	Request message rejected. A request was received to change a record or row on an application file or table, but the record or row did not exist.
N6	Request message rejected. A request was received to inquire on an application file or table, but the record or row for the account specified does not exist.
N7	Request message rejected. A request was received to update an application file or table, but an error occurred during the actual write to the file or table.
N8	Request message rejected. A request was received to delete a record or row from an application file or table, but an error occurred during the actual write to the file or table.

ISO	Description
N9	Request message rejected. A request was received from the host with a different FIID in the record than was contained in the message header.
P1	Request message rejected. A request was received from the host that contained an FIID that is not defined in the IDF.
P2	Request message rejected. A request was received from the host that contained an invalid file type.
P3	Request message rejected. A request was received for an inquiry of the Accounts segment of a CAF record, but this transaction is not supported. An inquiry must include the entire CAF record to retrieve information from the Accounts segment.
P4	Request message rejected. A request was received to add the Accounts segment of the CAF, but the account number and type to be added already exists in the file.
P5	Request message rejected. A request was received that would cause the number of account types specified in the Accounts segment of the CAF to exceed the maximum number of 5.
P6	Request message rejected. A request was received that would cause the number of accounts specified in the Accounts segment of the CAF to exceed the maximum number of 16.
P7	Request message rejected. A request was received to modify or delete a record in the CAF, but the account number specified does not exist in the file.
P8	Record not added, PBF update error. A request was received to add a record to the NBF or WHFF, but an error occurred when an attempt was made to read the corresponding PBF record. Request message rejected.
P9	Record not added, PBF record does not exist. A request was received to add a record to the NBF or WHFF, but when an attempt was made to access the corresponding PBF record, it did not exist. Request message rejected.

ISO	Description
Q1	PBF record not deleted, SPF/WHFF records exist. A request was received to delete a record from the PBF, but the stop payment/warning status flag in the BASE24-teller segment of this PBF record indicates SPF or WHFF records exist for the account. A PBF record cannot be deleted when SPF or WHFF records exist.
Q2	Request message rejected. A request was received to delete a record from the PBF, but the NBF record count field in the BASE24-teller segment of the PBF record indicates that NBF records exist for the account. A PBF record cannot be deleted when NBF records exist.
Q3	Record read or updated, PBF record does not exist. A request was received to update the NBF, SPF, or WHFF, but when the attempt was made to find the associated PBF record to update the stop pay or warning status flag or NBF record count in the BASE24-teller segment, the PBF record did not exist. A PBF record does not have to exist when an NBF, SPF, or WHFF record is updated.
Q4	Record read or updated, PBF read error. A request was received to update the NBF, SPF, or WHFF, but when the attempt was made to find the associated PBF record to update the stop pay or warning status or NBF record count in the BASE24-teller segment, the PBF record could not be read. An NBF, SPF, or WHFF record can be updated when the PBF record cannot be read.
Q5	NBF record deleted, invalid NBF record count in PBF. A request was received to delete an NBF record, but the NBF record count in the BASE24-teller segment of the PBF record indicates that no NBF records exist for the account. An NBF record can be deleted when the record count in the BASE24-teller segment of the PBF record is zero.
Q6	Record added, PBF write error. A request was received to add an SPF or WHFF record, but the attempt to update the stop pay or warning status in the BASE24-teller segment of the PBF record was unsuccessful. An SPF or WHFF record can be added when the PBF record cannot be updated.

ISO	Description
Q7	Record deleted, PBF write error. A request was received to delete an NBF, SPF, or WHFF record, but the attempt to update the stop pay or warning status or NBF record count in the BASE24-teller segment of the PBF record was unsuccessful. An NBF, SPF, or WHFF record can be deleted when the PBF record cannot be updated.
Q8	NBF record not added, not a passbook account. A request was received to add a record to the NBF, but the passbook indicator in the BASE24-teller segment of the PBF record indicated the account was not a passbook account.

Index

A

Activity reports, [3-9](#)

B

BASE24-from host maintenance processing, [1-2](#)

C

Cardholder Authorization File (CAF), [2-4](#)

Cardholder Authorization File (CAF) Accounts Segment Activity Report, [3-29](#)

Cardholder Authorization File (CAF) Activity Report, [3-10](#)

Check Status File (CSF), [2-5](#)

Check Status File (CSF) Activity Report, [3-33](#)

Corporate Check File (CCF), [2-5](#)

Corporate Check File (CCF) Activity Report, [3-37](#)

Customer Table (CSTT), [2-5](#)

Customer Table (CSTT) Activity Report, [3-41](#)

Customer/Account Relation Table (CACT), [2-6](#)

Customer/Account Relation Table (CACT) Activity Report, [3-48](#)

Customer/Cardholder Information File (CCIF), [2-6](#)

Customer/Cardholder Information File (CCIF) Activity Report, [3-52](#)

Customer/Cardholder Memo File (CCMF), [2-6](#)

Customer/Cardholder Memo File (CCMF) Activity Report, [3-61](#)

Customer/Personal ID Relation Table (CPIT), [2-6](#)

Customer/Personal ID Relation Table (CPIT) Activity Report, [3-65](#)

E

External Message File (EMF), [2-6](#)

External messages, [1-9](#)

F

From Host Maintenance process
file usage, [2-4](#)
initialization, [2-19](#)
log messages, [2-12](#)
routing, [2-11](#)

startup logic, [2-10](#)
warmboot, [2-19](#)

H

Host Interface process

BASE24-from host maintenance process
configuration considerations, [2-10](#)

options, [1-7](#)

usage with BASE24-from host maintenance product, [1-5](#)

I

Initialization, [2-19](#)

Institution Definition File (IDF)

processing usage, [2-7](#)

reporting usage, [3-4](#)

L

Log Message Configuration File (LMCF), processing usage, [2-7](#)

Log messages, [2-12](#)

Logical Network Configuration File (LCONF)

assigns, [2-13](#)

params, [2-14](#)

processing usage, [2-7](#)

M

Message flows, [2-24](#)

N

Negative Authorization File (NEG), [2-7](#)

Negative Card File (NEG) Activity Report, [3-68](#)

No Book File (NBF), [2-8](#)

No Book File (NBF) Activity Report, [3-72](#)

P

Personal Information Table (PIT), [2-8](#)

Personal Information Table (PIT) Activity Report, [3-77](#)

Positive Balance File (PBF), [2-8](#)

Positive Balance File (PBF) Activity Report, [3-82](#)

R

Reject reports, [3-101](#)

Report program
 data masking, [3-7](#)
 errors, [3-7](#)
 file usage, [3-4](#)
 output locations, [3-6](#)

Report types, [3-4](#)

Reporting, [1-11](#)

Reports, processing, [2-13](#)

Response codes
 description, [1-10](#)
 list, [4-2](#)

S

Starting the report program, [3-4](#)

Stop Payment File (SPF), [2-9](#)

Stop Payment File (SPF) Activity Report, [3-93](#)

Store-and-Forward File (SAF), [1-4](#)

Super Extract process, [1-6](#)

U

Update Log File (ULF)
 processing usage, [2-9](#)
 reporting usage, [3-4](#)

Update processing
 add request, [2-34](#)
 change request, [2-38](#)
 delete request, [2-36](#)
 increment request, [2-40](#)
 inquiry request, [2-37](#)

Update response messages, [2-41](#)

W

Warmboot, [2-19](#)

Warning/Hold/Float File (WHFF), [2-9](#)

Warning/Hold/Float File (WHFF) Activity Report, [3-97](#)

X

XPNET process, role, [2-11](#)