



BASE24 Release 6.0
Canadian Users
Conversion Implementation Guide

© 2004 by ACI Worldwide (Canada) Inc.

All rights reserved. All information contained in this document is confidential and proprietary to ACI Worldwide Inc. This material is a trade secret and its confidentiality is strictly maintained. Use of any copyright notice does not imply unrestricted or public access to these materials. No part of this document may be photocopied, electronically transferred, modified, or reproduced in any manner without the prior written consent from:

ACI Worldwide (Canada) Inc.
200 Wellington Street South, Suite 700
Toronto, Ontario M5V 3C7
(416) 813-3000

BASE24, BASE24-atm, BASE24-atm non-currency dispense, BASE24-atm self-service banking, BASE24-billpay, BASE24-from host maintenance, BASE24-pos, BASE24 Remote Banking, BASE24-telebanking, BASE24-teller, BASE24 Visa Cash, BASE24-frequent shopper, XPNET, and Enguard are trademarks or registered trademarks of ACI Worldwide Inc., or its subsidiaries.

Tandem is a trademark or registered trademark of HP Computer Corporation in the United States and/or other countries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Table of Contents

Preface.....	5
Document Control	5
Related Documents	5
Section 1	6
Release 6.0 Introduction	6
File Conversions	6
Section 2	8
BASE24 Base Release 6.0	8
Cardholders Authorization File (CAF)	8
Extract Configuration File (ECF)	9
Institution Definition File (IDF)	9
Security File (SEC)	10
User/Product File Relation file (UPFR).....	11
Usage Accumulation File (UAF)	11
Section 3	12
BASE24-pos Release 6.0	12
BASE24-pos Terminal Data files (PTD)	12
ACI Standard Device Configuration File (ACNF)	13
Response Code Description File (RCDF).....	13
PATHCONF Changes.....	14
Section 4	15
BASE24 Interchange Interfaces Release 6.0	15
Key File (KEYF).....	15
Section 5	17
Logical Network Configuration File Changes	17
Section 6	18
Helpful Hints	18

Preface

Document Control

Version 1.0 (S. Fernández) - 01/2004 Initial Version

Related Documents

- BASE24 Release 6.0 Implementation Guide
- BASE24 Release 6.0 Version 3 Implementation Guide
- Release 6.0 Data File Impacts, BA60UC04.AAREADME
- Release 6.0 Data File Impacts, PS60UC04.AAREADME
- BASE24-pos Files Maintenance Manual
- BASE24 Base Files Maintenance Manual

Section 1

Release 6.0 Introduction

This document describes the conversion programs required by Canadian Customers to move to Release 6.0. This document must be used in conjunction with the BASE24 Release 6.0 Implementation Guide.

The Canadian AIL code is included in BASE24 Release 6.0 version 4 or above and Transaction Security Services (TSS) version 3.3 or above.

The **BASE24 Release 6.0 Implementation Guide** is the primary reference document for information needed to upgrade existing BASE24 Release 5.3 to BASE24 6.0 Version 1 or Version 2.

The **BASE24 Release 6.0 Version 3 Implementation Guide** is the primary reference document for information needed to upgrade existing BASE24 Release 6.0 Version 2 systems to BASE24 Release 6.0 Version 3.

File Conversions

Certain files require conversion in order to implement release 6.0 changes or enhancements.

The conversion method is the traditional method that has always been used.

The input file (existing file) and output file (converted/initialized file) are two different files.

The conversion program:

- Reads the records from the input file
- Adds new fields
- Initializes the appropriate fields
- Writes the record to the output file.

This method is required when changing the structure of a file (e.g., increasing the record length, adding/deleting fields from segments, reorganizing fields within the record structure, etc.). This method can also be used to initialize existing user fields in a record.

This method requires system down time to convert the file (also requires an operator to manually rename the files that have been converted), move in the new objects of modules that access the file (e.g., device handler, auth, etc.) and then restart the objects.

This method impacts all BASE24 customers who use the file being converted even if they are not taking advantage of the enhancement for which the modifications are being made.

The conversion programs for Canadian Users are located in the CD60UC04 sub-volume.

The naming convention for the conversion files contained in the conversion sub-volume is:

- FIL <file name> E: External file
- FIL <file name> M: Make file
- FIL <file name> O: Object file
- FIL <file name> R: Run file
- FIL <file name> S: Source file

Note: All the Canadian conversion files start with FIL.

Section 2

BASE24 Base Release 6.0

This section describes the conversion programs required by Canadian customers to convert Base files to BASE24 6.0 when upgrading from release 5.3 to release 6.0.

File Conversions

Identifies the files that need to be converted in order to implement a given release 6.0 change or enhancement. This implies that a given file could be impacted by multiple changes and/or enhancements. BASE24 users need to consider all of the impacts to any one specific file before the actual conversion of a file.

The following is a list of all the base files that need to be converted using Canadian specific conversion programs:

- CAF
- ECF
- IDF
- SEC
- UPFR
- UAF

Cardholders Authorization File (CAF)

The CAF conversion program must be run to convert CAF records from the release 5.3 format to the release 6.0 format. Users must create the CAF file using the BADDLFUP file.

The CAF conversion program on the CD60UC04 subvolume can be used to convert the CAF. If modifications to the conversion program are necessary, the program can be modified by editing the FILCAFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#cafcnv.t,name $cafm,nowait/  
filcafm -force -list -listreplace
```

Users must update the FILCAFR obey file on the CD60UC04 subvolume with the appropriate information. FILCAFR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

Note: Even though a CAF conversion program is provided in release 6.0, it is recommended that BASE24 users convert the CAF using the Refresh process.

Extract Configuration File (ECF)

The ECF conversion program must be run to convert ECF records from the release 5.3 format to the release 6.0 format (i.e., the latest version of release 6.0). Running the conversion program is required for all users, not just those that are using the Format 2 File Support enhancement. Users must create the ECF file using the BADDLFUP file.

The ECF conversion program on the CD60UC04 subvolume can be used to convert the ECF. If modifications to the conversion program are necessary, the program can be modified by editing the FILECFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#ecfcnv.t,name $ecfm,nowait/  
filecfm -force -list -listreplace
```

Users must update the FILECFR obey file on the CD60UC04 subvolume with the appropriate information. FILECFR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

Release 6.0 Version 1 to Release 6.0 Version 2 Consideration:

For more information on release 6.0 version 2, refer to ***BAS24 Release 6.0 Implementation Guide***.

Institution Definition File (IDF)

The IDF conversion program must be run to convert IDF records from the release 5.3 format to the release 6.0 format. A new field titled IDF.IDFBASE.FIID-SEG-MAP-EXT has been added to the IDF file for this enhancement. The addition of

the field IDF.IDFBASE.FIID-SEG-MAP-EXT allows individual institutions to support up to 256 segments. The Conversion Program also zero fills field IDF.IDFBASE.BASE-SEG.SEG-MAP. This initialization puts the IDF file under the new segmentation scheme.

The IDF conversion program on the CD60UC04 subvolume can be used to convert the IDF. If modifications to the conversion program are necessary, the program can be modified by editing the FILIDFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#idfcnv.t,name $idfm,nowait/  
filidfm -force -list -listreplace
```

Users must update the FILIDFR obey file on the CD60UC04 subvolume with the appropriate information. FILIDFR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

Security File (SEC)

The SEC File Conversion Program is needed for two purposes. One purpose pertains to the fact that the Product Indicator field of the SEC Base record has been increased from 32 product indicator entries to 256 product indicator entries. The second function is to clean up old products and segments in the Security file. Some products have been consolidated and others removed. The Conversion Program will remove all SEC screen access records that no longer correspond to products found in the PITABLE.

The SEC conversion program on the CD60UC04 subvolume can be used to convert the SEC. If modifications to the conversion program are necessary, the program can be modified by editing the FILSECS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#filsec.t,name $secm,nowait/  
filsecm -force -list -listreplace
```

Users must update the FILSECR obey file on the CD60UC04 subvolume with the appropriate information. FILSECR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

User/Product File Relation file (UPFR)

The UPFR conversion program is required because certain products were consolidated and unsupported files must be removed from the UPFR.

The UPFR conversion program on the CD60UC04 subvolume can be used to convert the UPFR. If modifications to the conversion program are necessary, the program can be modified by editing the FILUPFRS file.

Note: The UPFR File Conversion must be run after the SEC File Conversion.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#upfrcnv.t,name $upfrm,nowait/  
filupfrm -force -list -listreplace
```

Users must update the FILUPFRR obey file on the CD60UC04 subvolume with the appropriate information. FILUPFRR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

Usage Accumulation File (UAF)

The UAF conversion program must be run to convert UAF records from the release 5.3 format to the release 6.0 format. Users must create the UAF file using the BADDLFUP file.

The UAF conversion program on the CD60UC04 subvolume can be used to convert the UAF. If modifications to the conversion program are necessary, the program can be modified by editing the FILUAFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#uafcncv.t,name $uafm,nowait/  
filuafm -force -list -listreplace
```

Users must update the FILUAFR obey file on the CD60UC04 subvolume with the appropriate information. FILUAFR must then be obeyed to execute the conversion program.

Section 3

BASE24-pos Release 6.0

This section describes the conversion programs required by Canadian customers to convert POS files to BASE24 6.0 when upgrading from release 5.3 to release 6.0.

File Conversions

Identifies the files that need to be converted in order to implement a given release 6.0 change or enhancement. This implies that a given file could be impacted by multiple changes and/or enhancements. BASE24 users need to consider all of the impacts to any one specific file before the actual conversion of a file.

The following is a list of all the pos files that need to be converted for Canadian BASE24 users:

- PTD
- ACNF
- RCDF

BASE24-pos Terminal Data files (PTD)

The PTD conversion program must be run to convert PTDF records that exist for the Hypercom devices (i.e., terminal type equals "D0", "D6", "D7", and "D8") and the ASPDH devices (i.e., terminal type equals "41") into the new PTD records. Users must create the PTD files and a new PTDF file using the PSDDLUP file.

The PTD conversion program on the CD60UC04 subvolume can be used to convert the PTDF. If modifications to the conversion program are necessary, the program can be modified by editing the FILPTDS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#ptdcnv.t,name  
$ptdm,nowait/filptdm -force -list -listreplace
```

Users must update the FILPTDR obey file on the CD60UC04 subvolume with the appropriate information. FILPTDR must then be obeyed to execute the conversion program.

For more information on file conversions, refer to the AAREAD04 file on the PS60UC04 subvolume.

ACI Standard Device Configuration File (ACNF)

The ACNF conversion program must be run to convert ACNF records from the release 5.3 format to the release 6.0 format. Users must create the ACNF file using the PSDDLUP file.

The ACNF conversion program on the CD60UC04 subvolume can be used to convert the ACNF. If modifications to the conversion program are necessary, the program can be modified by editing the FILACNFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#uafcncv.t,name $uafm,nowait/  
filuafm -force -list -listreplace
```

Users must update the FILACNFR obey file on the CD60UC04 subvolume with the appropriate information. FILACNFR must then be obeyed to execute the conversion program.

Response Code Description File (RCDF)

The RCDF conversion program must be run to convert AIRS records from the release 5.3 format to the release 6.0 format. Users must create the RCDF file using the PSDDLUP file.

The Response Code Description File (RCDF) replaces the ACI Standard Device Handler ISO Response File (AIRS). For more information about RCDF file refer to the ***BASE24-pos Files Maintenance Manual***.

The RCDF conversion program on the CD60UC04 subvolume can be used to convert the AIRS. If modifications to the conversion program are necessary, the program can be modified by editing the FILRCDFS file.

To compile the conversion program, enter at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#rcdfcncv.t,name $rcdfm,nowait/  
filrcdfm -force -list -listreplace
```

Users must update the FILRCDFR obey file on the CD60UC04 subvolume with the appropriate information. FILRCDFR must then be obeyed to execute the conversion program.

PATHCONF Changes

Delete the AIRS Server (i.e., SERVER-AIRS) from the PATHCONF file. Note that this server was needed in the previous releases of BASE24-pos). The AIRS Server can be deleted online through the PATHCOM utility, but it must also be deleted from the PATHCONF, so that any future PATHCOLD operation would not contain the AIRS Server.

The RCDF Server object is bound into the Classic Combined AFM Link Object (CCAFMLO).

Section 4

BASE24 Interchange Interfaces Release 6.0

This section describes the conversion programs required by Canadian customers to convert Interchange Interface files to BASE24 6.0 when upgrading from Fortify 5.3 to switch release 6.0.

File Conversions

Identifies the files that need to be converted in order to implement a given release 6.0 change or enhancement. This implies that a given file could be impacted by multiple changes and/or enhancements. BASE24 users need to consider all of the impacts to any one specific file before the actual conversion of a file.

The following is a list of all the files that need to be converted for Canadian BASE24 users:

- KEYF

Key File (KEYF)

The KEYF conversion program can be run to create ISECD records while updating KEYF records with key locators that point to the appropriate ISECD records. Running the conversion program is not required. ISECD records can be entered manually using the ACI Desktop Graphical User Interface. Key fields in corresponding KEYF records would have to be updated manually as well.

Notes:

- ***Field MAC ENCRYPT TYPE in all the records of KEYF file should be set to 1 before running the conversion. If it is set to 0 the conversion program doesn't fill the MAC information.***
- Interface Process Name for the IMN (DPC/FIID) will no longer have spaces. The conversion program will eliminate any existing spaces.

The KEYF conversion program is on the CD60UC04 subvolume. If modifications to the conversion program are necessary, the program can be modified by editing the FILKEYFS file.

To compile the conversion program, enter the following command at the TACL prompt:

```
$<volume>.makev500.makev501/out $s.#keyftss.t,name $keyfm,nowait/  
filkeyfm -force -list -listreplace
```

Users must update the FILKEYFR obey file on the CD60UC04 subvolume with the appropriate information. Make sure all parameters in the FILKEYFR obey file are set properly. FILKEYFR must then be obeyed to execute the conversion program.

If both KEYF and KEY6 files are converted, the KEYF conversion must be run first.

For more information on file conversions, refer to the AAREAD04 file on the BA60UC04 subvolume.

Section 5

Logical Network Configuration File Changes

This section describes the conversion programs required by Canadian customers to convert Base files to BASE24 6.0 when upgrading from release 5.3 to release 6.0.

This section describes the Logical Network Configuration File Changes made to the BASE24 release 6.0 that are specific for Canadian BASE24 users when upgrading from 5.3 to version of 6.0.

The following assign needs to be deleted for release 6.0 from LCONF:

POS-SPDH-AIRS — ACI STANDARD DEVICE H. ISO RESPONSE FILE

Refer to ***BASE24 Release 6.0 Version 3 Implementation Guide*** for explanations of how to set the following assigns and params regarding to RCDF new file:

ASSIGNS:

RCDF

RCDFEMT

PARAMS:

RCDFEMT-MAX-TBL-SIZE

RCDFEMT-WARM identifier

Section 6

Helpful Hints

1. You will need to update your standard pitable & cobnames files & change your spdhnams define to point to the Canadian version of the spdhnams file (PS60CDN).
2. The allmacs define should point to the standard custmacs file on ba60make..
3. All of the mlspdh (like the filspdh) code has been integrated into the standard spdh module. This object gets built using the product flags in the custmacs file.
4. The SCNFIL file in BA60UD06 will show all files that have been updated for the POS enhancement (Canadian).
5. There are 3 files in sw60cdn which have been modified for Canadian changes: bnetlibs, bnets & visamsgs.....if you are using these versions then you will have to update the defines in the sw60bnet.bnetmm & sw60visa.visamm files.....these interfaces can then be made thru the standard make stream.....if you are using the standard versions of these files then no define changes are necessary...