

BASE24 Release 6.0 Post Version 10

Migration Implementation Guide



© 2012 by ACI Worldwide, Inc. All rights reserved.

All information contained in this documentation, as well as the software described in it, is confidential and proprietary to ACI Worldwide, Inc., or one of its subsidiaries, is subject to a license agreement, and may be used or copied only in accordance with the terms of such license. Except as permitted by such license, no part of this documentation may be reproduced, stored in a retrieval system, or transmitted in any form or by electronic, mechanical, recording, or any other means, without the prior written permission of ACI Worldwide, Inc., or one of its subsidiaries.

ACI, ACI Worldwide, and the ACI product names used in this documentation are trademarks or registered trademarks of ACI Worldwide, Inc., or one of its subsidiaries.

Other companies' trademarks, service marks, or registered trademarks and service marks are trademarks, service marks, or registered trademarks and service marks of their respective companies.

Contents

Preface	iv
Document Control	iv
1: Introduction	1-5
Implementation Planning	1-6
Software Requirements	1-8
Conversion Planning	1-9
Conversion Program Guidelines	1-10
Other Documents	1-13
Definition of Terminology	1-16
Standard Information Format	1-21
2: Support Services	2-1
Product Consulting and Project Management	2-2
Project Planning Guide	2-3
Publications	2-9
Education	2-10
HELP24	2-11
ASTech Services	2-12
3: BASE24 Networks First Modifications	3-1
4: BASE24 Migration Modifications	4-1
5: BASE24 Networks First Visa FRLF Modifications	5-1

Preface

Document Control

A description of the document revisions is shown below. Any changes of text from one document version to another are indicated with the symbol “|” in the outside margin.

BASE24 Release 6.0 Post Version 10 for Migration (J. Wishart)
– Dec-2011

Addition of BASE24 Networks First Visa FRLF Modifications, (J. Wishart)
- Mar- 2012

1: Introduction

The ***BASE24 Release 6.0 Post Version 10 Migration Implementation Guide*** is the primary reference document for information needed to upgrade existing BASE24 Release 6.0 Version 10 systems to include any modifications necessary for the migration of a BASE24 system to BASE24-eps.

Note that this guide is intended to cover the installation of the software modifications needed for the BASE24 side of a BASE24/BASE24-eps migration system. It also includes the configuration changes necessary on BASE24 for the use of those software modifications once those modifications are installed. It does not cover details of the BASE24-eps side of the migration system, nor does it cover the data conversions that are necessary to build the BASE24-eps database from the existing BASE24 data. Similarly, it does not include details of how to migrate interfaces, devices, device handlers or other functions from BASE24 to BASE24-eps.

As no more releases of BASE24 are available after BASE24 Release 6.0 Version 10, customers may need to implement any modifications on an individual basis. For this reason, this Implementation Guide is in a different format to previous BASE24 Implementation Guides.

This section provides an overview of the planning requirements for BASE24 users wishing to include modifications for migration in BASE24 Release 6.0 Post Version 10. It also provides guidance for using this manual.

Also included in this section is a listing of other documents that a BASE24 user should obtain for implementation planning, the general software requirements for BASE24 Release 6.0 Post Version 10 for Migration, and a glossary of terms used throughout the guide.

Implementation Planning

BASE24 users must develop their own project plans for upgrading their BASE24 systems to Release 6.0 Post Version 10 and including modifications for migration. Project plans should address such issues as staffing and training requirements, host external message changes, device programming enhancements, hardware and software requirements, database configuration changes, data conversions and the upgrade method to be used.

ACI has provided BASE24 users with the ***BASE24 Release 6.0 Post Version 10 Migration Implementation Guide*** to assist in preparing project plans. This guide includes a list of services available to the BASE24 user and information that existing BASE24 users will need to upgrade to Release 6.0 Post Version 10 for Migration.

BASE24 Release 6.0 products include the following:

- ☐ BASE24-atm
- ☐ BASE24-pos
- ☐ BASE24-teller
- ☐ BASE24-remote banking
- ☐ BASE24 Interchange Interfaces
- ☐ BASE24 Value-Added Products:
 - o BASE24-card
 - o BASE24-customer service
 - o BASE24-infoBase
 - o BASE24-inventory

Who should use this guide?

There are two audiences for this guide: those who plan and manage the upgrade process and those who implement the upgrade to BASE24 Release 6.0 Post Version 10 for Migration. In either case, the reader should be experienced with BASE24 software, HP NSK products, and the user's current BASE24 configuration. This guide is not directed at new BASE24 users who will be installing a BASE24 application for the first time. New users should refer to the formal BASE24 publications listed under the Publications heading in Section 2.

To upgrade to BASE24 Release 6.0 Post Version 10 for Migration, users must be on BASE24 Release 6.0 Version 10. Refer to the ***BASE24 Release 6.0 Version 10 Implementation Guide*** to assist in planning the tasks necessary to upgrade to BASE24 Release 6.0 Version 10.

Using this guide, you can do the following:

- ☐ Determine what ACI services are available to assist in the upgrade to BASE24 Release 6.0 Post Version 10 for Migration.
- ☐ Develop a project plan to upgrade to BASE24 Release 6.0 Post Version 10 for Migration.
- ☐ Determine staffing and training needs.
- ☐ Gain a detailed understanding of the BASE24 Release 6.0 Post Version 10 for Migration.

Software Requirements

HP NSK Software Requirements

ACI recommends that the BASE24 user be on a current HP NSK-supported operating system to obtain maximum performance and support. However, BASE24 Release 6.0 is currently compatible with the HP NSK Guardian D45 Operating System. Customers choosing to implement Format 2 File support are required to be on a minimum Operating System level of D46.

XPNET

ACI requires that the BASE24 user be on an XPNET 3.0 or 3.1 system.

FIX

FIX 2.28 (or newer) is required to apply any new BASE24 fix files produced after 19 October 2006. FIX 2.28, like the previous version of FIX, will allow application of fix files to a specified file name in a concatenated list of fix files. This option can be combined with the FIRSTSCN and LASTSCN options to apply only fixes to the specified file name in a specified SCN range. As of 19 October 2006, FIX 2.28 (or the most current version of FIX) was automatically shipped with each software order. Please replace your existing FIX object with the most current version.

Conversion Planning

BASE24 users must develop their own project plans for upgrading their systems to BASE24 Release 6.0 Post Version 10 for Migration. Project plans should address such issues as staffing and training requirements, host external message changes, device programming enhancements, hardware and software requirements, database configuration changes, data conversions and the upgrade method to be used.

In general, all changes for BASE24 Release 6.0 Post Version 10 for Migration can be obtained by requesting the latest fixes from ACI and then retrofitting all fixes to the user's BASE24 Release 6.0 Version 10 modules.

Conversion Program Guidelines

Users of previous releases of BASE24 and previous versions of BASE24 Release 6.0 must run file conversion programs in order to migrate to the latest version of Release 6.0. Information about specific conversion programs can be found in subsequent sections of this document under the applicable enhancements. Following are general conversion program guidelines.

The *UC04 subvolumes (e.g., AT60UC04, BA60UC04, PS60UC04) contain the conversion programs for users migrating from BASE24 Release 5.3 to the latest version of BASE24 Release 6.0. The conversion programs on these subvolumes are kept up-to-date with each new version of BASE24 Release 6.0.

The *UC05 subvolumes (e.g., AT60UC05, BA60UC05, PS60UC05) contain the conversion programs for users migrating from Release 6.0 Version 1 to Release 6.0 Version 2. Also residing on these subvolumes are the Transaction Security Services (TSS) conversion programs, which are used to move key data to the new TSS database. The TSS conversion programs are required only if the user is implementing TSS.

The *UC06 subvolumes (e.g., AT60UC06, BA60UC06, PS60UC06) contain the conversion program for users migrating from Release 6.0 Version 2 to Release 6.0 Version 3. No changes are made to these programs other than necessary fixes.

The *UC07 subvolumes (e.g., AT60UC07, BA60UC07, PS60UC07) contain the conversion program for users migrating from Release 6.0 Version 3 to Release 6.0 Version 4. No changes are made to these programs other than necessary fixes.

The *UC08 subvolumes (e.g., AT60UC08, BA60UC08, PS60UC08) contain the conversion program for users migrating from Release 6.0 Version 4 to Release 6.0 Version 5. No changes are made to these programs other than necessary fixes.

The *UC09 subvolumes (e.g., AT60UC09, BA60UC09, PS60UC09) contain the conversion program for users migrating from Release 6.0 Version 5 to Release 6.0 Version 6. No changes are made to these programs other than necessary fixes.

The *UC0A subvolumes (e.g., AT60UC0A, BA60UC0A, PS60UC0A) contain the conversion program for users migrating from Release 6.0 Version 6 to Release 6.0 Version 7. No changes are made to these programs other than necessary fixes.

The *UC0B subvolumes (e.g., AT60UC0B, BA60UC0B, PS60UC0B) contain the conversion program for users migrating from Release 6.0 Version 7 to Release 6.0 Version 8. No changes are made to these programs other than necessary fixes.

The *UC0C subvolumes (e.g., AT60UC0C, BA60UC0C, PS60UC0C) contain the conversion program for users migrating from Release 6.0 Version 8 to Release 6.0 Version 9. No changes are made to these programs other than necessary fixes.

The *UC0D subvolumes (e.g., AT60UC0D, BA60UC0D, PS60UC0D) contain the conversion program for users migrating from Release 6.0 Version 9 to Release 6.0 Version 10. No changes are made to these programs other than necessary fixes.

The *UC0E subvolumes (e.g., AT60UC0E, BA60UC0E, PS60UC0E) would contain any conversion programs for users upgrading from Release 6.0 Version 10 to Release 6.0 Post Version 10 mandates and modifications from 2010. No such conversion programs are needed.

The *UC0F subvolumes (e.g., AT60UC0F, BA60UC0F, PS60UC0F) contain the conversion program for users upgrading from Release 6.0 Version 10 to Release 6.0 Post Version 10 mandates and modifications from 2011. No changes are made to these programs other than necessary fixes.

If a Release 5.3 user wants to convert to the latest Version of Release 6.0, the conversion programs on *UC04 should be run. If the user is implementing TSS, the TSS-specific conversion programs on *UC05 should also be run.

If a Release 6.0 Version 1 user wants to convert to Release 6.0 Version 2, the conversion programs on *UC05 should be run.

If a Release 6.0 Version 2 user wants to convert to Release 6.0 Version 3, the conversion programs on *UC06 should be run.

If a Release 6.0 Version 3 user wants to convert to Release 6.0 Version 4, the conversion programs on *UC07 should be run.

If a Release 6.0 Version 4 user wants to convert to Release 6.0 Version 5, the conversion programs on *UC08 should be run.

If a Release 6.0 Version 5 user wants to convert to Release 6.0 Version 6, the conversion programs on *UC09 should be run.

If a Release 6.0 Version 6 user wants to convert to Release 6.0 Version 7, the conversion programs on *UC0A should be run.

If a Release 6.0 Version 7 user wants to convert to Release 6.0 Version 8, the conversion programs on *UC0B should be run.

If a Release 6.0 Version 8 user wants to convert to Release 6.0 Version 9, the conversion programs on *UC0C should be run.

If a Release 6.0 Version 9 user wants to convert to Release 6.0 Version 10, the conversion programs on *UC0D should be run.

If a Release 6.0 Version 10 user wants to upgrade to Release 6.0 Post Version 10 mandates and modifications from 2010, the conversion programs on *UC0E should be run.

If a Release 6.0 Version 10 user wants to upgrade to Release 6.0 Post Version 10 mandates and modifications from 2011, the conversion programs on *UC0F should be run.

If a Release 6.0 user wants to convert from Version 1 to Version Post 10 mandates or modifications from 2011, multiple conversion programs must be run starting with *UC05. If the user is implementing TSS, the TSS-specific conversion programs on *UC05 should also be run. Following this, the user needs to run the conversion programs on *UC06, *UC07, *UC08, *UC09, *UC0A, *UC0B, *UC0C, *UC0D and UC0E. Finally, the user should run the conversion programs on *UC0F.

Customers who are migrating from BASE24 to BASE24-eps will need to execute the Migration conversion programs to convert their data from BASE24 Release 6.0 Version 10 to BASE24-eps Version 09.2. Please refer to the BASE24 to BASE24-eps Migration Conversion Program Guide on InfoLink for more details.

Other Documents

In addition to this guide, the reader can obtain other BASE24 and NET24-XPNET publications that cover operational and product-specific information required to fully understand and implement the BASE24 Release 6.0 Version Post 10 software. Such manuals include the formal publications mentioned under the Publications heading in Section 2, the event message documentation located on the BA60LOGM and OK60LOGM subvolumes, and the following documents:

BASE24 6.0 Installation Guide (Informal) - BA-AE000-55

A primary reference document for information about the installation of a BASE24 Release 6.0 system from scratch. This document is available on InfoLink.

The BASE24 6.0 Installation Guide is also provided with the software, located on the BA60UD04 subvolume as a file called BASE24. On this subvolume there is also a readme file called AAREAD04, which details how to move the Installation Guide to your hard drive and open it with Microsoft Word.

BASE24 Release 6.0 Interchange Interface Implementation Guide (Informal) - SW-DS0000-60

Describes the function and purpose of ACI's Release 6.0 Switch Interfaces. It explains how customers can implement Release 6.0 Switch Interfaces in their existing networks as well as in a BASE24 Release 6.0 network. It also explains how customers can implement their Fortify.1/Fortify.3 Interfaces in a Release 6.0 network. This document is intended to assist customers in configuring and controlling their Release 6.0 Switch Interchange Interfaces in all BASE24 release networks and their Fortify.1/Fortify.3 Interchange Interfaces in a BASE24 Release 6.0 network. This document is included as a Microsoft Word document and is shipped with the Release 6.0 Interchange Interface software. This document is named NSTLSW60 and is located on the SW60UD04 subvolume.

Note: This guide is to be used with BASE24 releases 4.0, 5.0, 5.1.2, 5.3, and 6.0.

Release 6.0 Data File Impacts Document (Informal)

A primary reference document for information about the data file impacts and the methods that can be used to upgrade to BASE24 Release 6.0 Post Version 10 mandates and modifications. This document is included as a HP NSK TGAL document and is shipped with the BASE24 Release 6.0 Post Version 10 mandates and modifications software. This document is named AAREAD0F and is located on the BA60UC0F subvolume.

BASE24 to BASE24-eps Migration Conversion Program Guide - BA-UT050-01

A primary reference document for information needed to convert data from the existing BASE24 Release 6.0 Version 10 systems to BASE24-eps Version 09.2, SP2.

BASE24-eps Networks First Implementation Guide (Informal)

Contains implementation guidelines for the Networks First program. It is intended for use by customers and ACI personnel involved in implementing Networks First at a customer site – where both BASE24 and BASE24-eps are installed on an HP NonStop platform.

In addition, please refer to the InfoLink BASE24 to BASE24 Migration section, which contains other information that may be useful for customers planning their BASE24 to BASE24-eps migration.

HELP24 and HELP24 InfoLink

HELP24 and HELP24 InfoLink are excellent sources of assistance and information. The following access options appear on the support page of the ACI Worldwide Inc. Internet website (<http://www.aciworldwide.com/support>).

- ☐ A current listing of HELP24 phones worldwide.
- ☐ An option to send an e-mail message to HELP24.
- ☐ An option to sign up for HELP24 InfoLink.
- ☐ An option to access HELP24 InfoLink once you have received a user ID and password.

Once you can log on to HELP24 InfoLink, you can do the following:

- ☐ Access the HELP24 database to open a new case.
- ☐ Access installation and fix release procedures online.
- ☐ Access all BASE24, BASE24-eps, and NET24-XPNET documentation online.
- ☐ Search the site for information about BASE24.

The **HELP24 eSupport Users Guide** contains procedures for opening a new case, accessing the database, and accessing documentation on-line. Once you log on to HELP24, the path to the **HELP24 eSupport Users Guide** is as follows:

Support Center > InfoLink > HELP24 eSupport Users Guide.

Once you log on to HELP24, the path to the installation procedures is as follows:

Support Center > InfoLink > Product Info > BASE24 > BASE24 6.0 Install Info and Guides.

The menu displayed gives you three options:

- ☐ Pre-Install Checklists - for BASE24 Release 6.0 and ITS
- ☐ Install Guides - Procedures for installing a software release or version for the first time.
- ☐ Retail Install Guides - Procedures for installing Retail 3.1 or Check Auth 3.2.

Once you log on to HELP24, the path to the Fix Information is:

Support Center > InfoLink > Fix Information > BASE24

Definition of Terminology

The following list has been defined to assist the reader in understanding the terms referred to within this document.

6.0 Interchange Interfaces

The BASE24 Interchange Interfaces developed in conjunction with BASE24 Release 6.0. These replace the Fortify.3 Interchange Interfaces and can be used with releases 4.0, 5.0, 5.1, 5.1.2, 5.3 and 6.0 of BASE24.

Accountholder

A person for whom a financial account has been established for some purpose. Accountholders may or may not use cards to initiate transactions on their accounts.

BASE24 User

An entity that has licensed BASE24 software products.

Bridge

A copy of the BASE24 HISO module that is used to communicate with BASE24-eps in a migration system is referred to as a bridge, or bridge process. Software modifications have been made to the BASE24 HISO code to facilitate HISO being used as a bridge process. These modifications to the code are only accessed at run time if the LCONF param MIGR-HISO-ENABLE is true for this particular HISO process. This term, and the term 'Migration HISO' can be used interchangeably.

Cardholder

A person who has been issued a plastic card for the purpose of initiating transactions.

Consumer

A person who utilizes services offered by a BASE24 user who may or may not require a plastic card.

Conversion Program

A utility within existing code that reads the records from an input file, adds new fields and initializes appropriate fields and then writes the record to an output file. The input file (existing file) and output file (converted/initialized file) are different files. This method (versus the initialization program and online conversion) is required when the record structure changes (e.g., increasing the record length, adding/deleting fields

from segments, etc.). This method can also be used to initialize existing user fields in a record.

This method requires system down time to convert the file. It also requires an operator to manually rename the file that has been converted, move in the new objects of modules that access the file (e.g., device handler, auth, etc.) and then restart the objects. This method impacts all BASE24 users who use the file being converted even if they are not taking advantage of the enhancement for which the modifications are being made.

Dummy Procedures

When bindable enhancement extensions are used in BASE24 product code, a dummy procedure exists in a dummy file on the main code subvolume, for each of the new procedures defined in the extension subvolume. This dummy procedure is executed if the bindable extension is NOT bound into this copy of the executable. Typically this dummy procedure returns without performing any functionality. The dump file is named with a 'D' at the end of the filename. For example, the ATM Authorization Dummy File is AUTHD and is present on the AT60AUTH subvolume.

Extended Memory Table file (EMT)

A data file produced by the EMT Build utility program. Once the EMT has been built with the EMT Build utility, processes that use the EMT must be warmbooted (or started if not running).

Extended Memory Table Build utility (EMT Build)

The EMT Build utility is a stand-alone program used to build tables in extended memory from information contained in disk files. This utility can build hash tables, radix tables, or custom designed tables. Refer to the **BASE24-atm Transaction Processing Manual**, **BASE24-pos Transaction Processing Manual**, or the **BASE24 ITS Kernel Configuration Manual** for additional information about this utility.

Extensions

Separate subvolumes are sometimes created as enhancements are added to the BASE24 product family. Placing bindable enhancement source code on separate subvolumes gives customers the option of not introducing the unwanted or unused functionality into their executable objects. These bindable enhancement extensions also allow ACI the ability to deliver these enhancement subvolumes (add-on modules) in a controlled manner as well as a billable option.

Hooks

When bindable enhancement extensions are used in BASE24 product code, the call in the main code module to the new extension procedure is known as a hook.

LCONF

The Logical Network Configuration File (LCONF) is the central location of file information and processing information for BASE24, and for this reason, it is one of the main components of every BASE24 logical network. One LCONF exists for each logical network. The records in LCONFs are classified as either assigns or params.

Make

The ACI Make utility configures and compiles ACI software. ACI implemented this utility to enable our customers, as well as our own developers, to maintain our software more effectively. ACI software includes hundreds of source files that must be compiled in a specific order to create the desired object files. The ACI Make utility automates this process, ensuring that object files are created in the correct order with all the necessary information. This utility also saves time and resources by automating the work of compiling, binding, moving, and securing object code.

Migration HISO

A copy of the BASE24 HISO module that is used to communicate with BASE24-eps in a migration system is referred to as a Migration HISO. Software modifications have been made to the BASE24 HISO code to facilitate HISO being used as a Migration HISO process. These modifications to the code are only accessed at run time if the LCONF param MIGR-HISO-ENABLE is true for this particular HISO process. This term, and the term 'bridge' can be used interchangeably.

Online (Inline) Conversion

A software routine within existing code that reads and updates each record in a file to initialize user fields that have been redefined as new fields for use by an enhancement. The file is converted in place (i.e., a new file is not created). The record is read, updated and then rewritten to the same file. This method (versus the conversion program) cannot be used when the record structure changes (e.g., increasing the record length, adding/deleting fields from segments, etc.).

The online conversion code will be executed each time a record is accessed (versus the conversion and initialization programs that are run once). When a record is read, the process will determine if the value of a new field is valid. If the value is not valid, the field will be initialized to the default value. The database is gradually converted as records are read and updated.

This method requires an operator to stop a process, roll in the new object and start processes that use the files that are impacted. This method does not require any

additional steps to be performed by an operator (e.g., running conversion/initialization programs, renaming files).

Operator

A person who carries out network operations functions, such as starting and stopping the system, entering ONCF commands, controlling logging, dealing with event messages, performing refreshes and extracts. The term *operator* also can refer to persons using BASE24 screens for such purposes as file maintenance, perusal, etc.

ACI Worldwide Inc

Standard Information Format

A standard format is used in Sections 3 and beyond to highlight and describe the various changes, conversion requirements, and implementation requirements BASE24 users need to consider when upgrading to BASE24 Release 6.0 Post Version 10 for Migration. This standard format is defined below.

In situations where the following information does not apply, the information is labeled as “Not applicable”

Prerequisites

Describes the software modules that must be licensed in order for this modification to be implemented.

Software Impacts

Describes the software modules impacted for a given modification and the nature of the impacts. This information includes a high level list of the modules impacted, how the modules are impacted (i.e., inline changes, hooks, dummy procs, extensions) and which customers are affected (i.e., all, or only those implementing the mandate or modification).

CUSTMACS Changes

Describes CUSTMACS changes required to implement a given modification. This information includes Make defines that have been added, deleted, or modified.

LCONF Assign Changes

Describes LCONF assign changes required to implement a given modification. This information includes assigns that have been added, deleted, or modified, along with an explanation of how these assigns can or must be set.

LCONF Param Changes

Describes LCONF param changes required to implement a given modification. This information includes params that have been added, deleted, or modified, along with an explanation of how these params can or must be set.

Database Configuration

Describes data file changes required to implement a given modification. This information includes file fields that have been added, deleted, or modified, along with an explanation of how these fields can or must be set. It also identifies file records and record segments that must be added, deleted, or modified.

New Data Files

Identifies new data files that must be created in order to implement a given modification.

Template Changes

Identifies file templates that must be created or modified in order to implement a given modification. It also identifies COBNAMEs and Device Handler Names (xxxxNAMS) file modifications that must be made.

Device Configuration

Identifies device configuration changes that are required in order to implement a given modification.

Mega Table (MEGATBL) Changes

Identifies Mega Table changes that are required in order to implement a given modification.

PI-Table Changes

Identifies Product Indicator (PI) Table changes that are required in order to implement a given modification.

SEG-Table Changes

Identifies Segment Indicator (SEG) Table changes that are required in order to implement a given modification.

Security Table (SECTBL) Changes

Identifies Security Table changes that are required in order to implement a given modification.

PATHCONF Changes

Identifies PATHCONF changes that are required in order to implement a given modification.

CRT Access Security Changes

Identifies CRT Access security changes that are required in order to implement a given modification. This includes changes that need to be made to BASE24 operator security records.

Routing Changes

Identifies routing and configuration changes that are required in order to implement a given modification. This includes required changes to files such as SPROUTE and the BASE24-pos Authorization Selection Table (AST).

Network Configuration

Identifies XPNET configuration changes that are required in order to implement a given modification. This includes NEF changes.

File Conversions

Identifies files that need to be converted in order to implement a given modification. This implies that a given file could be impacted by multiple mandates and/ or modifications. BASE24 users need to consider all of the impacts to any one specific file before the actual conversion of a file.

Host/Co-Network Impacts

Identifies impacts to a user's host or co-network as a result of a given modification. This includes changes to the external messages used to communicate with hosts and co-networks as well as changes to refresh and extract formats.

User/Operational Impacts

Identifies potential changes to a user's internal BASE24 operating procedures. This includes changes to operations and file maintenance screens, operator-initiated commands, and reports.

Vendor Impacts

Identifies any issues that need to be addressed with vendors in order to implement a given modification. This includes hardware, firmware, and software changes that vendors need to make in order for their products to function with the given modification.

Reference Documents

Lists any outside sources used in the design of a given modification. BASE24 users can refer to these documents for additional information.

ACI Worldwide Inc

2: Support Services

This section summarizes the various support services available from ACI. These support services are described as follows:

- ☐ Product consulting and project management
- ☐ Publications
- ☐ Education
- ☐ HELP24
- ☐ ASTech services

Other services, besides the traditional Installation service, such as go-live support, onsite conversion assistance, and software methodology and utility training are available or are being planned. Please contact your ACI Customer Manager for more details of the services ACI can offer.

.

Product Consulting and Project Management

No formal service programs have been created by ACI for upgrading customers to BASE24 Release 6.0 Post Version 10 for Migration. Customers need to review this entire document and any referenced manuals, to determine what they will need to do to upgrade their BASE24 system.

After reviewing all materials, customers should contact their ACI Customer Manager to discuss any services, such as project management, custom code upgrades, onsite staff, etc., required for upgrading.

Project Planning Guide

The following Project Planning Guide is designed to assist in the successful upgrade of a BASE24 system to BASE24 Release 6.0 Post Version 10 for Migration. Information contained in this guide provides insight into required planning and control of the entire project.

Following this project guide helps ensure the realization of the goals and business objectives of the BASE24 user.

1. IDENTIFY PROJECT TEAM

One of the initial tasks for the BASE24 upgrade is for the user to assign a project team who will be responsible for the success of the project. A project manager and team members will need to be assigned and specific responsibilities established.

2. DETERMINE HARDWARE REQUIREMENTS

An ACI sales representative can assist in determining whether additional hardware will be required for the BASE24 upgrade. It is the BASE24 user's responsibility to order the hardware and establish the delivery date with HP NSK. HP NSK will perform diagnostic testing on the hardware when it is installed at the site. Should hardware encryption be required, it will be necessary to determine the hardware requirements. Additional hardware should be ordered for installation before testing can occur.

If applicable, the BASE24 user should order any new device firmware/software required to implement the enhancements they have chosen to support. The delivery date for the device firmware/software should be agreed upon with the vendor, as this time frame will affect the entire project.

3. IDENTIFY COMMUNICATION REQUIREMENTS

If the BASE24 user has identified additional protocol requirements, the communications lines and modems should be ordered. The customer must coordinate this effort with the local communication company to ensure that the lines are configured in the least costly manner. The lines and modems must be installed and tested prior to the scheduled software installation date.

4. UPDATE HP NSK SOFTWARE REQUIREMENTS

ACI recommends that the BASE24 user be on a current HP NSK supported operating system to obtain maximum performance and support. BASE24 Release 6.0 requires a minimum of HP NSK Guardian D45 Operating System. Customers choosing to implement Format 2 File support are required to be on a minimum Operating System level of D46. In addition, BASE24 Release 6.0 requires TMF for the BASE24-remote banking product. Customers choosing to implement BASE24-eps Transaction Security Services (known as TSS) with BASE24 Release 6.0 must review the BASE24-eps Hardware and Software Requirements for the BASE24-eps release they will deploy.

5. UPGRADE TO XPNET 3.0 or 3.1

Customers should note that XPNET 3.0 is the minimum requirement for BASE24 Release 6.0.

6. PROJECT SCOPE MEETING

ACI does not believe this step is necessary for customers upgrading to BASE24 Release 6.0 Post Version 10 for Migration.

7. MIGRATION PLANNING

Users will need to use this document, and any references within it, for detailed analysis when creating their migration plan.

8. DEVELOP PROJECT SCOPE DOCUMENT

ACI does not believe this step is necessary for customers upgrading to BASE24 Release 6.0 Post Version 10 for Migration.

9. DEFINE REQUIREMENTS DEFINITION

The customer will be required to review existing CSMs to determine which ones will require retrofitting to the new version. With ACI's Fix Release methodology, BASE24 users should evaluate their CSMs to determine if they are handled as standard product in BASE24 Release 6.0 Post Version 10 or if they are specific to the customer's environment and will need to be upgraded to the new version.

10. DEVELOP PROJECT PLAN

The customer's project manager is responsible for developing an internal project plan. A review of the ACI project guidelines will help this person identify job responsibilities and establish time frames. A tracking mechanism should be included in the plan to ensure that the project is proceeding on schedule.

11. IDENTIFY CUSTOMER SPECIFIC MODIFICATION DEVELOPMENT

If the customer elects to have ACI develop modifications identified as required for the new version, a request will be submitted to ACI Software Development for a cost estimate. The functional descriptions and estimates will be sent to the customer for review and approval. Resources will be assigned and the final delivery dates established upon receipt of the signed contract.

Should the customer decide to develop any modifications in-house, resources will need to be assigned and scheduled. Once delivery dates are established, impacts to system testing can be determined.

12. DEFINE CERTIFICATION REQUIREMENTS

Customers currently on Fortify.3 will need to verify with each of the interchanges they connect to, to determine if they need to re-certify with the Interchanges with BASE24 Release 6.0 Version 10 code.

If re-certification is required, preliminary test times should be determined and a copy of the interchange test script secured.

The customer needs to set up test time with the interchange well in advance in order to insure time frames are met.

13. ESTABLISH TEST FACILITY

It is recommended that an area be designated specifically for testing the BASE24 Release 6.0 Post Version 10 for Migration software. The following items are recommended for the test area:

- ☐ 3 PCs
- ☐ Test devices
- ☐ Hard copy printer
- ☐ Test cards

14. INSTALL PRODUCTION HARDWARE

Installation of any additional computer hardware or peripherals is generally performed by the local hardware service organization or customer staff.

15. ATTEND BASE24 EDUCATION CLASSES

ACI offers a full suite of instructor led courses for BASE24-eps. The course descriptions and outlines can be viewed on the ACI Worldwide web site at www.aciworldwide.com.

16. DEVELOP INTERNAL PROCEDURES

There are no new internal procedures that ACI is aware of for BASE24 Release 6.0 Post Version 10 for Migration modifications. User/Operational impacts are noted in the detailed sections for each enhancement described within this document.

17. DEVELOP SYSTEM TEST PLAN

The customer is responsible for developing a system test plan. For a Migration system, testing will need to occur on both BASE24 and BASE24-eps, and depending on the phase of migration, testing may include transactions acquired on each of these systems.

Included in the test plan should be a description of each step specifying the test card to be used, the account to be used, the transaction to be executed, and the expected results. A procedure for retaining the results of the transaction processing should also be specified. Controlled testing and result verification procedures are key elements for successful system testing.

The execution of the system test plan will occur over a period of weeks to fully test all aspects of the system. BASE24 product functionality should be the first application tested. Any system modifications should then be thoroughly tested. The interface between the host and BASE24 should also be tested. This includes testing on-line authorization and the refresh and extract programs.

18. DEVELOP HOST SOFTWARE

During the course of a business day, BASE24 logs all completed and declined transactions to a transaction log file. After network settlement, the transaction log file can be extracted and used as input into the customer's nightly processing cycle on the host. There are no new features in BASE24 Release 6.0 Post Version 10 for Migration modifications for which ACI believes a customer's Host would require modifications.

After the nightly processing cycle on the host or periodically during the business day the host may need to update card and account files used by BASE24 for pre-authorization or stand-in processing. There are no new features in BASE24 Release 6.0 Post Version 10 for Migration modifications for which ACI believes a customer's Host would require modifications to this process.

19. INSTALL BASE24

BASE24 Release 6.0 Post Version 10 for Migration software will need to be installed at the customer site. Licensed BASE24 Release 6.0 Post Version 10 for

Migration software modules will be provided to the customer upon request for installation on their system.

20. CONVERT DATA FILES

ACI provides database conversion programs for selected BASE24 files. These files are discussed in the detail sections for each enhancement described within this document. Currently no BASE24 specific conversion programs exist for the Migration modifications.

ACI also provides Migration conversion programs to convert customer data from BASE24 Release 6.0 Version 10 to BASE24-eps Version 09.2. Please refer to the BASE24 to BASE24-eps Migration Conversion Program Guide on InfoLink for more details.

21. CERTIFY INTERCHANGE

This task involves implementing the interchange test script and receiving notice of certification from the interchange. Current BASE24 users should not have to re-certify their Interchange Interfaces, unless they are implementing new functionality not previously tested or as directed by the interchange.

22. PERFORM SYSTEM TESTING

Full business day cycle testing of the system should be performed as determined by the customer testing plan and procedures.

23. DEVELOP CONVERSION PLAN

The customer should develop an implementation plan for converting existing devices and interchange links to BASE24 Release 6.0 Post Version 10 for Migration. The installation of new devices and interchanges should also be included in this plan. A method of informing users of any changes to existing procedures should also be developed. The conversion schedule should be routed to all departments.

24. GO-LIVE

At the customer's request, an operational support analyst will visit the site one day prior to the "go-live" date to review the current software status and the BASE24 facilities. This individual will remain onsite to assist the customer with production cutover. The migration plan developed by the customer will be utilized in production cutover. On-site go-live support is a billable service.

25. COMPLETE POST IMPLEMENTATION REVIEW

In general, the purpose of this meeting is to ensure overall satisfaction of the customer's project.

26. TURN OVER TO CUSTOMER MANAGEMENT

If an ACI Project Manager has handled the BASE24 upgrade, a formal turnover meeting is held between the ACI Project Manager and the ACI Customer Manager to ensure a smooth transition in turnover of responsibilities for on-going customer support.

Publications

The BASE24 Release 6.0 documentation set contains the most current version of each document.

If a BASE24 manual has not been updated for BASE24 Release 6.0, the manual for the prior release appears on the BASE24 Release 6.0 menu with a note identifying the prior release.

The BASE24 documentation set has been updated to include the BASE24 Release 6.0 Post Version 10 for Migration modifications. The updated BASE24 documentation is available in three formats.

- ☐ **CD-ROM.** The CD-ROM contains all PDF files for the manuals in the documentation set.
- ☐ **HELP24 eSupport InfoLink.** All files for the manuals in the BASE24 Release 6.0 documentation set are located on the HELP24 eSupport InfoLink database. The files for individual manuals can be copied from the HELP24 eSupport InfoLink database.

In addition, the HELP24 eSupport InfoLink database contains the latest documentation including additions or revisions created between ZIP files or CD-ROMs.
- ☐ **Software Management Electronic Distribution.** ZIP or ZIP Executable files that contain the same contents as the CD-ROM are available through the ACI Electronic Distribution system (ED).

Documentation for XPNET 3.0 and XPNET 3.1 is available in a separate set titled NET24-XPNET 3.1 that is available in the same formats as the BASE24 documentation.

BASE24 customers can download files from the HELP24 eSupport InfoLink database or order the documentation ZIP files or CD-ROM from their ACI Customer Manager.

Education

BASE24 Technical Education offers a complete set of modules covering the components of the BASE24-eps system. BASE24-eps courses are structured into a modular format that eliminates repetitious material, provides information specific to certain job functions, offers hands-on lab experience, and enhances retention of information taught.

The modular format enables BASE24-eps users to choose modules applicable to their employees' job responsibilities. This provides consolidated training time and offers opportunities for additional employees to receive education.

The course descriptions, outlines and current education schedule can be viewed on the ACI Worldwide web site at www.aciworldwide.com.

HELP24

ACI Worldwide's eSupport site is available for customers to report problems or ask questions about BASE24 Release 6.0 Post Version 10 mandates and modifications. eSupport is an internet web based application that interfaces with the HELP24 Salesforce application.

With ACI eSupport, a customer can:

- ☐ See past and current cases and create new cases.
- ☐ Search KnowledgeBase solutions for support case solutions.
- ☐ See reports for cases by Product and Status.
- ☐ See other relevant technical documents.

An eSupport option, InfoLink, is the link to a wealth of information that can help in day to day business situations. It allows on-line access to ACI Publications, Fix History Information, HELP24 Hotlines and much more. [An eSupport customer ID can be obtained by sending an email to *globalhelp24support@aciworldwide.com* and requesting an eSupport Portal customer ID and password.](#)

To assist with troubleshooting, HELP24 has acquired a tool called WebEx. This is a state of the art web-based technology that allows ACI to troubleshoot issues in a secure, online environment. Compared to the dial-up environment used in the past, WebEx provides convenient access, a more stable connection and most importantly, it provides a collaborative environment which allows customers to actively participate in the session by viewing and asking questions about everything that goes on.

To address audit security requirements, WebEx provides the option to record the session so all steps can be documented in a file that can be accessed after the fact if necessary. WebEx has a file transfer option that provides the ability to transfer files from a customer site to ACI, or vice versa. This feature can be used in the event the file(s) are too large to email. [The ACI File Manger tool can also be used to send in files for cases, this tool can be obtained from Electronic Distribution \(ED\).](#)

ASTech Services

ACI offers customer support services through our ASTech Division which allows the selection of a la carte support services to meet individual customer requirements. ASTech, ACI Support and Technical Services, is a service support team which provides the customer with a variety of on-site and remote technical support. ASTech provides customers with supplemental staffing, system performance analysis, review and/or upgrading of previous release customer-specific software development, and detailed operational technical training.

Your ACI Customer Manager can provide you with details of services available in your region that have been tailored to the special needs of different areas of the world.

The following are examples of the various services ASTech could undertake to assist during the BASE24 upgrade.

Customer Software Analysis

ASTech personnel will perform a complete review of the customer's BASE24 software system and determine what current modifications (CSM code) exist at the customer location. ASTech personnel will perform a detailed comparison of existing customer specific software modifications to BASE24 Release 6.0 Post Version 10 for Migration functions. Upon completion of the review, the customer will be provided with a document that identifies all modules that contain code unique to their BASE24 system (file names, custom functions, custom function applicability, etc.).

Conversion Planning

This service option provides the customer with comprehensive support during the migration from a BASE24 only system to a BASE24/BASE24-eps migration system. ASTech assigns the customer a Technical Project Lead, or Tech Lead from ACI. The Tech Lead will be responsible for ensuring the success of the BASE24 upgrade project.

The Tech Lead will:

- ☐ Review the migration options and develop a detailed migration plan for the conversions project
- ☐ Review the Project Scope Document on behalf of the customer (if applicable)
- ☐ Review the customer's internal procedures to accommodate BASE24 Release 6.0 Post Version 10 for Migration functions.

Upgrade Custom Code

Prerequisite: The Customer Software Analysis to identify all code unique to the customer.

With this service, ACI will upgrade any necessary custom code to BASE24 Release 6.0 Post Version 10 for Migration. This includes unit testing of the code. Customizations that are no longer necessary will be removed. Customizations that must be carried forward can either be upgraded in their current form or be reengineered to take advantage of new functionality in BASE24 Release 6.0 Post Version 10. Reengineering customizations will add time to the estimate.

System Test Planning

Prerequisite: The Customer Software Analysis to identify all code unique to the customer.

ASTech personnel will develop and execute a BASE24 System test plan designed for the customer's specific needs. This service also includes the performance and documentation of the system acceptance testing.

Switch and Host Certification Support

Prerequisite: The Customer Software Analysis to identify all code unique to the customer.

This service option allows ASTech personnel to provide complete support of the various switch and/or host communication certification testing. This includes reviewing and refining the test scripts, performance of certification testing functions, evaluation of the testing results, and documentation and presentation of the results obtained during the certification testing.

Go-Live Support

ASTech personnel will be at the customer site assisting in all conversion tasks and being present for go-live support. This includes remaining on-site for a couple of days to ensure system stability.

Post Go-Live Support

After a successful go-live, a Tech Lead will provide on-going support which may be required by the customer. Tech Lead support can be provided at the customer location and/or remotely through ACI.

ACI Worldwide Inc

3: BASE24 Networks First Modifications

This section describes the implementation requirements associated with the BASE24 Networks First modifications.

The implementation requirements are identified using a standard format defined in Section 1.

These modifications are required for the first phase of migration plans for customers migrating from BASE24 to BASE24-eps.

As part of the migration plans, HISO will be used as a 'bridge' to allow the transfer of messages from BASE24 to BASE24-eps and vice versa. On the BASE24 side, the BASE24 HISO interface will be used, and on the BASE24-eps side, a BASE24-eps HISO 87 Interface will be used. The BASE24 system will be on an NSK system and the BASE24-eps system may be on an NSK, SUN or IBM system.

The following changes are supported as part of this modification:

1. Support of log-only transactions from BASE24-eps.

One of the requirements of Networks First is to allow a migrating customer to extract all transactions from the BASE24 TLF / PTLF log files. There may be some transactions in the BASE24-eps system that are not routed to BASE24. BASE24-eps will now route these transactions to BASE24, and BASE24 was modified to receive these transactions as "log-only" type transactions via the BASE24 HISO87 interface and ensure they are written to the (P)TLF. These "log-only" transactions will not be routed further.

- a. The BASE24 HISO Interface was modified to accept "log-only" type transactions via the BASE24-eps HISO87 interface. These log-only transactions will be forwarded to Authorization to be logged. These log-only transactions will be identified by an external message stat field value of "360", and the stat field of the internal message forwarded to Authorization will be "35".
- b. The BASE24 ATM Authorization and the BASE24 POS Router Authorization modules were modified to process "log-only" type transactions from the BASE24 HISO Interface, and log them to the (P)TLF with the correct message type. These log-only transactions will be identified by a stat field value of "35".

2. Support of FHM Hot Card Status Update messages from BASE24 to a BASE24-eps interchange interface(s).

The BASE24 HISO Interface was modified to route a card status message to the BASE24-eps HISO87 Interface to be forwarded to the interface(s) now on

BASE24-eps. Previously the BASE24 HISO Interface routed PATH requests to the interface(s) on BASE24.

The BASE24 HISO Interface will route a single hot card status message to the BASE24-eps HISO87 Interface if it determines that any of up to three interface processes named in the request from the Host are interfaces that have been migrated from BASE24 to BASE24-eps. It will not format and route a PATH request to that migrated interface. It will format and route a PATH request to any of the interfaces (named in the request from the Host) that remain on BASE24. LCONF params (MIGR-HISO-NAMEidentifier) will be used to determine whether an interface has been migrated from BASE24 to BASE24-eps

3. Alternate routing transactions from BASE24-eps to BASE24

One of the requirements of Networks First is to allow a migrating customer who currently supports alternating routing of transactions from one interface to another, to continue to support that concept if the first interface has been migrated to BASE24-eps but the second one has not.

The BASE24 HISO Interface was modified to accept a response from the BASE24-eps HISO87 Interface that needs to be alternate routed to an interface that is still on BASE24. These transactions will be identified by an external message stat field value of "350". These messages will be formatted correctly into the (P)STM as requests and forwarded to Authorization to be re-routed.

Assumptions and Restrictions

1. OAR is not supported by interfaces on BASE24-eps.
2. Bulk Check transactions are not supported for Networks First.
3. Statement print functionality is not supported for Networks First.
4. None of the interchanges supported by Networks First supports check guarantee/check verify transactions. Therefore, BASE24-eps HISO87 will not support sending check guarantee/check verify transactions to BASE24 or accept them from BASE24.
5. Log-only transactions will not be sent from BASE24 to BASE24-eps. This enhancement only supports sending log-only transactions from BASE24-eps to BASE24 in order for BASE24 to log transactions that are not routed by an acquiring interface.
6. Log-only transactions sent from BASE24-eps may be rejected by BASE24 if they cannot be converted from the SEM to the (P)STM formats. This means that customers must be prepared to look for exceptions transactions on both BASE24 and BASE24-eps.

7. When transactions are alternate routed from a BASE24-eps interface out to a BASE24 interface, there is the possibility of the transaction being logged to the journal on BASE24-eps as approved, and to BASE24's (P)TLF as denied, or vice versa.
8. If the sem.stat contains the value of "350", the response message received from BASE24-eps will be sent to the ATM authorization or the POS Router Authorization process to be alternate routed, regardless of whether the response was approved or denied.
9. Customers will need to evaluate their timer settings to ensure that transactions being sent between the BASE24 and BASE24-eps systems (and especially any transactions that are alternate routed between systems) can be successfully processed before a timeout situation occurs.
10. Switch settlement totals do not need to be replicated from BASE24 to BASE24-eps and vice versa. In BASE24 these totals are only journaled in the ILF; they are not logged to the (P)TLF. Since customers must currently extract the ILF to get this information, we have made the assumption that if interfaces remain on BASE24, the customer will continue to extract the ILF from BASE24.
11. BASE24-eps must communicate with the BASE24 HISO Interface in order to receive Hot Card Status updates from BASE24. Communication directly to the BASE24-fhm process is not allowed.
12. Card Status Updates received from the Host must be configured to be routed to BASE24-eps HISO 87.
13. BASE24 will only send FHM Card Status Update messages to BASE24-eps for interfaces that have been migrated. BASE24 will continue to route FHM Card Status Updates messages for interchanges whose interfaces have not been migrated, to the BASE24 interface.
14. If two interfaces have been migrated from BASE24 to BASE24-eps, and both are configured to receive FHM Hot Card Status update messages from a single message in from the Host, BASE24-eps will receive a single FHM Hot Card Status update request from BASE24. BASE24-eps is responsible for sending the FHM Hot Card Status update message to both of the interfaces now on BASE24-eps.

For example, if the Host sends an FHM Hot Card Status update request into BASE24 containing Hot Card information for VISA, Banknet and STAR, and both VISA and Banknet interfaces have been migrated to BASE24-eps, then the BASE24 HISO will send a single message to the BASE24-eps HISO87 interface containing the Hot Card information for both VISA and Banknet. It will also send a single message to the STAR interface still on BASE24, containing only the Hot Card information for STAR. BASE24-eps will be responsible for sending a message to each of the VISA and Banknet interfaces, each containing their Hot Card Information.
15. The Host must continue to configure the Hot Card Status update message to contain the name(s) or services of the interface processes that need to be

notified, as they were on BASE24. BASE24 will convert the BASE24 interface name to the Migration HISO name needed to pass the message to an interface now migrated to BASE24-eps.

16. If the Host configures a service to receive the Hot Card Status update request, rather than using a BASE24 process name, then the LCONF params that will configure the BASE24 Interface names and their Migration HISO equivalents, will also need to contain the service name rather than the BASE24 Interface name, to ensure that a match may be found.
17. If an FHM message other than a Card Status Update is received, BASE24-eps will send a reject message back to the host.
18. This enhancement will only support ISO formatted FHM messages (i.e. no support for ANSI format).
19. This enhancement will only support Card Status Update FHM messages.
20. For transactions to be routed to an interface now migrated to BASE24-eps, the SPROUTE will contain the name of the Migration HISO. This must not be a service; it must be the process name of the Migration HISO.
21. BASE24 is to be the database of record during the Networks First phase of the migration. All transactions must be logged to the BASE24 Transaction Log files, to be available for extract and perusal. Switch Settlement totals, for interfaces now migrated to BASE24-eps, are the only items that must be extracted from BASE24-eps.
22. The Migration HISOs will need to use a different physical SAF from the HISOs used to communicate with the Host. This will allow a BASE24 customer who performs SAF extracts to migrate interfaces to BASE24-eps and ensure that their Host receives the same data as before the migration. HISO will not need any code changes to support this; HISO already reads the LCONF for the SAF assign by specific process name.
23. It is expected that the Migration HISO will be configured to perform a PIN translate on transactions being sent to BASE24-eps via the bridge. This is to ensure that details of every ATM and POS device do not need to be known by an interface connected to BASE24-eps.
24. Transaction based pricing (TBP) reports will include all log-only transactions from BASE24-eps in the reports. They will be included in the appropriate counts, based on whether they are denied or approved, and based on the responder and originator fields in the (P)STM of the messages. TBP will be unaffected by alternate routed transactions from BASE24-eps. These will be sent to Auth as requests, and will only be logged to the (P)TLF and therefore counted by TBP on the eventual response.
25. Transaction analysis reports will also count all of the log-only transactions from BASE24-eps, and they will be counted in the correct buckets based on the responder field in the (P)STM. These counts will not be affected by the alternate routed transactions.

26. Extract will include all the log-only transactions from BASE24-eps, and they will be included in the hash total for the extract, so long as the (P)TLF's amount 1 is a valid amount. If the amount is not valid, then the transaction will be skipped, and details will be written to the Extract report to indicate the details of the skipped record. Extract is unaffected by the alternate routed transactions.

Prerequisites

The Transaction Security Services Version 09.2 Service Pack 2 must be installed prior to implementation of this enhancement.

Software Impacts

All BASE24 customers:

- ☐ Changes to BA60DDL.DDLBATKN.
- ☐ Inline changes to BA60SRC.BATKNCVS and BATKNID
- ☐ Inline changes to BA60AFT.COBTKN
- ☐ Inline changes to BA60HISO.BAHISOS and BAHISOG
- ☐ Updated event (log) message manual BA60LOGM.BAHISO
- ☐ Updated documentation files BA60MISC.EMF, BAMISCTD, LCONFBA and CONTENTS
- ☐ New documentation file BA60MISC.MIGRHISO containing station/line/device/process definitions for the Migration HISO.

All BASE24-atm customers:

- ☐ Inline changes to AT60AUTH.AUTHG, AUTHM, AUTHS and AUTHLIBS
- ☐ Inline changes to AT60HISO.ATHISOS
- ☐ Updated event (log) message manuals BA60LOGM.ATAUTH and ATHISO
- ☐ Updated documentation file BA60MISC.LCONFAT

All BASE24-pos customers:

- ☐ Inline changes to PS60RTAU.RTAUG, RTAUM, ROUTERS and AUTHLIBS
- ☐ Inline changes to PS60HISO.PSHISOS
- ☐ Updated event (log) message manuals BA60LOGM.PSHISO and PSROUTER
- ☐ Updated documentation file BA60MISC.LCONFPS

All BASE24-fhm customers:

- ☐ Inline changes to FH60HISO.FHHISOS
- ☐ Updated documentation file BA60MISC.LCONFFH

A complete list of the files affected by this enhancement can be found in the SCN file BA60UD0E.SCNMIGR1.

CUSTOMACS Changes

Not applicable

LCONF Assign Changes

Not applicable

LCONF Param Changes

This section describes the param records that must be added to the LCONF to support these changes. Details of the params are provided in the *BASE24 Logical Network Configuration File Manual*.

A sample of the following param is included in the LCONFBA file located on the BA60MISC subvolume.

MIGR-HISO-ENABLE

This param, used by the BASE24 Host Interface process, specifies whether this process is acting as a Migration HISO 'bridge' process.

The valid values are:

"Y" – this HISO process is a migration bridge

"N" – this HISO process is not a migration bridge.

A generic param (with the process of *****) will exist and be set to a value of "N" to ensure that all HISO processes configured to communicate with a Host will not perform any migration-specific processing. A specific param (with the process name specified) will exist for each HISO process that is to act as a Migration HISO 'bridge'.

The default value is "N" – this HISO process is not a migration bridge.

MIGR-INTF-DPC-NUM

This param, used by the BASE24 Host Interface process, specifies the DPC Number to be used in messages sent to BASE24-eps, when no DPC number is already present in the message.

The valid values are 0 – 9999.

During Migration from BASE24 to BASE24-eps, transactions for an interface now on BASE24-eps are likely to be SPROUTE routed to the Migration HISO bridge. When SPROUTE routing is used, no DPC number is present in the message, but a DPC number is required for the HISO process to read the Host Configuration File (HCF) record. This param allows a DPC number to be specified.

There is no default value.

This param is only read by the HISO process if the LCONF param MIGR-HISO-ENABLE is set to “Y”.

A sample of the following param is included in the LCONFAT file located on the BA60MISC subvolume.

MIGR-ATM-ENABLE

This param, used by the BASE24-atm Authorization process, the BASE24-atm Transaction Context Manager process and the BASE24-atm Settlement process, specifies whether this process is to perform any migration-specific authorization processing. The valid values are:

“Y” – this process will perform migration-specific processing

“N” – this process will not perform migration-specific processing.

A generic param (with the process of *****) will exist and be set to a value of “Y” as soon as any MIGR-HISO-ENABLE param has been added for a specific Migration HISO ‘bridge’ process. This will allow the authorization processes to process the log-only migration transactions sent from BASE24-eps. If no Migration HISO process is being used, this param should be set to a value of “N”.

The default value is “N” – this process will not perform migration-specific processing.

A sample of the following param is included in the LCONFPS file located on the BA60MISC subvolume.

MIGR-POS-ENABLE

This param, used by the BASE24-pos Router/Authorization process, the BASE24-pos Transaction Context Manager process and the BASE24-pos Settlement process, specifies whether this process is to perform any migration-specific authorization processing. The valid values are:

“Y” – this process will perform migration-specific processing

“N” – this process will not perform migration-specific processing.

A generic param (with the process of *****) will exist and be set to a value of “Y” as soon as any MIGR-HISO-ENABLE param has been added for a specific Migration HISO ‘bridge’ process. This will allow the authorization processes to process the log-only migration transactions sent from BASE24-eps. If no Migration HISO process is being used, this param should be set to a value of “N”.

The default value is “N” – this process will not perform migration-specific processing.

A sample of the following param is included in the LCONFFH file located on the BA60MISC subvolume.

MIGR-FHM-HISO-ENABLE

This param, used by the BASE24 Host Interface process, specifies whether this HISO process is to perform any migration-specific FHM processing. The valid values are:

“Y” – this process will perform migration-specific FHM processing

“N” – this process will not perform migration-specific FHM processing.

A generic param (with the process of *****) will exist and be set to a value of “Y” as soon as any Hot Card Status update requests from the Host will need to be sent to a BASE24 Migration HISO ‘bridge’ process to be sent on to BASE24-eps to be processed by an interface on that system. If no Migration HISO process is being used, this param should be set to a value of “N”.

The default value is “N” – this process will not perform migration-specific FHM processing.

MIGR-HISO-NAME*Identifier*

This series of params, used by the BASE24 Host Interface process, specify the service or symbolic name of a BASE24 interface process that has been migrated from BASE24 to BASE24-eps, and the corresponding BASE24 Migration HISO ‘bridge’ process name that will be used to communicate with the interface on BASE24-eps.

It is used by the FHM HISO process to determine whether Hot Card Status update requests should be forwarded to interfaces on BASE24 or on BASE24-eps.

The value is in the form of:

BASE24 Interface name/BASE24 Migration HISO process name

For example: MIGR-HISO-NAME1 P1A^STAR/P1A^MIGRHISO1

 MIGR-HISO-NAME2 P1A^VISA01/P1A^MIGRHISO2

Each MIGR-HISO-NAME param contains the name of one service or process that has migrated to BASE24-eps. When multiple interface processes or services have been migrated, this param will include an optional identifier to specify params used for the different processes or services in the same logical network. The optional identifier is usually a number but can be any unique set of characters that has not already been declared by another MIGR-HISO-NAME*Identifier* param.

Generic params (with the process of *****) will exist and be set to the correct process names as soon as any Hot Card Status update requests from the Host will need to be sent to a BASE24 Migration HISO ‘bridge’ process to be sent on

to BASE24-eps to be processed by an interface on that system. If no Migration HISO process is being used, these params do not need to exist.

A maximum of 50 params can be added.

There is no default value.

Database Configuration

Host Configuration File (HCF)

HCF records will need to be set up appropriately for the customer's current configuration. Each Migration HISO will need at least one HCF record to be configured, with a key that contains the DPC number that will be used for the connection to BASE24-eps, and details of the stations that are used to connect to BASE24-eps. This DPC number will also be set up in the LCONF's MIGR-INTF-DPC-NUM parameter.

If a customer accepts Host Card Status updates from the Host, the DPC number used to communicate with BASE24-eps must be the same as the number currently being used to communicate with the Host. A customer may wish to define a separate Migration HISO to process just Host Card status updates, in which case that Migration HISO will use the same DPC number as used to communicate with the Host, and the remaining Migration HISOs (used for sending transactions to BASE24-eps) may (but are not required to) use a different DPC number. In this case, the LCONF's MIGR-INTF-DPC-NUM parameter would be set to the value of the DPC number being used to send transactions to BASE24-eps.

For example:

Example 1: Customer uses the same Migration HISO(s) to handle Hot Card status updates as to handle transactions. The HISO that communicates to the HOST uses DPC 0001. All Migration HISOs will use DPC 0001. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0001.

Example 2: Customer uses a separate Migration HISO to handle Hot Card status updates. The HISO that communicates to the HOST uses DPC 0001. The Migration HISO that handles Hot Card status updates will use DPC 0001. The customer chooses to have the remaining Migration HISOs use the same DPC, DPC 0001. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0001.

Example 3: Customer uses a separate Migration HISO to handle Hot Card status updates. The HISO that communicates to the HOST uses DPC 0001. The Migration HISO that handles Hot Card status updates will use DPC 0001. The customer chooses to have the remaining Migration HISOs use a different DPC, DPC 0002. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0002.

It is suggested that a separate Token Group be added for the Migration bridge records. This allows a customer to configure some tokens to be sent to the Host, while others are used over the Migration bridge only.

In order to allow this, the HCF records for each of the Migration HISO bridge processes need to use a value for the Token Group (HCF screen 1) that is different from the value used for the Host's HISO processes.

BASE24-eps only supports variable format ISO messages over the bridge. In order to support this, the message format needs to be configured as '01' – variable format in the HCF records for the Migration HISO processes. For ATM this field is on screen 5, for POS this field is on screen 7.

External Message File (EMF)

Several changes are needed to the EMF records for the Migration HISO bridge processes, in order for transactions to be processed correctly in a migration system.

Sample EMF records applicable to a Migration system are available in the sample EMF provided on BA60MISC. They are labelled with the process name P1A^MIGRHISON1.

Customers are advised to verify their EMF settings to ensure that they will be appropriate for transaction processing in their specific migration system.

Token File (TKN)

This enhancement uses the following new tokens:

- ☐ Migration ATM Data1 Token (Token ID 'M1').
- ☐ Migration POS Data1 Token (Token ID 'M2').

If any of these tokens are to be logged to the BASE24-pos Transaction Log File (PTLF), the BASE24-atm Transaction Log File (TLF) or the BASE24 Interchange Log File (ILF), the appropriate token records must be configured in the Token file.

If any of these tokens are to be extracted with the TLF, PTLF or ILF, sent to the host, or passed through the BIC ISO Interchange Interface, the appropriate records must be configured in the Token file.

It is suggested that a separate Token Group be added for the Migration HISO records. This allows a customer to configure some tokens to be sent to the Host, while others are used over the bridge only. If this separate token group is defined, the M1, M2 and M4 tokens only need to be configured for the Migration HISO.

New Data Files

Not applicable

Template Changes

Not applicable

Device Configuration

Not applicable

Mega Table (MEGATBL) Changes

Not applicable

PI-Table Changes

Not applicable

SEG-Table Changes

Not applicable

Security Table (SECTBL) Changes

Not applicable

PATHCONF Changes

Not applicable

CRT Access Security Changes

Not applicable

Routing Changes

The PRECMD file used in SPROUTE routing, or the IDF routing table, or the AST file must be amended to route transactions to a migration HISO process if the transaction needs to be routed to an interface migrated to BASE24-eps.

Network Configuration

At least one migration HISO process must be configured, with stations defined that communicate with the BASE24-eps HISO87 process. Multiple migration HISO processes can be defined, as required by the customer's network configuration.

File Conversions

Not applicable

Host/Co-Network Impacts

Super Extract Process

Host's need to be aware that the additional log-only transactions sent from BASE24-eps will be included in a (P)TLF extract. Similarly, advices sent from BASE24-eps will be included in a (P)TLF extract.

User/Operational Impacts

Performance Considerations

Routing transactions from BASE24 to BASE24-eps for authorization (or vice versa) will extend the transaction path and may result in reduced throughput compared to a customer's existing BASE24 system.

Alternate routing of transactions from BASE24-eps back to BASE24 will also extend the transaction path. The customer must evaluate their timer settings to ensure that the timers allow for the extended transaction path.

Event Messages

New event (log) messages were created as a result of this enhancement. Operators must be trained to recognize the new event messages and perform the appropriate remedy for a given message. Refer to the BA60LOGM.event message documentation files.

Vendor Impacts

Not applicable

Reference Documents

Not applicable

4: BASE24 Migration Modifications

This section describes the implementation requirements associated with the BASE24 Migration modifications.

The implementation requirements are identified using a standard format defined in Section 1.

For customers who have already installed Networks First, these modifications are required for the next phase of migration plans for migrating from BASE24 to BASE24-eps.

As part of the migration plans, HISO will be used as a 'bridge' to allow the transfer of messages from BASE24 to BASE24-eps and vice versa. On the BASE24 side, the BASE24 HISO interface will be used, and on the BASE24-eps side, a BASE24-eps HISO 87 interface will be used. The BASE24 system will be on an NSK system and the BASE24-eps system may be on an NSK, SUN or IBM system. Changes that were made as part of the Network First enhancements will be a prerequisite for these modifications.

Various migration scenarios have been identified, and changes were required to BASE24 to ensure that the system would function correctly in each of these scenarios. These changes are described below:

1. Sending financial "log-only" transactions and ATM/POS Device Handler settlement totals to BASE24-eps.

One of the requirements of migration is to allow a migrating customer to extract all transactions from either the BASE24 TLF / PTLF log files or the BASE24-eps journals. During a migration scenario where the authorization occurs on the BASE24-eps system, but the acquiring endpoints are on BASE24, there are some transactions (e.g., terminal settlement totals) that do not get routed by the acquiring end-point. Therefore, advices cannot be configured for these transactions. BASE24 was modified to send these transactions to BASE24-eps as "log-only" type transactions via the BASE24 HISO87 interface. These "log-only" transactions will not be routed further once in the BASE24-eps process, they will simply be journaled.

- a. Send Terminal Settlement totals to BASE24-eps as log-only transactions.

BASE24 will now send Terminal Settlement totals to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE or MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS or MIGR-POS-PROCESING-OPTS is set to a "1" or a "3"). The totals will be sent to a destination configured in the LCONF Param

MIGR-ATM-HISO-DEST or MIGR-POS-HISO-DEST. In the case of POS, fields already existed in the SEM to carry the totals, while in the case of ATM, SEM field 114 will contain the total details.

BASE24 will send these messages to BASE24-eps as “0520” messages, and BASE24-eps will respond to BASE24 with an “0530” acknowledgement message.

- b. Send Clerk Settlement totals to BASE24-eps as log-only transactions.

BASE24 will now send Clerk Settlement totals to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a “1” or a “3”). These totals will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. The clerk totals themselves will be placed in SEM field S-126 which has been redefined in order to carry them.

BASE24 will send these messages to BASE24-eps as “0520” messages, and BASE24-eps will respond to BASE24 with an “0530” acknowledgement message.

- c. Send Batch update transactions to BASE24-eps as log-only transactions

BASE24 will now send Batch Update transactions to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. The (P)STM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0320” messages, and BASE24-eps will respond to BASE24 with an “0330” acknowledgement message.

- d. Send “9980” (C1000 money in drawer) messages to BASE24-eps as log-only transactions.

BASE24 will now send “9980” messages to BASE24-eps as denied “0220’s” via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST. The STM.rte.stat will be set to a “36” and the HISO

will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” messages, and BASE24-eps will respond to BASE24 with an “0230” acknowledgement message.

- e. Send “0200” declined surcharging messages to BASE24-eps as log-only transactions.

BASE24 will now send “0200” declined surcharging messages to BASE24-eps as denied “0220’s” via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST. The STM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” messages, and BASE24-eps will respond to BASE24 with an “0530” acknowledgement message.

- f. Send “0200” declined DCC messages to BASE24-eps as log-only transactions.

BASE24 will now send “0200” declined DCC messages to BASE24-eps as denied “0220’s” via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST. The STM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” messages, and BASE24-eps will respond to BASE24 with an “0230” acknowledgement message.

- g. Send Acquirer routing token log-only messages to BASE24-eps as log-only transactions.

BASE24 will now send messages with the acquirer routing token present to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS is set to

a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST. The STM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” or “0420” messages, and BASE24-eps will respond to BASE24 with an appropriate acknowledgement message (it may be an “0230”, or an “0430” depending on the original message type sent to BASE24-eps).

- h. Send “9920” and “9921” EMV Transaction certificate messages to BASE24-eps as log-only transactions.

BASE24 will now send “9920” and “9921” EMV transaction certificate messages to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. The “9920” message will be sent to BASE24-eps as an “0120” message, while the “9921” message will be sent as an “0420”.

The PSTM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” (for the “9920” certificate message) or “0420” (for the “9921” certificate message) messages, and BASE24-eps will respond to BASE24 with an appropriate acknowledgement message (it will be an “0230”, or an “0430” depending on the original message type sent to BASE24-eps).

- i. Send “9900” SPDH Bad MAC messages to BASE24-eps as log-only transactions.

BASE24 will now send “9900” messages to BASE24-eps as denied “0220”s via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a “1” or a “3”). These transactions will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. The PSTM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as “0220” messages, and BASE24-eps will respond to BASE24 with an “0230” acknowledgement message.

- j. Send Terminal Statistics messages to BASE24-eps as log-only transactions.

BASE24 will now send Terminal Statistics from Hypercom to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a "1" or a "3"). These transactions will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. Existing fields are already defined in the SEM to carry the statistics information.

BASE24 will send these messages to BASE24-eps as "0520" messages, and BASE24-eps will respond to BASE24 with an "0530" acknowledgement message.

- k. Send POS "9991" messages to BASE24-eps as log-only transactions.

BASE24 will now send "9991" messages to BASE24-eps as denied 0220's via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-POS-PROCESSING-OPTS is set to a "1" or a "3"). These transactions will be sent to a destination configured in the LCONF Param MIGR-POS-HISO-DEST. The PSTM.rte.stat will be set to a "36" and the HISO will set the SEM.stat field to a "360" to indicate that this is a log-only transaction.

BASE24 will send these messages to BASE24-eps as "0220" messages, and BASE24-eps will respond to BASE24 with an "0230" acknowledgement message.

2. Receiving financial "log-only" transactions and ATM/POS Device Handler settlement totals from BASE24-eps.

One of the requirements of migration is to allow a migrating customer to extract all transactions from either the BASE24 TLF / PTLF log files or the BASE24-eps journals. During a migration scenario where the authorization occurs on the BASE24 system, but the acquiring endpoints are on BASE24-eps, there are some transactions (e.g., terminal settlement totals) that do not get routed by the acquiring end-point. Therefore, advices cannot be configured for these transactions. BASE24 was modified to receive these transactions as "log-only" type transactions via the BASE24 HISO87 interface and ensure they are written to the (P)TLF. These "log-only" transactions will not be routed further.

- a. Receive Terminal Settlement totals from BASE24-eps as log-only transactions.

BASE24 will now receive Terminal Settlement totals from BASE24-eps via the BASE24-eps HISO87 interface. These totals will be passed directly to an

Authorization process to be logged to the (P)TLF. The messages from the HISO to the Authorization process are in the (P)TLF format. In the case of POS, fields already exist in the SEM to carry the totals, while in the case of ATM, SEM field 114 will contain the total details which are then moved into the TLF structure.

BASE24 will respond to BASE24-eps with an "0530" acknowledgement message.

- b. Receive Clerk Settlement totals from BASE24-eps as log-only transactions.

BASE24 will now receive Clerk Settlement totals from BASE24-eps via the BASE24-eps HISO87 interface. These totals will be passed directly to an Authorization process to be logged to the PTLF. The messages from the HISO to the Authorization process are in the PTLF format. The clerk totals themselves will be pulled from SEM field S-126 which has been redefined to carry them.

BASE24 will respond to BASE24-eps with an "0530" acknowledgement message.

- c. Receive Batch update transactions from BASE24-eps as log-only transactions

BASE24 will now receive Batch Update transactions from BASE24-eps via the BASE24-eps HISO87 interface. The incoming SEM.stat field will be set to a "360" to indicate that this is a log-only transaction, and HISO will set the (P)STM.rte.stat to a "36".

BASE24 will respond to BASE24-eps with an "0330" acknowledgement message.

3. Bi-directional Support of Mobile Top-up Transactions

The BASE24 HISO87 Interface now supports Mobile Top-up transactions. During migration, these transactions may need to be sent to BASE24-eps for authorization, or received from BASE24-eps via the bridge for authorization on BASE24.

- a. Send Mobile Top-up transactions to BASE24-eps as log-only transactions

BASE24 will now send Mobile Top-up transactions to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE or MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of log-only transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS or MIGR-POS-PROCESSING-OPTS is set to a "1" or a "3"). These transactions will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST or MIGR-POS-HISO-DEST. The HISO process converts the internal transaction codes to valid external codes. The

(P)STM.rte.stat will be set to a “36” and the HISO will set the SEM.stat field to a “360” to indicate that this is a log-only transaction.

BASE24-eps will respond to BASE24 with an “0230” acknowledgement message.

- b. Receive Mobile Top-up transactions from BASE24-eps as log-only transactions

BASE24 will now receive Mobile Top-up transactions from BASE24-eps via the BASE24-eps HISO87 interface. The HISO process converts the external transaction codes to valid internal codes. The incoming SEM.stat field will be set to a “360” to indicate that this is a log-only transaction, and HISO will set the (P)STM.rte.stat to a “36”.

BASE24 will respond to BASE24-eps with an “0230” acknowledgement message.

- 4. Advices will be sent to BASE24-eps for all transactions authorized on BASE24.

One of the requirements of migration is to allow a migrating customer to extract all transactions from either the BASE24 TLF / PTLF log files or the BASE24-eps journals. Customers will be required to configure advices for online transactions on both systems (BASE24 and BASE24-eps). This will allow online transactions to be journaled on both systems. The migration code modifications ensured that advices can be sent to BASE24-eps for all transactions authorized on BASE24.

- a. Send advice transactions to BASE24-eps

BASE24 will now send advice transactions to BASE24-eps via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF params MIGR-ATM-ENABLE or MIGR-POS-ENABLE and MIGR-HISO-ENABLE are true) and if the current migration scenario requires the sending of advice transactions to BASE24-eps (the LCONF Param MIGR-ATM-PROCESSING-OPTS or MIGR-POS-PROCESSING-OPTS is set to a “2” or a “3”). If the M4 Token – the BASE24-Migration EPS HISO token - is present, then BASE24-eps has seen this transaction before and an advice will not be sent. Otherwise, the advice message will be sent to a destination configured in the LCONF Param MIGR-ATM-HISO-DEST or MIGR-POS-HISO-DEST.

BASE24-eps will respond to BASE24 with an “0230” acknowledgement message.

- b. Receive advice transactions from BASE24-eps

BASE24 will now forward denied advices received from BASE24-eps via the HISO Interface to the appropriate Authorization process to be logged to the TLF.

5. Bi-directional Open Account Relation (OAR) support

During migration it is possible that the card database may reside on one system (i.e., BASE24 or BASE24-eps) and the ATM device handlers to reside on the other system. It must be possible to support the Open Account Relation flow in these situations.

Multiple Account Select/OAR between BASE24 and BASE24-eps is limited to one leg with a maximum of 10 accounts (max 5 FROM accounts and max 5 TO accounts).

a. Send OAR request information to BASE24-eps.

BASE24 will now send multiple account selection information in SEM field S-122 to BASE24-eps as part of the "0200" request via the BASE24-eps HISO87 interface, if the processes are running in a migration environment (the LCONF param MIGR-HISO-ENABLE is true).

b. Receive OAR responses from BASE24-eps.

BASE24 will now receive OAR response transactions from BASE24-eps via the BASE24-eps HISO87 interface. These messages will arrive from BASE24-eps as "0906" messages and will be converted by HISO into "9906" messages, so long as MIGR-HISO-ENABLE param is true. SEM field S-127 has been redefined to be able to carry the multiple account data. This "9906" message is passed onto the Authorization process where it will be formatted and passed on to the Device Handler, as required, so long as the MIGR-ATM-ENABLE param is true.

6. Bi-directional Support of Statement Print Transactions

During migration it is possible to support Statement Print transactions that are acquired on one system and authorized on the other. The migration code modifications ensured the BASE24 HISO interface can correctly handle these transactions.

7. Encrypted Data Translation

BASE24 supports an Encrypted Balance Token. The migration code modifications ensured that the BASE24 HISO is able to pass this token to BASE24-eps in such a way that the BASE24-eps system could correctly access the encrypted data.

8. Support of the complete BASE24-atm and BASE24-pos transaction set.

The migration code modifications ensured that the BASE24 HISO87 interface can support the complete BASE24-atm and BASE24-pos transaction set. This involved ensuring that HISO can both send and receive all of these transactions correctly.

9. Additional changes.

- a. Fixed the handling of a log-only '0215' statement print response.

The BASE24 HISO Interface formats the log-only "0215" message correctly as a statement print layout before passing it on to the Authorization process. This was a fix to Networks First processing.

- b. Fix the handling of a log-only '0205' statement print requests.

The BASE24 Authorization formats the log-only "0205" statement print request message correctly as a statement print layout before writing it to the TLF. This was a fix to Networks First processing.

- c. Fix the handling of a log-only '0500', '0510' and '0520' settlement messages.

The BASE24 HISO Interface formats the log-only '0500', '0510' and '0520' settlement messages correctly as PTLF format messages before passing them on to the Authorization process. This was a fix to Networks First processing.

Assumptions and Restrictions

1. Log-only transactions sent from BASE24-eps may be rejected by BASE24 if they cannot be converted from the SEM to the (P)STM formats. Similarly, log-only transactions sent from BASE24 may be rejected by BASE24-eps. This means that customers must be prepared to look for exceptions transactions on both BASE24 and BASE24-eps.
2. Customers will need to evaluate their timer settings to ensure that transactions being sent between the BASE24 and BASE24-eps systems (and especially any transactions that are alternate routed between systems) can be successfully processed before a timeout situation occurs.
3. Switch settlement totals do not need to be replicated from BASE24 to BASE24-eps and vice versa. In BASE24 these totals are only journaled in the ILF; they are not logged to the (P)TLF. If interfaces remain on BASE24, the customer will extract the ILF from BASE24. Most customers already extract the ILF.
4. A POS customer does not have to support sending of terminal settlement totals to the Host in order to have the settlement totals passed to BASE24-eps as log-only messages via the BASE24 HISO process. However, the logging of these totals to the PTLF must be configured in the PTDF record for the terminal in order to have the settlement totals passed to BASE24-eps via the BASE24 HISO process and a valid destination must be configured in the MIGR-POS-HISO-DEST LCONF param.
5. An ATM customer does not have to configure logging of the terminal settlement totals to the TLF. These totals will automatically be logged to the TLF. They will be passed to BASE24-eps as log-only messages via the BASE24 HISO process as long as a valid destination is configured in the MIGR-ATM-HISO-DEST LCONF param.

6. If Terminal settlement totals are to be sent to BASE24-eps as log-only messages, the HCF must be set to require an acknowledgement from Data Processing Center (DPC) for the Migration HISO process. This will allow the HISO to process the responses from BASE24-eps.
7. BASE24-eps does not support the sending of completions to the Host for Terminal Settlement totals. Once a customer moves a POS device to the BASE24-eps system, completions will no longer be sent to the Host for these totals, even if these totals are being sent back to BASE24 as log-only messages to be written to the BASE24 PTLF, and BASE24 is configured to send them out to the Host.
8. It is expected that the Migration HISO will be configured to perform a PIN translate on transactions being sent to BASE24-eps via the bridge. This is to ensure that details of every ATM and POS device do not need to be known by an interface connected to BASE24-eps.
9. If statement print transactions are supported by a customer, and the devices are on BASE24 and the connection to the Host is on BASE24-eps, the customer must know that only non-compressed data will be returned from BASE24-eps in the statement print transaction response, as BASE24-eps does not support compressed data.
10. If statement print transactions are supported by a customer, and the devices are on BASE24-eps and the connection to the Host is on BASE24, the statement print token added by BASE24-eps must indicate that non-compressed data will be requested from the Host. This will ensure that only non-compressed data is sent back in the response to BASE24-eps, as BASE24-eps does not support compressed data.
11. When customers migrate their Auth processing from BASE24 to BASE24-eps, if they use CAF only method on BASE24 they can migrate cards over by prefix or FIID. If they use CAF/PBF method they can only migrate cards over a whole FIID at a time.
12. For customers who use the message-based model for ATM Mobile Top-up transactions, the devices, device handlers, Transaction Context Manager (TCM) and Telco interface must all remain on BASE24. Only the authorization can be migrated to BASE24-eps if full support for message-based model Mobile Top-up is required. BASE24-eps does not support the message-based model.
13. For customers who use the definitions-based model for ATM Mobile Top-up transitions, the device handlers, the Transaction Context Manager (TCM) and the Telco interface must all be on the system that has the devices connected, during migration. If the devices remain on BASE24, so must all the modules listed above. When the devices are migrated over to BASE24-eps, the above modules/functions must migrate too.
14. For customers who perform POS Mobile Top-up transactions, the devices, device handlers, Transaction Context Manager (TCM) and Telco interface must all remain on BASE24. Only the authorization can be migrated to BASE24-eps if full

- support for POS Mobile Top-up is required. BASE24-eps does not support the acquiring of POS Mobile Top-up transactions.
15. Transaction surcharge fees will be calculated on the system that acquired the transaction, prior to routing the transaction to the authorizing system. In other words, if a device is “hooked” to BASE24, the surcharge amount for transactions received from that device will be calculated on BASE24 using BASE24 settings/configuration. Similarly, if a device is “hooked” to BASE24-eps, the surcharge amount for transactions received from that device will be calculated on BASE24-eps using BASE24-eps surcharge settings/configuration.
 16. Dynamic Currency Conversion (DCC) conversions will be performed on the system that acquired the transaction, prior to routing the transaction to the authorizing system. BASE24-eps does not currently support DCC.

Prerequisites

The Transaction Security Services Version 09.2 Service Pack 6 must be installed prior to implementation of this enhancement.

BASE24's Network First changes are required to be in place before these migration changes are added – see BA60UD0E.SCNMIGR1 for a complete list of the files affected by the Networks First enhancement.

Software Impacts

All BASE24 customers:

- ☐ Changes to BA60DDL.DDLGISO, DDLGPSTM, DDLGSTM AND DDLBATKN.
- ☐ Inline changes to BA60SRC.BATKNCVS and BATKNID
- ☐ Inline changes to BA60AFT.COBTKN
- ☐ Inline changes to BA60HISO.BAHISOS
- ☐ Updated documentation files BA60MISC.EMF, BAMISCTD and CONTENTS

All BASE24-atm customers:

- ☐ Inline changes to AT60AUTH.AUTHG, AUTHS and AUTHLIBS
- ☐ Inline changes to AT60HISO.ATHISOS, ATHISOM and ATHISOG
- ☐ Inline changes to AT60SETL.SETLS and SETLG
- ☐ Updated event (log) message manuals BA60LOGM.ATAUTH, ATSETL and ATHISO
- ☐ Updated documentation file BA60MISC.LCONFAT

All BASE24-atm Mobile Top-up customers:

- ☐ Inline changes to AT60TCM.ATCMG, ATCMLOGS and ATCMS

All BASE24-pos customers:

- ☐ Inline changes to PS60RTAU.RTAUG, ROUTERS, AUTHS and AUTHLIBS
- ☐ Inline changes to PS60HISO.PSHISOS, PSHISOM and PSHISOG
- ☐ Inline changes to PS60SETL.SETLS and SETLG
- ☐ Updated event (log) message manuals BA60LOGM.PSROUTER, PSSETL and PSHISO
- ☐ Updated documentation file BA60MISC.LCONFPS

All BASE24-pos Mobile Top-up customers:

- ☐ Inline changes to PS60TCM.PTCMG, PTCMLOGS and PTCMS

All BASE24-pos Hypercom customers:

- ☐ Inline changes to PS60HPDH.HPDHS

All BASE24-pos CRTAuth customers:

- ☐ Inline changes to BP60CRTA.CRTAUDHS

A complete list of the files affected by this enhancement can be found in the SCN file BA60UD0F.SCNMIGR2.

CUSTOMACS Changes

Not applicable

LCONF Assign Changes

This section describes the existing BASE24 assign records that are required to be present in the LCONF to support this enhancement. Details of the assigns are provided in the *BASE24 Logical Network Configuration File Manual*. These assigns already exist in the LCONFBA file located on the BA60MISC subvolume.

SAF

The Migration HISOs will need to use a different physical SAF from the HISOs used to communicate with the Host. This will allow a BASE24 customer who performs SAF extracts to migrate Interfaces to BASE24-eps and ensure that their Host receives the same data as before the migration. HISO will not need any code changes to support this; HISO already reads the LCONF for the SAF assign by specific process name.

Add an LCONF assign to define a SAF for each of the Migration HISO bridge processes. These bridge processes may share the same physical SAF file if a customer wishes.

LCONF Param Changes

This section describes the existing BASE24 param records that are required to be present in the LCONF to support this enhancement.

These params already exist in the LCONFBA file located on the BA60MISC subvolume.

MIGR-HISO-ENABLE

This param must be set to “Y” for the Migration HISOs and to “N” for other HISOs.

HOST-SELECTED-ACCT

This param must be set to False for each process that is acting as a Migration HISO.

SAF-PRIOR-TO-SEND

This param must be set to “Y” for each process that is acting as a Migration HISO.

This param already exists in the LCONFAT file located on the BA60MISC subvolume.

MIGR-ATM-ENABLE

This param must be set to “Y” if any Migration HISOs are processing in the system.

These params already exist in the LCONFPS file located on the BA60MISC subvolume.

ADJ-ADVICE-RC

This param must be set to “3” for each process that is acting as a Migration HISO. This ensures adjustments sent over the bridge contain response codes and not adjustment codes.

MIGR-POS-ENABLE

This param must be set to “Y” if any Migration HISOs are processing in the system.

This section describes the param records that must be added to the LCONF to support these changes. Details of the params are provided in the *BASE24 Logical Network Configuration File Manual*.

Samples of the following params are included in the LCONFAT file located on the BA60MISC subvolume.

MIGR-ATM-HISO-DEST

This param, used by the BASE24-atm Authorization process, the BASE24-atm Transaction Context Manager process and the BASE24-atm Settlement process, specifies the name of the service to which the Migration HISO processes belong, or the process name of the Migration HISO process. This service/process name will be used to determine the process to which log-only transactions and advices destined for BASE24-eps are to be sent.

There is no default value.

This param is only read by the appropriate processes if the LCONF param MIGR-ATM-ENABLE is set to “Y”.

MIGR-ATM-PROCESSING-OPTS

This param, used by the BASE24-atm Authorization process, the BASE24-atm Transaction Context Manager process, the BASE24-atm Host Interface process and the BASE24-atm Settlement process, specifies the migration-specific processing option that is to be performed. The valid values are:

- “0” - no log-onlys or advices sent to BASE24-eps for journaling,
- “1” - send log-onlys only to BASE24-eps for journaling,
- “2” - send advices only to BASE24-eps for journaling,
- “3” - send log-onlys and advices to BASE24-eps for journaling

The default value is “0” – no log-onlys or advices to be sent to BASE24-eps.

If the journal on BASE24-eps is to be used as the database of record, against which the extracts and reports are to be run, then this param must be set to “3” to ensure

that the BASE24-eps journal will contain details of all transactions and log-only records that are present on the BASE24-atm Transaction Log File (TLF).

If the BASE24-atm TLF is to be used as the database of record, against which the extracts and reports are to be run, then this param will be set to “0” as the BASE24-eps journal will not require copies of transactions and log-only records currently on the TLF.

This param is only read by the appropriate processes if the LCONF param MIGR-ATM-ENABLE is set to “Y”.

MIGR-ATM-ADVC-DESTxx

This series of params, used by the BASE24-atm Authorization process, specify the names of the Migration HISO processes that are used to handle advice transactions being sent between BASE24 and BASE24-eps during migration. Each unique process or service name must exist in this list; each entry must be differentiated by a unique two character value in place of the xx above. These params will be used to determine whether a message is destined for BASE24-eps or not, so that a determination can be made as to whether a reversal is required or an advice to be sent. Maximum of 50 entries allowed.

There is no default value.

This param is only read by the BASE24-atm Authorization process if the LCONF param MIGR-ATM-ENABLE is set to “Y” and MIGR-ATM-PROCESSING-OPTS param is set to “2” or “3”.

Samples of the following params are included in the LCONFPS file located on the BA60MISC subvolume.

MIGR-POS-HISO-DEST

This param, used by the BASE24-pos Router/Authorization process, the BASE24-pos Transaction Context Manager process and the BASE24-pos Settlement process, specifies the name of the service to which the Migration HISO processes belong, or the process name of the Migration HISO process. This service/process name will be used to determine the process to which log-only transactions and advices destined for BASE24-eps are to be sent.

There is no default value.

This param is only read by the appropriate processes if the LCONF param MIGR-POS-ENABLE is set to “Y”.

MIGR-POS-PROCESSING-OPTS

This param, used by the BASE24-pos Router/Authorization process, the BASE24-pos Transaction Context Manager process, the BASE24-pos Host Interface

process and the BASE24-pos Settlement process, specifies the migration-specific processing option that is to be performed. The valid values are:

- “0” - no log-onlys or advices sent to BASE24-eps for journaling,
- “1” - send log-onlys only to BASE24-eps for journaling,
- “2” - send advices only to BASE24-eps for journaling,
- “3” - send log-onlys and advices to BASE24-eps for journaling

The default value is “0” – no log-onlys or advices to be sent to BASE24-eps.

If the journal on BASE24-eps is to be used as the database of record, against which the extracts and reports are to be run, then this param will need to be set to “3” to ensure that the BASE24-eps journal will contain details of all transactions and log-only records that are present on the BASE24-pos Transaction Log File (PTLF).

If the BASE24-pos PTLF is to be used as the database of record, against which the extracts and reports are to be run, then this param must be set to “0” as the BASE24-eps journal will not require copies of transactions and log-only records currently on the TLF.

This param is only read by the appropriate processes if the LCONF param MIGR-POS-ENABLE is set to “Y”.

MIGR-POS-ADVC-DESTxx

This series of params, used by the BASE24-pos Router/Authorization process, specify the names of the Migration HISO processes that are used to handle advice transactions being sent between BASE24 and BASE24-eps during migration. Each unique process or service name must exist in this list; each entry must be differentiated by a unique two character value in place of the xx above. These params will be used to determine whether a message is destined for BASE24-eps or not, so that a determination can be made as to whether a reversal is required or an advice to be sent. Maximum of 50 entries allowed.

There is no default value.

This param is only read by the BASE24-pos Router/Authorization process if the LCONF param MIGR-POS-ENABLE is set to “Y” and MIGR-POS-PROCESSING-OPTS param is set to “2” or “3”.

Database Configuration

Host Configuration File (HCF)

HCF records will need to be set up appropriately for the customer’s current configuration. Each Migration HISO will need at least one HCF record to be configured, with a key that contains the DPC number that will be used for the connection to BASE24-eps, and details of the stations that are used to connect to

BASE24-eps. This DPC number will also be set up in the LCONF's MIGR-INTF-DPC-NUM parameter.

If a customer accepts Host Card Status updates from the Host, the DPC number used to communicate with BASE24-eps must be the same as the number currently being used to communicate with the Host. A customer may wish to define a separate Migration HISO to process Host Card status updates only. In this case the Migration HISO will use the same DPC number as used to communicate with the Host, and the remaining Migration HISOs (used for sending transactions to BASE24-eps) may (but are not required to) use a different DPC number. In this case the LCONF's MIGR-INTF-DPC-NUM parameter would be set to the value of the DPC number being used to send transactions to BASE24-eps.

For example:

Example 1: Customer uses the same Migration HISO(s) to handle Hot Card status updates as to handle transactions. The HISO that communicates to the HOST uses DPC 0001. All Migration HISOs will use DPC 0001. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0001.

Example 2: Customer uses a separate Migration HISO to handle Hot Card status updates. The HISO that communicates to the HOST uses DPC 0001. The Migration HISO that handles Hot Card status updates will use DPC 0001. The customer chooses to have the remaining Migration HISOs use the same DPC, DPC 0001. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0001.

Example 3: Customer uses a separate Migration HISO to handle Hot Card status updates. The HISO that communicates to the HOST uses DPC 0001. The Migration HISO that handles Hot Card status updates will use DPC 0001. The customer chooses to have the remaining Migration HISOs use a different DPC, DPC 0002. The LCONF's MIGR-INTF-DPC-NUM parameter will be set to 0002.

It is suggested that a separate Token Group be added for the Migration bridge records. This allows a customer to configure some tokens to be sent to the Host, while others are used over the Migration bridge only.

In order to allow this, the HCF records for each of the Migration HISO processes need to use a value for the Token Group (HCF screen 1) that is different from the value used for the Host's HISO processes.

If Terminal settlement totals are to be sent to BASE24-eps as log-only messages, the HCF records for the Migration HISO processes must be set to require an ack from DPC (HCF Screen 1). This will allow the HISO to process the responses from BASE24-eps.

BASE24-eps only supports variable format ISO messages over the bridge. In order to support this, the message format needs to be configured as '01' – variable format in the HCF records for the Migration HISO processes. For ATM this field is on screen 5, for POS this field is on screen 7.

The HCF screen 7 PSEM type field must not be set to “8” or “9” for Migration HISO processes.

External Message File (EMF)

Several changes are needed to the EMF records for the Migration HISO processes, in order for transactions to be processed correctly in a Migration system.

Sample EMF records applicable to a migration system are available in the sample EMF provided on BA60MISC. They are labelled with the process name P1A^MIGRHISO.

In addition, customers using specific Interfaces or processing certain transaction types may need additional field changes. Changes noted from ACI's testing are as follows:

- ☐ Customers processing POS transactions that originate from the VISA interface need to set the EMF records on BASE24 for field 18 to conditional
- ☐ Customers sending multiple account selection (OAR) messages to BASE24-eps must ensure that bit 122 is turned on in the EMF for those messages.

Customers are advised to verify their EMF settings to ensure that they will be appropriate for transaction processing in their specific migration system.

Token File (TKN)

This enhancement uses the following new token:

- ☐ Migration EPS HISO Token (Token ID 'M4').

This enhancement uses the following existing tokens:

- ☐ Migration ATM Data1 Token (Token ID 'M1').
- ☐ Migration POS Data1 Token (Token ID 'M2').

If any of these tokens are to be logged to the BASE24-pos Transaction Log File (PTLF), the BASE24-atm Transaction Log File (TLF) or the BASE24 Interchange Log File (ILF), the appropriate token records must be configured in the Token file.

If any of these tokens are to be extracted with the TLF, PTLF or ILF, sent to the host, or passed through the BIC ISO Interchange Interface, the appropriate records must be configured in the Token file.

It is suggested that a separate Token Group be added for the Migration bridge records. This allows a customer to configure some tokens to be sent to the Host, while others are used over the Migration bridge only. If this separate token group is defined, the M1, M2 and M4 tokens only need to be configured for the Migration bridge.

Note: Migration ATM Settlement Totals Token (Token ID 'M3") is defined internally in the DDLBATKN, and is used as a buffer to set up the ATM Settlement totals, but the actual token is not used over the Migration bridge. Instead the data is placed in the ISO Secondary Reserved 3 National field (Field 114). Token ID M3 does not need to be configured in the TKN file.

New Data Files

Not applicable

Template Changes

Not applicable

Device Configuration

Not applicable

Mega Table (MEGATBL) Changes

Not applicable

PI-Table Changes

Not applicable

SEG-Table Changes

Not applicable

Security Table (SECTBL) Changes

Not applicable

PATHCONF Changes

Not applicable

CRT Access Security Changes

Not applicable

Routing Changes

The PRECMD file used in SPROUTE routing, or the IDF routing table, or the AST file must be amended to route transactions to a Migration HISO process if the transaction needs to be routed to an interface now migrated to BASE24-eps.

Network Configuration

At least one Migration HISO process must be configured, with stations defined that communicate with the BASE24-eps HISO87 process. Multiple Migration HISO processes can be defined, as required by the customer's network configuration.

File Conversions

Not applicable

Host/Co-Network Impacts

Super Extract Process

Hosts need to be aware that the additional log-only transactions sent from BASE24-eps will be included in a (P)TLF extract. Similarly, advices sent from BASE24-eps will be included in a (P)TLF extract.

User/Operational Impacts

Performance Considerations

Routing transactions from BASE24 to BASE24-eps for authorization (or vice versa) will extend the transaction path and may result in reduced throughput compared to a customer's existing BASE24 system.

Alternate routing of transactions from BASE24-eps back to BASE24 will also extend the transaction path. The customer must evaluate their timer settings to ensure that they can process these transactions as required.

Event Messages

New event (log) messages were created as a result of this enhancement. Operators must be trained to recognize the new event messages and perform the appropriate remedy for a given message. Refer to the BA60LOGM.event message documentation files.

Vendor Impacts

Not applicable

Reference Documents

Not applicable

5: BASE24 Networks First Visa FRLF Modifications

This section describes the implementation requirements associated with the BASE24 Networks First Visa FRLF modifications.

The implementation requirements are identified using a standard format defined in Section 1.

For customers who have already installed Networks First, these modifications are required to allow file updates to be sent to VisaNet from the BASE24 VisaNet File Request Log (FRLF) screen, once the Visa Interface has been migrated from BASE24 to BASE24-eps.

Prior to migration, BASE24 customers used the FRLF screen to initiate a file update request to VisaNet in order to add a Visa card to the VISA Exception File. Before the addition of this modification, this functionality was not available during the migration from BASE24 to BASE24-eps, when the Visa Interface resided on BASE24-eps.

This modification adds support in BASE24 for operators to continue to make use of the FRLF Pathway screen to initiate these Visa Hot Card updates after the VisaNet Interface has been migrated to BASE24-eps. Changes that were made as part of the Network First enhancements will be a prerequisite for these modifications.

For customers who have migrated their Visa Interface to BASE24-eps, the FRLF Pathway screen can now be accessed directly from the BASE24 Pathway menu, rather than being accessed off the Visa Specific menu from the Visa ICF(E) record. The FRLF Pathway components, the requester, server and screen file, are now delivered on the From Host Maintenance (FHM) HISO subvolume. The Path server has been reconfigured to send the Hot Card requests to the Migration bridge process, rather than the BASE24 VisaInterface process.

The Migration bridge process now converts the Pathway request into an ISO 0300 file update message, and sends it to BASE24-eps where it is forwarded on to VisaNet. BASE24-eps responds with an 0310 file update response message, and the Migration bridge process formats and writes a records to the FRLF, allowing the details to be accessed by the customer via Pathway.

Assumptions and Restrictions

1. The BASE24 Pathway configuration for the Visa FRLF Path Server will be modified to specify the appropriate name of the Migration bridge process used to carry Visa Interface traffic to BASE24-eps.
2. Customers must have licensed the From Host Maintenance (FHM) HISO modules to be able to take this modification.
3. Only BASE24 was affected by this modification, no changes were made to BASE24-eps.

4. Only Visa Hot Card updates are being supported with this modification. MasterCard updates to BankNet are not supported with this modification.
5. The BASE24 Visa Interface, and its associated requesters and servers, were not affected by this modification. The FRLF DDL and the Requester and server code for the FRLF were copied to the FHM HISO subvolume for use in migration.
6. The FRLF Requester/Server conform to the PCI audit enhancement and create OMF records whenever the file is read. These records use the application code of "IH".

Prerequisites

The Transaction Security Services Version 09.2 Service Pack 6 must be installed prior to implementation of this enhancement.

BASE24's Network First changes are required to be in place before these migration changes are added – see BA60UD0E.SCNMIGR1 for a complete list of the files affected by the Networks First enhancement.

Software Impacts

All BASE24 customers:

- ☐ Changes to BA60AFT.SECTBL, MEGATBL and SVMHLPS.
- ☐ Inline changes to BA60HISO.BAHISOS and BAHISOG
- ☐ Updated documentation files BA60MISC.EMF.
- ☐ Updated event (log) message manuals BA60LOGM.BAHISO

All BASE24-fhm customers:

- ☐ Inline changes to FH60DDL.DDLGFHM, FHDDLMM and FHDDLMM
- ☐ Inline changes to FH60HISO.FHHISOS, FHHISOM and FHHISOMM
- ☐ Updated event (log) message manual BA60LOGM.FHMHISO
- ☐ Updated documentation file BA60MISC.LCONFFH
- ☐ New file FH60DDL.DDLFFRLF
- ☐ New files FH60HISO.RQFRLFM, RQFRLFS, SVFRLFM, SVFRLFS and SCRNFRFLF

A complete list of the files affected by this enhancement can be found in the SCN file BA60UD0G.SCNFRFLF.

CUSTOMACS Changes

Not applicable

LCONF Assign Changes

This section describes the existing BASE24 assign record that needs to be present in the LCONF to support this enhancement. Details of the assign are provided in the *BASE24 Logical Network Configuration File Manual*.

FRLF

The Migration HISO will now access the assign for the FRLF. Previously this assign existed and was accessed by the BASE24 Visa Interface.

LCONF Param Changes

This section describes the existing BASE24 param records that need to be present in the LCONF to support this enhancement. Details of the params are provided in the *BASE24 Logical Network Configuration File Manual*.

FRLF-NOTIFY-INTERVAL

FRLF-NOTIFY-PERCENTAGE

The Migration HISO will now access these parameters in order to provide percentage full management of the FRLF. Previously these params existed and were accessed by the BASE24 Visa Interface.

This section describes the param records that must be added to the LCONF to support these changes. Details of the params are provided in the *BASE24 Logical Network Configuration File Manual*.

MIGR-VFRLF-NAME

This param, used by the BASE24 Migration HISO bridge process, specifies a value that will be used by BASE24-eps to look up a file type, allowing BASE24-eps to route this Hot Card message to the correct Interface process. The value from this param will be used to fill in field 113 of the ISO 0300 message bound for BASE24-eps, and will allow BASE24-eps to access the BASE24 service/BASE24-eps file type mapping configuration and determine how to route this message. The value set in this param must exist in the BASE24 service/BASE24-eps file type mapping configuration datasource. For consistency with Hot Card messages sent in from a Host rather than via Pathway, ACI suggests that the value of this param is set to the name of the BASE24 Visa interface process that was used to process Visa transactions, prior to the migration of the Interface to BASE24-eps.

There is no default value.

All of the above assigns and params required for this modification are only read by the Migration HISO bridge process if the LCONF param MIGR-HISO-ENABLE is set

to “Y” to indicate that BASE24 to BASE24-eps Migration is occurring.

Samples of the above assigns and params are included in the LCONFFH file located on the BA60MISC subvolume.

Database Configuration

External Message File (EMF)

Several changes are needed to the EMF records for the 0300/0310 messages processed by the Migration HISO processes.

Sample EMF records applicable to a Networks First migration system using the Visa FRLF modification, are available in the sample EMF provided on BA60MISC. They are labelled with the process name P1A^MIGRHISON1.

Customers are advised to verify their EMF settings to ensure that they will be appropriate for transaction processing in their specific migration system.

New Data Files

Not applicable

Template Changes

Not applicable

Device Configuration

Not applicable

Mega Table (MEGATBL) Changes

The FRLF has been added to the list of requesters that use the extended message format, in the MEGATBL file.

PI-Table Changes

Not applicable

SEG-Table Changes

Not applicable

Security Table (SECTBL) Changes

Entries were added to the SECTBL to support the FRLF screens 1 and 2. This file will appear on the BASE Product Menu.

PATHCONF Changes

Add the Server-FRLF into Pathcom. Suggested settings are:

```
RESET SERVER
SET SERVER AUTORESTART 0
SET SERVER CPUS x:y
SET SERVER CREATEDELAY 1 MINS
SET SERVER DEBUG OFF
SET SERVER DELETEDELAY 20 MINS
SET SERVER HIGHPIN ON
SET SERVER HOMETERM \sys.$PLOG
SET SERVER LINKDEPTH 1
SET SERVER MAXSERVERS 1
SET SERVER NUMSTATIC 0
SET SERVER PRI 145
SET SERVER PROGRAM \sys.$volume.FH60OBJ.SVFRLF
SET SERVER TIMEOUT 60 SECS
SET SERVER TMF OFF
SET SERVER VOLUME \sys.$volume.LNETEXEC
```

ADD SERVER SERVER-VRLF

CRT Access Security Changes

Access to the FRLF screens must be added through the SEC requester for the appropriate users.

Routing Changes

Not applicable

Network Configuration

A change needs to be made to the station definition that is used for Server-Vpath. Instead of a destination of the BASE24 VISA Interface process name (e.g. P1A^VISA), the destination must now be set to the Migration bridge process that will carry Visa traffic to BASE24-eps, for example P1A^MIGRVISA.

File Conversions

Not applicable

Host/Co-Network Impacts

Not applicable

User/Operational Impacts

Event Messages

New event (log) messages were created as a result of this enhancement. Operators must be trained to recognize the new event messages and perform the appropriate remedy for a given message. Refer to the BA60LOGM.event message documentation files.

Vendor Impacts

Not applicable

Reference Documents

Not applicable