# SERVER INSTALLATION PROCEDURE FOR USING REXCS

- Install Latest Ubuntu OS version.
- Provide Railnet Static IP and ensure connectivity.

cd /etc/netplan sudo nano 00-installer-config.yaml

```
This is the network config written by 'subiquity'
network:
 ethernets:
   enp5s0:
    addresses:
     - 10.
                 89/23
     nameservers:
       addresses:
       - 203.153.44.44
       - 203.153.44.44
       - 203.153.41.28
       - 203.153.44.44
       - 203.153.41.28
       search:
       - 203.153.41.28
     routes:
     - to: default
       via: 10.
 version: 2
               Write Out ^W Where Is
  Help
                                       ^K Cut
                                                      Execute
                                                                    Location
                            Replace
```

Provide IP address for the server, gateway address and DNS accordingly. Save [cntrl+o] and Exit [cntrl+x]

- Install Desktop environment if required. Using following list of commands
  - o sudo apt update && apt upgrade
  - o sudo apt install ubuntu-desktop
  - o sudo apt install lightdm
  - o sudo systemctl start lightdm.service
  - o sudo service lightdm start

## To remove Desktop Environment:

- sudo apt autoremove ubuntu-desktop
- sudo systemctl stop lightdm.service
- sudo apt autoremove lightdm

1 | Page RExCS Admin

#### • Enable root password:

" sudo passwd root" then enter.

Type desired root password and Enter

Retype the password if asked and Enter

## Enable root login via SSH.

Open Terminal and login to root. [ie: type "su" and click enter, then provide root password.]

#nano /etc/ssh/sshd\_config

Check for the line #PermitRootLogin. Remove # from that line and make it as

PermitRootLogin yes

Save [cntrl+o] and Exit [cntrl+x]

systemctl restart sshd or

service sshd restart

## • Install REXCL and related software using install file

Open browser in the Server or any other workstation and go to

"github.com/ptiriset/Asterisk".

Click on "CODE" button and then Download files as ZIP file.

Extract the Downloaded ZIP file to any folder.

The extracted folder should have full permission. For that, need to do

"#chmod -R 777 'folderName'" in terminal.

Open that extracted folder where "install" file is available.

Open terminal from that folder (with root access preferably).

Type "./install" and click /Enter/ button.

Installation will start and will take few minutes to complete.

#### • Login to *RExCS* [10.187.1.2].

New user need to signup to use **REXCS.** The user account will be activated by Admin.

Once the account is activated, Login to **REXCS**.

For new Exchange creation, **Create new 'Registrar'** by providing all the necessary details including IP of the server, root username and Root password.

Create Intercoms in the Registrar,

Start creating Phone-accounts,

Other features required for the exchange also can be configured in the UI pages.

Then Save it to VOIP server by clicking "Save to Server" button.

The Created Registrar, ICOMs, accounts etc will be saved in the database of **REXCS** and can be edited or deleted any time by logging in with same user account.

2 | Page RExCS Admin