Questions & Answers

1. Write about the Data Link layer design issues.

Data Link Layer Design Issues:

The data link layer has a number of specific functions it can carry out. These functions include

- 1. Providing a well-defined service interface to the network layer.
- 2. Dealing with transmission errors.
- 3. Regulating the flow of data so that slow receivers are not swamped by fast senders.

To accomplish these goals, the data link layer takes the packets it gets from the network layer and encapsulates them into frames for transmission. Each frame contains a frame header, a payload field for holding the packet, and a frame trailer, as illustrated in Fig.1. Frame management forms the heart of what the data link layer does.




Fig.1. Relationship between packets and frames

In fact, in many networks, these functions are found only in the upper layers and not in the data link layer. However, no matter where they are found, the principles are pretty much the same, so it does not really matter where we study them. In the data link layer they often show up in their simplest and purest forms, making this a good place to examine them.

2. Discuss the services provided by the data link layer to the network layer.

Services Provided to the Network Layer:

The function of the data link layer is to provide services to the network layer. The principal service is transferring data from the network layer on the source machine to the network layer on the destination machine. On the source machine is an entity, call it a process, in the network layer that hands some bits to the data link layer for transmission to the destination. The job of the data link layer is to transmit the bits to the destination machine so they can be handed over to the network layer there, as shown in Fig. 2.1(a). The actual transmission follows the path of Fig. 2.1(b), but it is easier to think in terms of two data link layer processes communicating using a data link protocol.




Fig. 2.1. (a) Virtual communication (b) Actual communication

The data link layer can be designed to offer various services. The actual services offered can vary from system to system. Three reasonable possibilities that are commonly provided are

Questions & Answers

- 2. Acknowledged connectionless service.
- 3. Acknowledged connection-oriented service.

Let us consider each of these in turn:

Unacknowledged connectionless service consists of having the source machine send independent frames to the destination machine without having the destination machine acknowledge them. No logical connection is established beforehand or released afterward. If a frame is lost due to noise on the line, no attempt is made to detect the loss or recover from it in the data link layer. This class of service is appropriate when the error rate is very low so that recovery is left to higher layers. It is also appropriate for real-time traffic, such as voice, in which late data are worse than bad data. Most LANs use unacknowledged connectionless service in the data link layer.

The next step up in terms of reliability is acknowledged connectionless service. When this service is offered, there are still no logical connections used, but each frame sent is individually acknowledged. In this way, the sender knows whether a frame has arrived correctly. If it has not arrived within a specified time interval, it can be sent again. This service is useful over unreliable channels, such as wireless systems

It is perhaps worth emphasizing that providing acknowledgements in the data link layer is just an optimization, never a requirement. The network layer can always send a packet and wait for it to be acknowledged. If the acknowledgement is not forthcoming before the timer expires, the sender can just send the entire message again. The trouble with this strategy is that frames usually have a strict maximum length imposed by the hardware and network layer packets do not. If the average packet is broken up into, say, 10 frames, and 20 percent of all frames are lost, it may take a very long time for the packet to get through. If individual frames are acknowledged and retransmitted, entire packets get through much faster. On reliable channels, such as fiber, the overhead of a heavyweight data link protocol may be unnecessary, but on wireless channels, with their inherent unreliability, it is well worth the cost.

Getting back to our services, the most sophisticated service the data link layer can provide to the network layer is connection-oriented service. With this service, the source and destination machines establish a connection before any data are transferred. Each frame sent over the connection is numbered, and the data link layer guarantees that each frame sent is indeed received. Furthermore, it guarantees that each frame is received exactly once and that all frames are received in the right order. With connectionless service, in contrast, it is conceivable that a lost acknowledgement causes a packet to be sent several times and thus received several times. Connection-oriented service, in contrast, provides the network layer processes with the equivalent of a reliable bit stream.

Questions & Answers

When connection-oriented service is used, transfers go through three distinct phases. In the first phase, the connection is established by having both sides initialize variables and counters needed to keep track of which frames have been received and which ones have not. In the second phase, one or more frames are actually transmitted. In the third and final phase, the connection is released, freeing up the variables, buffers, and other resources used to maintain the connection.

Consider a typical example: a WAN subnet consisting of routers connected by point-to-point leased telephone lines. When a frame arrives at a router, the hardware checks it for errors (using techniques we will study late in this chapter), then passes the frame to the data link layer software (which might be embedded in a chip on the network interface board). The data link layer software checks to see if this is the frame expected, and if so, gives the packet contained in the payload field to the routing software. The routing software then chooses the appropriate outgoing line and passes the packet back down to the data link layer software, which then transmits it. The flow over two routers is shown in Fig.2.2.




Fig.2.2. Placement of the data link protocol

The routing code frequently wants the job done right, that is, with reliable, sequenced connections on each of the point-to-point lines. It does not want to be bothered too often with packets that got lost on the way. It is up to the data link protocol, shown in the dotted rectangle, to make unreliable communication lines look perfect or, at least, fairly good. As an aside, although we have shown multiple copies of the data link layer software in each router, in fact, one copy handles all the lines, with different tables and data structures for each one.

3. Explain the need of framing in detail in data link layer

Framing:

To provide service to the network layer, the data link layer must use the service provided to it by the physical layer. What the physical layer does is accept a raw bit stream and attempt to deliver it to the destination. This bit stream is not guaranteed to be error free. The number of bits received may be less than, equal to, or more than the number of bits transmitted, and they may have different values. It is up to the data link layer to detect and, if necessary, correct errors. The usual approach is for the data link layer to break the bit stream up into discrete frames and compute the checksum for each frame. When a frame arrives at the destination, the checksum is recomputed. If the newly computed checksum is different from the one contained in the frame, the data link layer knows that an error has occurred and takes steps to deal with it (e.g., discarding the bad frame and possibly also sending back an error report).

Breaking the bit stream up into frames is more difficult than it at first appears. One way to achieve this framing is to insert time gaps between frames, much like the spaces between words in ordinary text. However, networks rarely make any guarantees about timing, so it is possible these gaps might be squeezed out or other gaps might be inserted during transmission. Since it is too risky to count on timing to mark the start and end of each frame, other methods have been devised. We will look at four methods:

- 1. Character count.
- 2. Flag bytes with byte stuffing.
- 3. Starting and ending flags, with bit stuffing.
- 4. Physical layer coding violations.

The first framing method uses a field in the header to specify the number of characters in the frame. When the data link layer at the destination sees the character count, it knows how many characters follow and hence where the end of the frame is. This technique is shown in Fig.3.1(a) for four frames of sizes 5, 5, 8, and 8 characters, respectively.

Questions & Answers




Fig.3.1 A character stream. (a) Without errors. (b) With one error.

The trouble with this algorithm is that the count can be garbled by a transmission error. For example, if the character count of 5 in the second frame of Fig. 3.1(b) becomes a 7, the destination will get out of synchronization and will be unable to locate the start of the next frame. Even if the checksum is incorrect so the destination knows that the frame is bad, it still has no way of telling where the next frame starts. Sending a frame back to the source asking for a retransmission does not help either, since the destination does not know how many characters to skip over to get to the start of the retransmission. For this reason, the character count method is rarely used anymore.

The second framing method gets around the problem of resynchronization after an error by having each frame start and end with special bytes. In the past, the starting and ending bytes were different, but in recent years most protocols have used the same byte, called a flag byte, as both the starting and ending delimiter, as shown in Fig. 3.2(a) as FLAG. In this way, if the receiver ever loses synchronization, it can just search for the flag byte to find the end of the current frame. Two consecutive flag bytes indicate the end of one frame and start of the next one.




Fig. 3.2 (a) A frame delimited by flag bytes (b) Four examples of byte sequences before and after byte stuffing.

A serious problem occurs with this method when binary data, such as object programs or floating-point numbers, are being transmitted. It may easily happen that the flag byte's bit pattern occurs in the data. This situation will usually interfere with the framing. One way to solve this problem is to have the sender's data link layer insert a special escape byte (ESC) just before each "accidental" flag byte in the data. The data link layer on the receiving end removes the escape byte before the data are given to the network layer. This technique is called byte stuffing or character stuffing. Thus, a framing flag byte can be distinguished from one in the data by the absence or presence of an escape byte before it.

Of course, the next question is: What happens if an escape byte occurs in the middle of the data? The answer is that it, too, is stuffed with an escape byte. Thus, any single escape byte is part of an escape sequence, whereas a doubled one indicates that a single escape occurred naturally in the data. Some examples are shown in Fig. 3.3(b). In all cases, the byte sequence delivered after de stuffing is exactly the same as the original byte sequence.

The byte-stuffing scheme depicted in Fig. 3.3 is a slight simplification of the one used in the PPP protocol that most home computers use to communicate with their Internet service provider.

Questions & Answers

A major disadvantage of using this framing method is that it is closely tied to the use of 8-bit characters. Not all character codes use 8-bit characters. For example UNICODE uses 16-bit characters, As networks developed, the disadvantages of embedding the character code length in the framing mechanism became more and more obvious, so a new technique had to be developed to allow arbitrary sized characters.

The new technique allows data frames to contain an arbitrary number of bits and allows character codes with an arbitrary number of bits per character. It works like this. Each frame begins and ends with a special bit pattern, 011111110 (in fact, a flag byte). Whenever the sender's data link layer encounters five consecutive 1s in the data, it automatically stuffs a 0 bit into the outgoing bit stream. This bit stuffing is analogous to byte stuffing, in which an escape byte is stuffed into the outgoing character stream before a flag byte in the data.

When the receiver sees five consecutive incoming 1 bits, followed by a 0 bit, it automatically de stuffs (i.e., deletes) the 0 bit. Just as byte stuffing is completely transparent to the network layer in both computers, so is bit stuffing. If the user data contain the flag pattern, 01111110, this flag is transmitted as 011111010 but stored in the receiver's memory as 01111110.




Figure 3.3 Bit stuffing. (a) The original data. (b) The data as they appear on the line. (c) The data as they are stored in the receiver's memory after destuffing.

With bit stuffing, the boundary between two frames can be unambiguously recognized by the flag pattern. Thus, if the receiver loses track of where it is, all it has to do is scan the input for flag sequences, since they can only occur at frame boundaries and never within the data. The last method of framing is only applicable to networks in which the encoding on the physical medium contains some redundancy. For example, some LANs encode 1 bit of data by using 2 physical bits. Normally, a 1 bit is a high-low pair and a 0 bit is a low-high pair. The scheme means that every data bit has a transition in the middle, making it easy for the receiver to locate the bit boundaries. The combinations high-high and low-low are not used for data but are used for delimiting frames in some protocols.

Questions & Answers

As a final note on framing, many data link protocols use combination of a character count with one of the other methods for extra safety. When a frame arrives, the count field is used to locate the end of the frame. Only if the appropriate delimiter is present at that position and the checksum is correct is the frame accepted as valid. Otherwise, the input stream is scanned for the next delimiter.

4. Explain error correction and detection at the data link layer.

Error-Correcting Codes:

Network designers have developed two basic strategies for dealing with errors. One way is to include enough redundant information along with each block of data sent, to enable the receiver to deduce what the transmitted data must have been. The other way is to include only enough redundancy to allow the receiver to deduce that an error occurred, but not which error, and have it request a retransmission. The former strategy uses error-correcting codes and the latter uses error-detecting codes. The use of error-correcting codes is often referred to as forward error correction.

Each of these techniques occupies a different ecological niche. On channels that are highly reliable, such as fiber, it is cheaper to use an error detecting code and just retransmit the occasional block found to be faulty. However, on channels such as wireless links that make many errors, it is better to add enough redundancy to each block for the receiver to be able to figure out what the original block was, rather than relying on a retransmission, which itself may be in error.

To understand how errors can be handled, it is necessary to look closely at what an error really is. Normally, a frame consists of m data (i.e., message) bits and r redundant, or check, bits. Let the total length be n (i.e., n = m + r). An n-bit unit containing data and check bits is often referred to as an n-bit codeword.

Given any two code words, say, 10001001 and 10110001, it is possible to determine how many corresponding bits differ. In this case, 3 bits differ. To determine how many bits differ, just exclusive OR the two code words and count the number of 1 bits in the result, for example:

10001001 10110001 00111000

Questions & Answers

The number of bit positions in which two code words differ is called the Hamming distance. Its significance is that if two codewords are a Hamming distance d apart, it will require d single-bit errors to convert one into the other.

In most data transmission applications, all 2m possible data messages are legal, but due to the way the check bits are computed, not all of the 2n possible codewords are used. Given the algorithm for computing the check bits, it is possible to construct a complete list of the legal codewords, and from this list find the two codewords whose Hamming distance is minimum. This distance is the Hamming distance of the complete code. The error-detecting and error-correcting properties of a code depend on its Hamming distance. To detect d errors, you need a distance d + 1 code because with such a code there is no way that d single-bit errors can change a valid codeword into another valid codeword. When the receiver sees an invalid codeword, it can tell that a transmission error has occurred. Similarly, to correct d errors, you need a distance 2d + 1 code because that way the legal codewords are so far apart that even with d changes, the original codeword is still closer than any other codeword, so it can be uniquely determined. As a simple example of an error-detecting code, consider a code in which a single parity b appended to the data. The parity bit is chosen so that the number of 1 bits in the codeword is even (or odd).

For example, when 1011010 is sent in even parity, a bit is added to the end to make it 10110100. With odd parity 1011010 becomes 10110101. A code with a single parity bit has a distance 2, since any single-bit error produces a codeword with the wrong parity. It can be used to detect single errors.

As a simple example of an error-correcting code, consider a code with only four valid codewords:

0000000000, 0000011111, 11111100000, and 1111111111

This code has a distance 5, which means that it can correct double errors. If the codeword 0000000111 arrives, the receiver knows that the original must have been 0000011111. If, however, a triple error changes 00000000000 into 0000000111, the error will not be corrected properly.

Imagine that we want to design a code with m message bits and r check bits that will allow all single errors to be corrected. Each of the 2^m legal messages has n illegal codewords at a distance 1 from it. These are formed by systematically inverting each of the n bits in the n-bit codeword formed from it. Thus, each of the 2^m legal messages requires n + 1 bit patterns dedicated to it. Since the total number of bit patterns is 2^n , we must have $(n + 1)2m \le 2n$.

Questions & Answers

Using n = m + r, this requirement becomes $(m + r + 1) \le 2r$. Given m, this puts a lower limit on the number of check bits needed to correct single errors. This theoretical lower limit can, in fact, be achieved using a method due to Hamming (1950).

The bits of the codeword are numbered consecutively, starting with bit 1 at the left end, bit 2 to its immediate right, and so on. The bits that are powers of 2 (1, 2, 4, 8, 16, etc.) are check bits. The rest (3, 5, 6, 7, 9, etc.) are filled up with the m data bits. Each check bit forces the parity of some collection of bits, including itself, to be even (or odd). A bit may be included in several parity computations. To see which check bits the data bit in position k contributes to, rewrite k as a sum of powers of 2. For example, 11 = 1 + 2 + 8 and 29 = 1 + 4 + 8 + 16. A bit is checked by just those check bits occurring in its expansion (e.g., bit 11 is checked by bits 1, 2, and 8).

When a codeword arrives, the receiver initializes a counter to zero. It then examines each check bit, k (k = 1, 2, 4, 8 ...), to see if it has the correct parity. If not, the receiver adds k to the counter. If the counter is zero after all the check bits have been examined (i.e., if they were all correct), the codeword is accepted as valid. If the counter is nonzero, it contains the number of the incorrect bit. For example, if check bits 1, 2, and 8 are in error, the inverted bit is 11, because it is the only one checked by bits 1, 2, and 8. Figure 4.1 shows some 7-bit ASCII characters encoded as 11-bit codewords using a Hamming code. Remember that the data are found in bit positions 3, 5, 6, 7, 9, 10, and 11.

Char.	ASCII	Check bits
н	1001000	00110010000
a	1100001	10111001001
m	1101101	11101010101
m	1101101	11101010101
1	1101001	01101011001
n	1101110	01101010110
g	1100111	01111001111
	0100000	10011000000
C	1100011	11111000011
0	1101111	10101011111
d	1100100	11111001100
0	1100101	00111000101
		Order of bit transmission

Fig.4.1. Use of a Hamming code to correct burst errors

Hamming codes can only correct single errors. However, there is a trick that can be used to www.sppewnitdHamming codes to correct burst errors. A sequence of k consecutivewordsworld.com

Questions & Answers

arranged as a matrix, one codeword per row. Normally, the data would be transmitted one codeword at a time, from left to right. To correct burst errors, the data should be transmitted one column at a time, starting with the leftmost column. When all k bits have been sent, the second column is sent, and so on, as indicated in Fig.4.1. When the frame arrives at the receiver, the matrix is reconstructed, one column at a time. If a burst error of length k occurs, at most 1 bit in each of the k codewords will have been affected, but the Hamming code can correct one error per codeword, so the entire block can be restored. This method uses kr check bits to make blocks of km data bits immune to a single burst error of length k or less.

Error-Detecting Codes:

Error-correcting codes are widely used on wireless links, which are notoriously noisy and error prone when compared to copper wire or optical fibers. Without error-correcting codes, it would be hard to get anything through. However, over copper wire or fiber, the error rate is much lower, so error detection and retransmission is usually more efficient there for dealing with the occasional error. As a simple example, consider a channel on which errors are isolated and the error rate is 10-6 per bit. Let the block size be 1000 bits. To provide error correction for 1000-bit blocks, 10 check bits are needed; a megabit of data would require 10,000 check bits. To merely detect a block with a single 1-bit error, one parity bit per block will suffice. Once every 1000 blocks, an extra block (1001 bits) will have to be transmitted. The total overhead for the error detection + retransmission method is only 2001 bits per megabit of data, versus 10,000 bits for a Hamming code.

If a single parity bit is added to a block and the block is badly garbled by a long burst error, the probability that the error will be detected is only 0.5, which is hardly acceptable. The odds can be improved considerably if each block to be sent is regarded as rectangular matrix n bits wide and k bits high, as described above. A parity bit is computed separately for each column and affixed to the matrix as the last row. The matrix is then transmitted one row at a time. When the block arrives, the receiver checks all the parity bits. If any one of them is wrong, the receiver requests a retransmission of the block. Additional retransmissions are requested as needed until an entire block is received without any parity errors. This method can detect a single burst of length n, since only 1 bit per column will be changed. A burst of length n + 1 will pass undetected, however, if the first bit is inverted, the last bit is inverted, and all the other bits are correct. (A burst error does not imply that all the bits are wrong; it just implies that at least the first and last are wrong.) If the block is badly garbled by a long burst or by multiple shorter bursts, the probability that any of the n columns will have the correct parity, by accident, is 0.5, so the probability of a bad block being accepted when it should not be is 2⁻ⁿ.

Although the above scheme may sometimes be adequate, in practice, another method is in widespread use: the polynomial code, also known as a CRC (Cyclic Redundancy Check). Polynomial codes are based upon treating bit strings as representations of polynomials with

Questions & Answers

with k terms, ranging from x^{k-1} to x^0 . Such a polynomial is said to be of degree k-1. The high-order (leftmost) bit is the coefficient of x^{k-1} ; the next bit is the coefficient of x^{k-2} , and so on. For example, 110001 has 6 bits and thus represent a six-term polynomial with coefficients 1, 1, 0, 0, 0, and 1: x5 + x4 + x0.

Polynomial arithmetic is done modulo 2, according to the rules of algebraic field theory. There are no carries for addition or borrows for subtraction. Both addition and subtraction are identical to exclusive OR. For example:

Long division is carried out the same way as it is in binary except that the subtraction is done modulo 2, as above. A divisor is said "to go into" a dividend if the dividend has as many bits as the divisor. When the polynomial code method is employed, the sender and receiver must agree upon a generator polynomial, G(x), in advance. Both the high- and low-order bits of the generator must be 1. To compute the checksum for some frame with m bits, corresponding to the polynomial M(x), the frame must be longer than the generator polynomial. The idea is to append a checksum to the end of the frame in such a way that the polynomial represented by the checksummed frame is divisible by G(x). When the receiver gets the checksummed frame, it tries dividing it by G(x). If there is a remainder, there has been a transmission error.

The algorithm for computing the checksum is as follows:

- 1. Let r be the degree of G(x). Append r zero bits to the low-order end of the frame so it now contains m + r bits and corresponds to the polynomial $x^r M(x)$.
- 2. Divide the bit string corresponding to G(x) into the bit string corresponding to $x^r M(x)$, using modulo 2 division.
- 3. Subtract the remainder (which is always r or fewer bits) from the bit string corresponding to x^r M(x) using modulo 2 subtractions. The result is the checksummed frame to be transmitted. Call its polynomial T(x).


Figure illustrates the calculation for a frame 1101011011 using the generator G(x) = x4 + x + 1.

Questions & Answers

Frame : 1101011011

Generator: 10011

Message after 4 zero bits are appended: 11010110110000



Transmitted frame: 1101011111110

Fig.5.1. Calculation of the polynomial code checksum

6. Write short notes on an unrestricted simplex protocol and a stop and wait protocol.

An Unrestricted Simplex Protocol:

Questions & Answers

As an initial example we will consider a protocol that is as simple as it can be. Data are transmitted in one direction only. Both the transmitting and receiving network layers are always ready. Processing time can be ignored. Infinite buffer space is available. And best of all, the communication channel between the data link layers never damages or loses frames. This thoroughly unrealistic protocol, which we will nickname "utopia," is shown in Fig.6.1.

```
/* Protocol 1 (utopia) provides for data transmission in one direction only, from
  sender to receiver. The communication channel is assumed to be error free
  and the receiver is assumed to be able to process all the input infinitely quickly.
  Consequently, the sender just sits in a loop pumping data out onto the line as
  fast as it can. */
typedef enum {frame_arrival} event_type;
#include "protocol.h"
void sender1(void)
                                    /* buffer for an outbound frame */
 frame s:
 packet buffer;
                                    /* buffer for an outbound packet */
 while (true) {
     from_network_layer(&buffer); /* go get something to send */
                                    /* copy it into s for transmission */
     s.info = buffer:
     to_physical_layer(&s);
                                    /* send it on its way */
                                    /* Tomorrow, and tomorrow, and tomorrow,
                                      Creeps in this petty pace from day to day
                                      To the last syllable of recorded time.
                                         - Macbeth, V, v */
}
void receiver1(void)
 frame r:
 event_type event;
                                    /* filled in by wait, but not used here */
 while (true) {
     wait_for_event(&event);
                                    /* only possibility is frame_arrival */
                                    /* go get the inbound frame */
     from_physical_layer(&r);
     to_network_layer(&r.info);
                                    /* pass the data to the network layer */
```

Fig. 6.1 An unrestricted simplex protocol

The protocol consists of two distinct procedures, a sender and a receiver. The sender runs in the data link layer of the source machine, and the receiver runs in the data link layer of the destination machine. No sequence numbers or acknowledgements are used here, so MAX SEQ

Questions & Answers

is not needed. The only event type possible is frame_arrival (i.e., the arrival of an undamaged frame).

The sender is in an infinite while loop just pumping data out onto the line as fast as it can. The body of the loop consists of three actions: go fetch a packet from the (always obliging) network layer, construct an outbound frame using the variable s, and send the frame on its way. Only the info field of the frame is used by this protocol, because the other fields have to do with error and flow control and there are no errors or flow control restrictions here.

The receiver is equally simple. Initially, it waits for something to happen, the only possibility being the arrival of an undamaged frame. Eventually, the frame arrives and the procedure wait_for_event returns, with event set to frame_arrival (which is ignored anyway). The call to from_physical_layer removes the newly arrived frame from the hardware buffer and puts it in the variable r, where the receiver code can get at it. Finally, the data portion is passed on to the network layer, and the data link layer settles back to wait for the next frame, effectively suspending itself until the frame arrives.

A Simplex Stop-and-Wait Protocol:

The main problem we have to deal with here is how to prevent the sender from flooding the receiver with data faster than the latter is able to process them. In essence, if the receiver requires a time Δt to execute from_physical_layer plus to_network_layer, the sender must transmit at an average rate less than one frame per time Δt . Moreover, if we assume that no automatic buffering and queuing are done within the receiver's hardware, the sender must never transmit a new frame until the old one has been fetched by from_physical_layer, lest the new one overwrite the old one.

In certain restricted circumstances (e.g., synchronous transmission and a receiving data link layer fully dedicated to processing the one input line), it might be possible for the sender to simply insert a delay into protocol 1 to slow it down sufficiently to keep from swamping the receiver. However, more usually, each data link layer will have several lines to attend to, and the time interval between a frame arriving and its being processed may vary considerably. If the network designers can calculate the worst-case behavior of the receiver, they can program the sender to transmit so slowly that even if every frame suffers the maximum delay, there will be no overruns. The trouble with this approach is that it is too conservative. It leads to a bandwidth utilization that is far below the optimum, unless the best and worst cases are almost the same (i.e., the variation in the data link layer's reaction time is small).

A more general solution to this dilemma is to have the receiver provide feedback to the sender.

After having passed a packet to its network layer, the receiver sends a little dummy frame back

www.spte.theleender which, in effect, gives the sender permission to transmit the next frame Afteroid.com

Questions & Answers

having sent a frame, the sender is required by the protocol to bide its time until the little dummy (i.e., acknowledgement) frame arrives. Using feedback from the receiver to let the sender know when it may send more data is an example of the flow control mentioned earlier.

Protocols in which the sender sends one frame and then waits for an acknowledgement before proceeding are called stop-and-wait. Figure 6.2 gives an example of a simplex stop-and-wait protocol.

```
/* Protocol 2 (stop-and-wait) also provides for a one-directional flow of data from
 sender to receiver. The communication channel is once again assumed to be error
 free, as in protocol 1. However, this time, the receiver has only a finite buffer
 capacity and a finite processing speed, so the protocol must explicitly prevent
 the sender from flooding the receiver with data faster than it can be handled. */
typedef enum {frame_arrival} event_type;
#include "protocol.h"
void sender2(void)
 frame s:
                                     /* buffer for an outbound frame */
 packet buffer;
                                     /* buffer for an outbound packet */
 event_type event;
                                     /* frame_arrival is the only possibility */
 while (true) {
     from_network_layer(&buffer);
                                     /* go get something to send */
     s.info = buffer;
                                     /* copy it into s for transmission */
     to_physical_laver(&s);
                                     /* bye-bye little frame */
     wait_for_event(&event);
                                     /* do not proceed until given the go ahead */
void receiver2(void)
                                     /* buffers for frames */
 frame r, s;
 event_type event;
                                     /* frame_arrival is the only possibility */
 while (true) {
     wait_for_event(&event);
                                     /* only possibility is frame_arrival */
                                     /* go get the inbound frame */
     from_physical_layer(&r);
     to_network_layer(&r.info);
                                     /* pass the data to the network layer */
     to_physical_layer(&s);
                                     /* send a dummy frame to awaken sender */
}
}
```

Fig.6.2 A simplex stop-and-wait protocol

7. Write a short notes on stop and wait protocol in a very noisy channel.

A Simplex Protocol for a Noisy Channel:

An example of this kind of protocol is shown in Fig.7. Protocols in which the sender waits for a positive acknowledgement before advancing to the next data item are often called PAR (Positive Acknowledgement with Retransmission) or ARQ (Automatic Repeat reQuest). Like protocol 2, this one also transmits data only in one direction.

```
/* Protocol 3 (par) allows unidirectional data flow over an unreliable channel. ★/
 #define MAX_SEQ 1
                                               /* must be 1 for protocol 3 */
 typedef enum {frame_arrival, cksum_err, timeout} event_type;
  #include "protocol.h"
 void sender3(void)
                                               /* seq number of next outgoing frame */
   seg_nr next_frame_to_send;
   frame s:
                                               /* scratch variable */
                                               /* buffer for an outbound packet */
   packet buffer;
   event_type event;
                                               /* initialize outbound sequence numbers */
   next_frame_to_send = 0;
   from_network_layer(&buffer);
                                               /* fetch first packet */
   while (true) {
                                               /* construct a frame for transmission */
      s.info = buffer;
      s.seq = next_frame_to_send;
                                               /* insert sequence number in frame */
      to_physical_layer(&s);
                                               /* send it on its way */
      start_timer(s.seq);
                                               /* if answer takes too long, time out */
      wait_for_event(&event);
                                               /* frame_arrival, cksum_err, timeout */
      if (event == frame_arrival) {
           from_physical_layer(&s);
                                               /* get the acknowledgement */
           if (s.ack == next_frame_to_send) {
                stop_timer(s.ack);
                                               /* turn the timer off */
                from_network_layer(&buffer); /* get the next one to send */
                inc(next_frame_to_send);
                                               /* invert next_frame_to_send */
}
           }
```

Questions & Answers

```
void receiver3(void)
  seg_nr frame_expected;
  frame r, s;
  event_type event;
  frame_expected = 0;
  while (true) {
     wait_for_event(&event);
                                               /* possibilities: frame_arrival, cksum_err */
     if (event == frame_arrival) {
                                               /* a valid frame has arrived. */
           from_physical_layer(&r);
                                               /* go get the newly arrived frame */
                                               /* this is what we have been waiting for. */
           if (r.seq == frame_expected) {
               to_network_layer(&r.info);
                                               /* pass the data to the network layer */
               inc(frame_expected);
                                               /* next time expect the other sequence nr */
          s.ack = 1 - frame_expected;
                                               /* tell which frame is being acked */
          to_physical_layer(&s);
                                               /* send acknowledgement */
    }
}
```

Fig.7. A positive acknowledgement with retransmission protocol

8. Explain sliding window protocol.

Sliding Window Protocols:

In the previous protocols, data frames were transmitted in one direction only. In most practical situations, there is a need for transmitting data in both directions. One way of achieving full-duplex data transmission is to have two separate communication channels and use each one for simplex data traffic (in different directions). If this is done, we have two separate physical circuits, each with a "forward" channel (for data) and a "reverse" channel (for acknowledgements). In both cases the bandwidth of the reverse channel is almost entirely wasted. In effect, the user is paying for two circuits but using only the capacity of one. A better idea is to use the same circuit for data in both directions. After all, in protocols 2 and 3 it was already being used to transmit frames both ways, and the reverse channel has the same capacity as the forward channel. In this model the data frames from A to B are intermixed with the acknowledgement frames from A to B. By looking at the kind field in the header of an incoming frame, the receiver can tell whether the frame is data or acknowledgement.

Although interleaving data and control frames on the same circuit is an improvement over having two separate physical circuits, yet another improvement is possible. When a data frame arrives, instead of immediately sending a separate control frame, the receiver restrains itself and waits until the network layer passes it the next packet. The acknowledgement is attached to the outgoing data frame (using the ack field in the frame header). In effect, the acknowledgement gets a free ride on the next outgoing data frame. The technique of temporarily delaying outgoing

piggybacking. The principal advantage of using piggybacking over having distinct acknowledgement frames is a better use of the available channel bandwidth. The ack field in the frame header costs only a few bits, whereas a separate frame would need a header, the acknowledgement, and a checksum. In addition, fewer frames sent means fewer "frame arrival" interrupts, and perhaps fewer buffers in the receiver, depending on how the receiver's software is organized. In the next protocol to be examined, the piggyback field costs only 1 bit in the frame header. It rarely costs more than a few bits.




Fig.8.A sliding window of size 1, with a 3-bit sequence number (a) Initially (b) After the first frame has been sent (c) After the first frame has been received (d) After the first acknowledgement has been received.

Since frames currently within the sender's window may ultimately be lost or damaged in transit, the sender must keep all these frames in its memory for possible retransmission. Thus, if the maximum window size is n, the sender needs n buffers to hold the unacknowledged frames. If the window ever grows to its maximum size, the sending data link layer must forcibly shut off the network layer until another buffer becomes free. The receiving data link layer's window corresponds to the frames it may accept. Any frame falling outside the window is discarded without comment. When a frame whose sequence number is equal to the lower edge of the window is received, it is passed to the network layer, an acknowledgement is generated, and the window is rotated by one. Unlike the sender's window, the receiver's window always remains at its initial size. Note that a window size of 1 means that the data link layer only accepts frames in order, but for larger windows this is not so. The network layer, in contrast, is always fed data in the preper order regardless of the data link layer's window size. Figure 8 shows an example with

Questions & Answers

a maximum window size of 1. Initially, no frame are outstanding, so the lower and upper edges of the sender's window are equal, but as time goes on, the situation progresses as shown.

9. Explain the operation of one-bit sliding window protocol.

A One-Bit Sliding Window Protocol:

Before tackling the general case, let us first examine a sliding window protocol with a maximum window size of 1. Such a protocol uses stop-and-wait since the sender transmits a frame and waits for its acknowledgement before sending the next one. Figure 9.1 depicts such a protocol. Like the others, it starts out by defining some variables. Next_frame_to_send tells which frame the sender is trying to send. Similarly, frame_expected tells which frame the receiver is expecting. In both cases, 0 and 1 are the only possibilities.

Under normal circumstances, one of the two data link layers goes first and transmits the first frame. In other words, only one of the data link layer programs should contain the to_physical_layer and start_timer procedure calls outside the main loop. In the event that both data link layers start off simultaneously, a peculiar situation arises, as discussed later. The starting machine fetches the first packet from its network layer, builds a frame from it, and sends it. When this (or any) frame arrives, the receiving data link layer checks to see if it is a duplicate, just as in protocol 3. If the frame is the one expected, it is passed to the network layer and the receiver's window is slid up. The acknowledgement field contains the number of the last frame received without error. If this number agrees with the sequence number of the frame the sender is trying to send, the sender knows it is done with the frame stored in buffer and can fetch the next packet from its network layer. If the sequence number disagrees, it must continue trying to send the same frame. Whenever a frame is received, a frame is also sent back.

Now let us examine protocol 4 to see how resilient it is to pathological scenarios. Assume that computer A is trying to send its frame 0 to computer B and that B is trying to send its frame 0 to A. Suppose that A sends a frame to B, but A's timeout interval is a little too short. Consequently, A may time out repeatedly, sending a series of identical frames, all with seq = 0 and ack = 1.

Questions & Answers

```
/* Protocol 4 (sliding window) is bidirectional. */
#define MAX_SEQ 1
                                              /* must be 1 for protocol 4 */
typedef enum {frame_arrival, cksum_err, timeout} event_type;
#include "protocol.h"
void protocol4 (void)
                                              /* 0 or 1 only */
  seq_nr next_frame_to_send;
                                              /* 0 or 1 only */
  seq_nr frame_expected;
  frame r, s;
                                              /* scratch variables */
  packet buffer;
                                              /* current packet being sent */
  event_type event;
  next_frame_to_send = 0;
                                              /* next frame on the outbound stream */
  frame_expected = 0;
                                              /* frame expected next */
  from_network_layer(&buffer);
                                              /* fetch a packet from the network layer */
                                              /* prepare to send the initial frame */
  s.info = buffer;
  s.seq = next_frame_to_send;
                                              /* insert sequence number into frame */
  s.ack = 1 - frame_expected;
                                              /* piggybacked ack */
                                              /* transmit the frame */
  to_physical_layer(&s):
  start_timer(s.seq);
                                              /* start the timer running */
  while (true) {
     wait_for_event(&event);
                                              /* frame_arrival, cksum_err, or timeout */
     if (event == frame_arrival) {
                                              /* a frame has arrived undamaged. */
           from_physical_layer(&r);
                                              /* go get it */
           if (r.seq == frame_expected) {
                                              /* handle inbound frame stream. */
                to_network_layer(&r.info);
                                              /* pass packet to network layer */
                inc(frame_expected);
                                              /* invert seq number expected next */
           if (r.ack == next_frame_to_send) { /* handle outbound frame stream. */
                stop_timer(r.ack):
                                              /* turn the timer off */
                from_network_layer(&buffer); /* fetch new pkt from network layer */
                inc(next_frame_to_send);
                                              /* invert sender's sequence number */
     s.info = buffer;
                                              /* construct outbound frame */
     s.seg = next_frame_to_send;
                                              /* insert sequence number into it */
     s.ack = 1 - frame_expected;
                                              /* seg number of last received frame */
     to_physical_layer(&s);
                                              /* transmit a frame */
     start_timer(s.seq);
                                              /* start the timer running */
}
```

Fig.9.1 A 1-bit sliding window protocol

When the first valid frame arrives at computer B, it will be accepted and frame_expected will be set to 1. All the subsequent frames will be rejected because B is now expecting frames with sequence number 1, not 0. Furthermore, since all the duplicates have ack = 1 and B is still waiting for an acknowledgement of 0, B will not fetch a new packet from its network layer.

After every rejected duplicate comes in, B sends A a frame containing seq = 0 and ack = 0. Eventually, one of these arrives correctly at A, causing A to www.specworld.in 22 www.smartzworld.com

Questions & Answers

begin sending the next packet. No combination of lost frames or premature timeouts can cause the protocol to deliver duplicate packets to either network layer, to skip a packet, or to deadlock. However, a peculiar situation arises if both sides simultaneously send an initial packet. This synchronization difficulty is illustrated by Fig.9.2. In part (a), the normal operation of the protocol is shown. In (b) the peculiarity is illustrated. If B waits for A's first frame before sending one of its own, the sequence is as shown in (a), and every frame is accepted. However, if A and B simultaneously initiate communication, their first frames cross, and the data link layers then get into situation (b). In (a) each frame arrival brings a new packet for the network layer; there are no duplicates. In (b) half of the frames contain duplicates, even though there are no transmission errors. Similar situations can occur as a result of premature timeouts, even when one side clearly starts first. In fact, if multiple premature timeouts occur, frames may be sent three or more times.




Fig.9.2 Two scenarios for protocol 4 (a) Normal case (b) Abnormal case. The notation is (seq, ack, packet number). An asterisk indicates where a network layer accepts a packet.

10. Explain the sliding window protocol using Go-back-n protocol and using selective repeat.

A Protocol Using Go Back N:

Questions & Answers

Until now we have made the tacit assumption that the transmission time required for a frame to arrive at the receiver plus the transmission time for the acknowledgement to come back is negligible. Sometimes this assumption is clearly false. In these situations the long round-trip time can have important implications for the efficiency of the bandwidth utilization. As an example, consider a 50-kbps satellite channel with a 500-msec round-trip propagation delay. Let us imagine trying to use protocol 4 to send 1000-bit frames via the satellite. At t=0 the sender starts sending the first frame. At t=20 msec the frame has been completely sent. Not until t=270 msec has the frame fully arrived at the receiver, and not until t=520 msec has the acknowledgement arrived back at the sender, under the best of circumstances (no waiting in the receiver and a short acknowledgement frame). This means that the sender was blocked during 500/520 or 96 percent of the time. In other words, only 4 percent of the available bandwidth was used. Clearly, the combination of a long transit time, high bandwidth, and short frame length is disastrous in terms of efficiency.

The problem described above can be viewed as a consequence of the rule requiring a sender to wait for an acknowledgement before sending another frame. If we relax that restriction, much better efficiency can be achieved. Basically, the solution lies in allowing the sender to transmit up to w frames before blocking, instead of just 1. With an appropriate choice of w the sender will be able to continuously transmit frames for a time equal to the round-trip transit time without filling up the window. In the example above, w should be at least 26. The sender begins sending frame 0 as before. By the time it has finished sending 26 frames, at t = 520, the acknowledgement for frame 0 will have just arrived. Thereafter, acknowledgements arrive every 20 msec, so the sender always gets permission to continue just when it needs it. At all times, 25 or 26 unacknowledged frames are outstanding. Put in other terms, the sender's maximum window size is 26.

The need for a large window on the sending side occurs whenever the product of bandwidth x round-trip-delay is large. If the bandwidth is high, even for a moderate delay, the sender will exhaust its window quickly unless it has a large window. If the delay is high (e.g., on a geostationary satellite channel), the sender will exhaust its window even for a moderate bandwidth. The product of these two factors basically tells what the capacity of the pipe is, and the sender needs the ability to fill it without stopping in order to operate at peak efficiency.

This technique is known as pipelining. If the channel capacity is b bits/sec, the frame size 1 bits, and the round-trip propagation time R sec, the time required to transmit a single frame is 1/b sec. After the last bit of a data frame has been sent, there is a delay of R/2 before that bit arrives at the receiver and another delay of at least R/2 for the acknowledgement to come back, for a total delay of R. In stop-and-wait the line is busy for 1/band idle for R, giving

line utilization = l/(l + bR)

Questions & Answers

If l < bR, the efficiency will be less than 50 percent. Since there is always a nonzero delay for the acknowledgement to propagate back, pipelining can, in principle, be used to keep the line busy during this interval, but if the interval is small, the additional complexity is not worth the trouble.

Pipelining frames over an unreliable communication channel raises some serious issues. First, what happens if a frame in the middle of a long stream is damaged or lost? Large numbers of succeeding frames will arrive at the receiver before the sender even finds out that anything is wrong. When a damaged frame arrives at the receiver, it obviously should be discarded, but what should the receiver do with all the correct frames following it? Remember that the receiving data link layer is obligated to hand packets to the network layer in sequence. In Fig. 10.1 we see the effects of pipelining on error recovery.




Fig.10.1. Pipelining and error recovery Effect of an error when (a) receiver's window size is 1 and (b) receiver's window size is large

Two basic approaches are available for dealing with errors in the presence of pipelining. One way, called go back n, is for the receiver simply to discard all subsequent frames, sending no acknowledgements for the discarded frames. This strategy corresponds to a receive window of size 1. In other words, the data link layer refuses to accept any frame except the next one it must give to the network layer. If the sender's window fills up before the timer runs out, the pipeline will begin to empty. Eventually, the sender will time out and retransmit all unacknowledged

Questions & Answers

frames in order, starting with the damaged or lost one. This approach can waste a lot of bandwidth if the error rate is high.

In Fig.10.1 (a) we see go back n for the case in which the receiver's window is large. Frames 0 and 1 are correctly received and acknowledged. Frame 2, however, is damaged or lost. The sender, unaware of this problem, continues to send frames until the timer for frame 2 expires. Then it backs up to frame 2 and starts all over with it, sending 2, 3, 4, etc. all over again.

The other general strategy for handling errors when frames are pipelined is called selective repeat. When it is used, a bad frame that is received is discarded, but good frames received after it are buffered. When the sender times out, only the oldest unacknowledged frame is retransmitted. If that frame arrives correctly, the receiver can deliver to the network layer, in sequence, all the frames it has buffered. Selective repeat is often combined with having the receiver send a negative acknowledgement (NAK) when it detects an error, for example, when it receives a checksum error or a frame out of sequence. NAKs stimulate retransmission before the corresponding timer expires and thus improve performance.

In Fig.10.1 (b), frames 0 and 1 are again correctly received and acknowledged and frame 2 is lost. When frame 3 arrives at the receiver, the data link layer there notices that is has missed a frame, so it sends back a NAK for 2 but buffers 3. When frames 4and 5 arrive, they, too, are buffered by the data link layer instead of being passed to the network layer. Eventually, the NAK 2 gets back to the sender, which immediately resends frame 2. When that arrives, the data link layer now has 2, 3, 4, and 5 and can pass all of them to the network layer in the correct order. It can also acknowledge all frames up to and including 5, as shown in the figure. If the NAK should get lost, eventually the sender will time out for frame 2 and send it (and only it) of its own accord, but that may be a quite a while later. In effect, the NAK speeds up the retransmission of one specific frame.

Questions & Answers

```
/* Protocol 5 (go back n) allows multiple outstanding frames. The sender may transmit up
 to MAX_SEQ frames without waiting for an ack. In addition, unlike in the previous
 protocols, the network layer is not assumed to have a new packet all the time. Instead,
 the network layer causes a network_layer_ready event when there is a packet to send. */
#define MAX_SEQ 7
                                          /* should be 2 n - 1 */
typedef enum {frame_arrival, cksum_err, timeout, network_layer_ready} event_type;
#include "protocol.h"
static boolean between(seq_nr a, seq_nr b, seq_nr c)
/* Return true if a <=b < c circularly; false otherwise. */
 if (((a \le b) \&\& (b < c)) || ((c < a) \&\& (a <= b)) || ((b < c) \&\& (c < a)))
     return(true);
  else
     return(false);
static void send_data(seq_nr frame_nr, seq_nr frame_expected, packet buffer[])
/* Construct and send a data frame. */
                                          /* scratch variable */
 frame s:
 s.info = buffer[frame_nr];
                                          /* insert packet into frame */
 s.seq = frame_nr;
                                          /* insert sequence number into frame */
 s.ack = (frame_expected + MAX_SEQ) % (MAX_SEQ + 1);/* piggyback ack */
                                          /* transmit the frame */
 to_physical_layer(&s);
 start_timer(frame_nr);
                                          /* start the timer running */
```

Questions & Answers

```
void protocol5(void)
                                         /* MAX_SEQ > 1; used for outbound stream */
 seg_nr next_frame_to_send;
 seq_nr ack_expected;
                                         /* oldest frame as yet unacknowledged */
 seq_nr frame_expected;
                                         /* next frame expected on inbound stream */
 frame r;
                                         /* scratch variable */
 packet buffer[MAX_SEQ + 1];
                                         /* buffers for the outbound stream */
 seq_nr nbuffered;
                                         /* # output buffers currently in use */
                                         /* used to index into the buffer array */
 seq_nri;
 event_type event;
                                         /* allow network_layer_ready events */
 enable_network_layer();
 ack_expected = 0;
                                         /* next ack expected inbound */
 next_frame_to_send = 0;
                                         /* next frame going out */
 frame_expected = 0;
                                         /* number of frame expected inbound */
                                         /* initially no packets are buffered */
 nbuffered = 0;
 while (true) {
   wait_for_event(&event);
                                         /* four possibilities: see event_type above */
   switch(event) {
                                         /* the network layer has a packet to send */
    case network_layer_ready:
         /* Accept, save, and transmit a new frame. */
         from_network_layer(&buffer[next_frame_to_send]); /* fetch new packet */
         nbuffered = nbuffered + 1;
                                         /* expand the sender's window */
         send_data(next_frame_to_send, frame_expected, buffer);/* transmit the frame */
         inc(next_frame_to_send);
                                         /* advance sender's upper window edge */
         break;
    case frame_arrival:
                                         /* a data or control frame has arrived */
         from_physical_layer(&r);
                                         /* get incoming frame from physical layer */
         if (r.seg == frame_expected) {
              /* Frames are accepted only in order. */
              to_network_layer(&r.info); /* pass packet to network layer */
              inc(frame_expected);
                                         /* advance lower edge of receiver's window */
```

Fig.10.2 A sliding window protocol using go back n

Selective repeat corresponds to a receiver window larger than 1. Any frame within the window may be accepted and buffered until all the preceding ones have been passed to the network layer. This approach can require large amounts of data link layer memory if the window is large. These two alternative approaches are trade-offs between bandwidth and data link layer buffer space. Depending on which resource is scarcer, one or the other can be used. Figure 10.2 shows a pipelining protocol in which the receiving data link layer only accepts frames in order; frames following an error are discarded. In this protocol, for the first time we have dropped the assumption that the network layer always has an infinite supply of packets to send. When the network layer has a packet it wants to send, it can cause a network_layer_ready event to happen. However, to enforce the flow control rule of no more than MAX_SEQ unacknowledged frames outstanding at any time, the data link layer must be able to keep the network layer from bothering it with more work. The library procedures enable_network_layer and disable network layer do this job.

Questions & Answers

A Protocol Using Selective Repeat

This protocol works well if errors are rare, but if the line is poor, it wastes a lot of bandwidth on retransmitted frames. An alternative strategy for handling errors is to allow the receiver to accept and buffer the frames following a damaged or lost one. Such a protocol does not discard frames merely because an earlier frame was damaged or lost. In this protocol, both sender and receiver maintain a window of acceptable sequence numbers. The sender's window size starts out at 0 and grows to some predefined maximum, MAX_SEQ. The receiver's window, in contrast, is always fixed in size and equal to MAX_SEQ. The receiver has a buffer reserved for each sequence number within its fixed window. Associated with each buffer is a bit (arrived) telling whether the buffer is full or empty. Whenever a frame arrives, its sequence number is checked by the function between to see if it falls within the window. If so and if it has not already been received, it is accepted and stored. This action is taken without regard to whether or not it contains the next packet expected by the network layer. Of course, it must be kept within the data link layer and not passed to the network layer until all the lower-numbered frames have already been delivered to the network layer in the correct order.

Questions & Answers

```
/* Protocol 6 (selective repeat) accepts frames out of order but passes packets to the
  network layer in order. Associated with each outstanding frame is a timer. When the timer
  expires, only that frame is retransmitted, not all the outstanding frames, as in protocol 5. */
#define MAX_SEQ 7
                                                 /* should be 2"n - 1 */
#define NR_BUFS ((MAX_SEQ + 1)/2)
typedef enum (frame_arrival, cksum_err, timeout, network_layer_ready, ack_timeout) event_type
#include "protocol.h"
boolean no_nak = true;
                                                 /* no nak has been sent yet */
seg_nr oldest_frame = MAX_SEQ + 1:
                                                 /* initial value is only for the simulator */
static boolean between(seg_nr a, seg_nr b, seg_nr c)
/* Same as between in protocol5, but shorter and more obscure. */
 return ((a <= b) && (b < c)) || ((c < a) && (a <= b)) || ((b < c) && (c < a));
static void send_frame(frame_kind fk, seq_nr frame_nr, seq_nr frame_expected, packet buffer[])
/* Construct and send a data, ack, or nak frame. */
 frame s:
                                                 /* scratch variable */
 s.kind = fk:
                                                 /* kind == data, ack, or nak */
 if (fk == data) s.info = buffer[frame_nr % NR_BUFS];
 s.seq = frame_nr;
                                                 /* only meaningful for data frames */
 s.ack = (frame_expected + MAX_SEQ) % (MAX_SEQ + 1);
 if (fk == nak) no_nak = false;
                                                 /* one nak per frame, please */
                                                 /* transmit the frame */
 to physical layer(&s);
 if (fk == data) start_timer(frame_nr % NR_BUFS);
 stop ack timer();
                                                 /* no need for separate ack frame */
void protocol6(void)
 seg nr ack expected;
                                                 /* lower edge of sender's window */
                                                 /* upper edge of sender's window + 1 */
 seq_nr next_frame_to_send;
 seg_nr frame_expected;
                                                 /* lower edge of receiver's window */
                                                 /* upper edge of receiver's window + 1 */
 seq_nr too_far;
                                                 /* index into buffer pool */
 int i:
                                                 /* scratch variable */
 frame r;
 packet out_buf[NR_BUFS];
                                                 /* buffers for the outbound stream */
 packet in_buf[NR_BUFS];
                                                 /* buffers for the inbound stream */
```

Questions & Answers

```
boolean arrived[NR_BUFS];
                                               /* inbound bit map */
seq_nr nbuffered;
                                               /* how many output buffers currently used */
event_type event;
enable_network_layer();
                                               /* initialize */
ack_expected = 0:
                                               /* next ack expected on the inbound stream */
next frame to send = 0;
                                               /* number of next outgoing frame */
frame_expected = 0;
too_far = NR_BUFS:
                                               /* initially no packets are buffered */
nbuffered = 0:
for (i = 0; i < NR_BUFS; i++) arrived[i] = false;
while (true) {
  wait for event(&event);
                                               /* five possibilities: see event_type above */
  switch(event) {
   case network_layer_ready:
                                               /* accept, save, and transmit a new frame */
        nbuffered = nbuffered + 1;
                                               /* expand the window */
        from_network_layer(&out_buf[next_frame_to_send % NR_BUFS]); /* fetch new packet */
        send_frame(data, next_frame_to_send, frame_expected, out_buf):/* transmit the frame */
                                               /* advance upper window edge */
        inc(next_frame_to_send);
        break:
   case frame arrival:
                                               /* a data or control frame has arrived */
        from_physical_layer(&r);
                                               /* fetch incoming frame from physical layer */
        if (r.kind == data) {
             /* An undamaged frame has arrived. */
             if ((r.seq != frame_expected) && no_nak)
                send_frame(nak, 0, frame_expected, out_buf); else start_ack_timer();
             if (between(frame_expected,r.seq,too_far) && (arrived[r.seq%NR_BUFS]==false)) {
                  /* Frames may be accepted in any order. */
                  arrived[r.seq % NR_BUFS] = true; /* mark buffer as full */
                  in_buf[r.seq % NR_BUFS] = r.info; /* insert data into buffer */
                  while (arrived[frame_expected % NR_BUFS]) {
                       /* Pass frames and advance window. */
                       to_network_layer(&in_buf[frame_expected % NR_BUFS]);
                       no nak = true:
                       arrived[frame_expected % NR_BUFS] = false;
```

Fig.10.3 A sliding window protocol using selective repeat

11. Give the detailed description of HDLC frame format.

Data Link Protocols:

The first one, HDLC, is a classical bit-oriented protocol whose variants have been in use for decades in many applications. The second one, PPP, is the data link protocol used to connect home computers to the Internet.

HDLC—High-Level Data Link Control:

These are a group of closely related protocols that are a bit old but are still heavily used. They are all derived from the data link protocol first used in the IBM mainframe world: SDLC (Synchronous Data Link Control) protocol. After developing SDLC, IBM submitted it to ANSI and ISO for acceptance as U.S. and international standards, respectively. ANSI modified it to become ADCCP (Advanced Data Communication Control Procedure), and ISO modified it to become HDLC (High-level Data Link Control). CCITT then adopted and modified HDLC for its LAP (Link Access Procedure) as part of the X.25 network interface standard but later modified it again to LAPB, to make it more compatible with a later version of HDLC. The nice thing about standards is that you have so many to choose from. Furthermore, if you do not like any of them, you can just wait for next year's model. These protocols are based on the same principles. All are bit oriented, and all use bit stuffing for data transparency. They differ only in minor, but nevertheless irritating, ways. The discussion of bit-oriented protocols that follows is intended as a general introduction. For the specific details of any one protocol, please consult the appropriate definition.

All the bit-oriented protocols use the frame structure shown in Fig.11.1. The Address field is primarily of importance on lines with multiple terminals, where it is used to identify one of the terminals. For point-to-point lines, it is sometimes used to distinguish commands from responses.



Fig.11.1. Frame format for bit-oriented protocols

Questions & Answers

The Data field may contain any information. It may be arbitrarily long, although the efficiency of the checksum falls off with increasing frame length due to the greater probability of multiple burst errors.

The Checksum field is a cyclic redundancy code. The frame is delimited with another flag sequence (01111110). On idle point-to-point lines, flag sequences are transmitted continuously. The minimum frame contains three fields and totals 32 bits, excluding the flags on either end.

The contents of the Control field for these three kinds are shown in Fig.11.2. The protocol uses a sliding window, with a 3-bit sequence number. Up to seven unacknowledged frames may be outstanding at any instant. The Seq field in Fig.11.2 (a) is the frame sequence number. The Next field is a piggybacked acknowledgement. However, all the protocols adhere to the convention that instead of piggybacking the number of the last frame received correctly, they use the number of the first frame not yet received (i.e., the next frame expected). The choice of using the last frame received or the next frame expected is arbitrary; it does not matter which convention is used, provided that it is used consistently.




Fig.11.2 Control field of (a) an information frame, (b) a supervisory frame, (c) an unnumbered frame

The P/F bit stands for Poll/Final. It is used when a computer (or concentrator) is polling a group of terminals. When used as P, the computer is inviting the terminal to send data. All the frames sent by the terminal, except the final one, have the P/F bit set to P. The final one is set to F. In some of the protocols, the P/F bit is used to force the other machine to send a Supervisory frame immediately rather than waiting for reverse traffic onto which to piggyback the window information. The bit also has some minor uses in connection with the Unnumbered frames.

The various kinds of Supervisory frames are distinguished by the Type field. Type 0 is an acknowledgement frame (officially called RECEIVE READY) used to indicate the next frame expected. This frame is used when there is no reverse traffic to use for piggybacking.

Type 1 is a negative acknowledgement frame (officially called REJECT). It is used to indicate that a transmission error has been detected. The Next field indicates the first frame in sequence www.spectremed correctly (i.e., the frame to be retransmitted). The sender is required to retransmit abortle.com

Questions & Answers

outstanding frames starting at Next. This strategy is similar to our protocol 5 rather than our protocol 6.

Type 2 is RECEIVE NOT READY. It acknowledges all frames up to but not including Next, just as RECEIVE READY does, but it tells the sender to stop sending. RECEIVE NOT READY is intended to signal certain temporary problems with the receiver, such as a shortage of buffers, and not as an alternative to the sliding window flow control. When the condition has been repaired, the receiver sends a RECEIVE READY, REJECT, or certain control frames.

Type 3 is the SELECTIVE REJECT. It calls for retransmission of only the frame specified. In this sense it is like our protocol 6 rather than 5 and is therefore most useful when the sender's window size is half the sequence space size, or less. Thus, if a receiver wishes to buffer out-of-sequence frames for potential future use, it can force the retransmission of any specific frame using Selective Reject. HDLC and ADCCP allow this frame type, but SDLC and LAPB do not allow it (i.e., there is no Selective Reject), and type 3 frames are undefined.

The third class of frame is the Unnumbered frame. It is sometimes used for control purposes but can also carry data when unreliable connectionless service is called for. The various bit-oriented protocols differ considerably here, in contrast with the other two kinds, where they are nearly identical. Five bits are available to indicate the frame type, but not all 32 possibilities are used.

12. Explain the working of the data link layer in the internet.

The Data Link Layer in the Internet:

The Internet consists of individual machines (hosts and routers) and the communication infrastructure that connects them. Within a single building, LANs are widely used for interconnection, but most of the wide area infrastructure is built up from point-to-point leased lines.

In practice, point-to-point communication is primarily used in two situations. First, thousands of organizations have one or more LANs, each with some number of hosts (personal computers, user workstations, servers, and so on) along with a router (or a bridge, which is functionally similar). Often, the routers are interconnected by a backbone LAN. Typically, all connections to the outside world go through one or two routers that have point-to-point leased lines to distant routers. It is these routers and their leased lines that make up the communication subnets on which the Internet is built.

The second situation in which point-to-point lines play a major role in the Internet is the millions of individuals who have home connections to the Internet using modems and dial-up telephone lines. Usually, what happens is that the user's home PC calls up an Internet service provider's router and then acts like a full-blown Internet host. This method of operation is

Questions & Answers

no different from having a leased line between the PC and the router, except that the connection is terminated when the user ends the session. A home PC calling an Internet service provider is illustrated in Fig.12. The modem is shown external to the computer to emphasize its role, but modern computers have internal modems.




Fig.12. A home personal computer acting as an Internet host

13. Explain the point-to-point protocol with frame format. Explain how it provides the facility through link control protocol and network control protocol.

PPP-The Point-to-Point Protocol:

The Internet needs a point-to-point protocol for a variety of purposes, including router-to-router traffic and home user-to-ISP traffic. This protocol is PPP (Point-to-Point Protocol), which is defined in RFC 1661 and further elaborated on in several other RFCs (e.g., RFCs 1662 and 1663). PPP handles error detection, supports multiple protocols, allows IP addresses to be negotiated at connection time, permits authentication, and has many other features. PPP provides three features:

- 1. A framing method that unambiguously delineates the end of one frame and the start of the next one. The frame format also handles error detection.
- 2. A link control protocol for bringing lines up, testing them, negotiating options, and bringing them down again gracefully when they are no longer needed. This protocol is called LCP (Link

Questions & Answers

Control Protocol). It supports synchronous and asynchronous circuits and byte-oriented and bit-oriented encodings.

3. A way to negotiate network-layer options in a way that is independent of the network layer protocol to be used. The method chosen is to have a different NCP (Network Control Protocol) for each network layer supported.

To see how these pieces fit together, let us consider the typical scenario of a home user calling up an Internet service provider to make a home PC a temporary Internet host. The PC first calls the provider's router via a modem. After the router's modem has answered the phone and established a physical connection, the PC sends the router a series of LCP packets in the payload field of one or more PPP frames. These packets and their responses select the PPP parameters to be used.

Once the parameters have been agreed upon, a series of NCP packets are sent to configure the network layer. Typically, the PC wants to run a TCP/IP protocol stack, so it needs an IP address. There are not enough IP addresses to go around, so normally each Internet provider gets a block of them and then dynamically assigns one to each newly attached PC for the duration of its login session. If a provider owns n IP addresses, it can have up to n machines logged in simultaneously, but its total customer base may be many times that. The NCP for IP assigns the IP address. At this point, the PC is now an Internet host and can send and receive IP packets, just as hardwired hosts can. When the user is finished, NCP tears down the network layer connection and frees up the IP address. Then LCP shuts down the data link layer connection. Finally, the computer tells the modem to hang up the phone, releasing the physical layer connection.

The PPP frame format was chosen to closely resemble the HDLC frame format, since there was no reason to reinvent the wheel. The major difference between PPP and HDLC is that PPP is character oriented rather than bit oriented. In particular, PPP uses byte stuffing on dial-up modem lines, so all frames are an integral number of bytes. It is not possible to send a frame consisting of 30.25 bytes, as it is with HDLC. Not only can PPP frames be sent over dial-up telephone lines, but they can also be sent over SONET or true bit-oriented HDLC lines (e.g., for router-router connections). The PPP frame format is shown in Fig.13.




Fig.13. The PPP full frame format for unnumbered mode operation

All PPP frames begin with the standard HDLC flag byte (01111110), which is byte stuffed if it occurs within the payload field. Next comes the Address field, which is always set to the binary value 11111111 to indicate that all stations are to accept the frame. Using this value avoids the issue of having to assign data link addresses.

Questions & Answers

The Address field is followed by the Control field, the default value of which is 00000011. This value indicates an unnumbered frame. In other words, PPP does not provide reliable transmission using sequence numbers and acknowledgements as the default. In noisy environments, such as wireless networks, reliable transmission using numbered mode can be used. The exact details are defined in RFC 1663, but in practice it is rarely used. Since the Address and Control fields are always constant in the default configuration, LCP provides the necessary mechanism for the two parties to negotiate an option to just omit them altogether and save 2 bytes per frame.

The fourth PPP field is the Protocol field. Its job is to tell what kind of packet is in the Payload field. Codes are defined for LCP, NCP, IP, IPX, AppleTalk, and other protocols. Protocols starting with a 0 bit are network layer protocols such as IP, IPX, OSI CLNP, XNS. Those starting with a 1 bit are used to negotiate other protocols. These include LCP and a different NCP for each network layer protocol supported. The default size of the Protocol field is 2 bytes, but it can be negotiated down to 1 byte using LCP.

The Payload field is variable length, up to some negotiated maximum. If the length is not negotiated using LCP during line setup, a default length of 1500 bytes is used. Padding may follow the payload if need be. After the Payload field comes the Checksum field, which is normally 2 bytes, but a 4-byte checksum can be negotiated.

In summary, PPP is a multiprotocol framing mechanism suitable for use over modems, HDLC bit-serial lines, SONET, and other physical layers. It supports error detection, option negotiation, header compression, and, optionally, reliable transmission using an HDLC-type frame format.

14. Explain how the PPP frame format used for lines is brought up and down.

The (simplified) diagram of Fig.14 shows the phases that a line goes through when it is brought up, used, and taken down again. This sequence applies both to modem connections and to router-




Fig.14 A simplified phase diagram for bringing a line up and down

The protocol starts with the line in the DEAD state, which means that no physical layer carrier is present and no physical layer connection exists. After physical connection is established, the line moves to ESTABLISH. At that point LCP option negotiation begins, which, if successful, leads to AUTHENTICATE. Now the two parties can check on each other's identities if desired. When the NETWORK phase is entered, the appropriate NCP protocol is invoked to configure the network layer. If the configuration is successful, OPEN is reached and data transport can take place. When data transport is finished, the line moves into the TERMINATE phase, and from there, back to DEAD when the carrier is dropped.

LCP negotiates data link protocol options during the ESTABLISH phase. The LCP protocol is not actually concerned with the options themselves, but with the mechanism for negotiation. It provides a way for the initiating process to make a proposal and for the responding process to accept or reject it, in whole or in part. It also provides a way for the two processes to test the line quality to see if they consider it good enough to set up a connection. Finally, the LCP protocol also allows lines to be taken down when they are no longer needed.

15. Write different types of LCP packets defined in RFC 1661.

Eleven types of LCP frames are defined in RFC 1661. These are listed in Fig.15. The four configure- types allow the initiator (I) to propose option values and the responder (R) to accept or reject them. In the latter case, the responder can make an alternative proposal or announce that it is not willing to negotiate certain options at all. The options being negotiated and their proposed values are part of the LCP frames.

Name	Direction	Description
Configure-request	$I \rightarrow R$	List of proposed options and values
Configure-ack	I ← R	All options are accepted
Configure-nak	I ← R	Some options are not accepted
Configure-reject	I ← R	Some options are not negotiable
Terminate-request	$I \rightarrow B$	Request to shut the line down
Terminate-ack	I ← R	OK, line shut down
Code-reject	I←R	Unknown request received
Protocol-reject	I ← B	Unknown protocol requested
Echo-request	I→R	Please send this frame back
Echo-reply	I←R	Here is the frame back
Discard-request	I→R	Just discard this frame (for testing)

Fig.15 The LCP frame types

The Terminate- codes shut a line down when it is no longer needed. The Code-reject and Protocol-reject codes indicate that the responder got something that it does not understand. This situation could mean that an undetected transmission error has occurred, but more likely it means that the initiator and responder are running different versions of the LCP protocol. The Echotypes are used to test the line quality. Finally, Discard-request helps debugging. If either end is having trouble getting bits onto the wire, the programmer can use this type for testing. If it manages to get through, the receiver just throws it away, rather than taking some other action that might confuse the person doing the testing.

The options that can be negotiated include setting the maximum payload size for data frames, enabling authentication and choosing a protocol to use, enabling line-quality monitoring during normal operation, and selecting various header compression options.

Questions & Answers