2023/6/20 10:33 Document

Copyright (c) 2023, Oracle. All rights reserved. Oracle Confidential.

Unable to drop GoldenGate user: ORA-20782: Cannot DROP object used in Oracle GoldenGate replication while trigger is enabled (Doc ID 1924642.1)

Modified: Sep 10, 2014 Type: HOWTO

In this Document

Goal

Solution

APPLIES TO:

Oracle GoldenGate - Version 11.1.1.0.0 and later Information in this document applies to any platform.

GOAL

Unable to drop the GoldenGate user. The following error is returned:

SQL> drop user GGS cascade; drop user GGS cascade

*

ERROR at line 1:

ORA-00604: error occurred at recursive SQL level 2

ORA-20782: Oracle GoldenGate DDL Replication Error: Code :ORA-20782: Cannot DROP object used in Oracle GoldenGate replication while trigger is enabled. Consult Oracle GoldenGate documentation and/or call Oracle GoldenGate Technical Support if you wish to do so., error stack: ORA-06512: at line 231

ORA-06512: at line 957

The GoldenGate installation has been deleted/removed some time ago, and you are not sure what version of GoldenGate was used.

SOLUTION

The ddl_remove and ddl_disable can be run from any version, only to install the trigger we need the correct version. We suggest that you download the latest 11.2.x version available for your environment, go to OGG Installation location and open SQL prompt and login as sysdba

- 1)@ddl_disable.sql
- 2)@ ddl_remove.sql
- 3)@marker_remove.sql

Now try deleting the user and remove the installed directory.

Didn't find what you are looking for?