Recap

Network Hardware Components

Links, Nodes (Hosts, Routers, Switches)

Network Architecture & Protocols

- OSI Architecture (7 layers)
 - Physical, Data Link, Network, Transport, Session, Representation, Application
- Internet Architecture (5 layers)
 - Physical, Subnetwork, IP (Network), TCP/UDP (Transport), Application

Application Programming Interface

Interface exported by the network

Since most network protocols are implemented (those in the high protocol stack) in software and nearly all computer systems implement their network protocols as part of the operating system, when we refer to the interface "exported by the network", we are generally referring to the interface that the OS provides to its networking subsystem

The interface is called the network Application Programming Interface (API)

Application Programming Interface (Sockets)

Socket Interface was originally provided by the Berkeley distribution of Unix

- Now supported in virtually all operating systems

Each protocol provides a certain set of *services*, and the API provides a syntax by which those services can be invoked in this particular OS

IP Address

Internet Protocol address (IP address) identifies a device in the network


- <u>Network-layer</u> addressing
- Two versions in use
 - IPv4 has 32-bit addresses written like 192.0.2.1; only 4 billion IPv4 addresses, not enough for current Internet usage
 - IPv6 has 128-bit addresses written like 2001:db8:0:1234:0:567:8:1

IP Address Geography

IP Addresses are geographical
Routers do not need to know every IP
Address on the entire Internet
First few bits of address indicate where to
forward the packet

129.186.X.Y -- addresses at ISU campus 128.255.X.Y -- addresses at Ulowa

IPv4 Address Map of Year 2016



Port

Port numbers identify individual process

- Transport-layer addressing
- Port number is 16-bits unsigned, can range from 0 to 65,535

Common Port Assignments

Port numbers 0 to 1023 are typically reserved for well-known applications

Notable well-known port numbers

Number	Assignment
20	File Transfer Protocol (FTP) Data Transfer
21	File Transfer Protocol (FTP) Command Control
22	Secure Shell (SSH) Secure Login
23	Telnet remote login service, unencrypted text messages
25	Simple Mail Transfer Protocol (SMTP) email delivery
53	Domain Name System (DNS) service
67, 68	Dynamic Host Configuration Protocol (DHCP)
80	Hypertext Transfer Protocol (HTTP) used in the World Wide Web
110	Post Office Protocol (POP3)
119	Network News Transfer Protocol (NNTP)
123	Network Time Protocol (NTP)
143	Internet Message Access Protocol (IMAP) Management of digital mail
161	Simple Network Management Protocol (SNMP)
194	Internet Relay Chat (IRC)
443	HTTP Secure (HTTPS) HTTP over TLS/SSL

Socket

What is a socket?

- The point where a local application process attaches to the network
- An interface between an application and the network
- An application requests to create the socket

A **socket** is a combination of IP Address, transmission protocol, and port

Servers **bind** to a socket to **listen** for incoming connections and then **accept** the connection

Clients **connect** to a socket and then send/receive messages over the socket

Socket

Socket Family

PF_INET denotes the Internet family

PF_UNIX denotes the Unix pipe facility

PF_PACKET denotes direct access to the network interface (i.e., it bypasses the TCP/IP protocol stack)

Socket Type

SOCK_STREAM is used to denote a byte stream (e.g., TCP)

SOCK_DGRAM is an alternative that denotes a message oriented service (e.g., UDP)

Creating a Socket

```
int sockfd = socket(address_family, type, protocol);
```

The socket number returned is the socket descriptor for the newly created socket

```
int sockfd = socket (PF_INET, SOCK_STREAM, 0);
int sockfd = socket (PF_INET, SOCK_DGRAM, 0);
```

Why protocol =0?

The combination of PF_INET and SOCK_STREAM implies TCP PF_INET and SOCK_DGRAM implies UDP

Server

- Passive open
- Prepares to accept connection, does not actually establish a connection

Server invokes

Bind

- Binds the newly created socket to the specified address i.e. the network address of the local participant (the server)
- Address is a data structure which combines IP and port

Listen

Defines how many connections can be pending on the specified socket

Accept

- Carries out the passive open
- Blocking operation
 - Does not return until a remote participant has established a connection
 - When it does, it returns a new socket that corresponds to the newly established connection and the address argument contains the remote participant's address

Example Application: Server

```
#include <stdio.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <netdb.h>
#define SERVER PORT 5432
#define MAX PENDING 5
#define MAX_LINE 256
int main()
        struct sockaddr_in sin;
        char buf[MAX LINE];
        int len;
```

```
int s, new_s;
/* build address data structure */
bzero((char *)&sin, sizeof(sin));
sin.sin_family = AF_INET;
sin.sin_addr.s_addr = INADDR_ANY; //any local address
sin.sin port = htons(SERVER PORT);
/* setup passive open */
if ((s = socket(PF_INET, SOCK_STREAM, 0)) < 0) {
         perror("simplex-talk: socket");
         exit(1);
```

Example Application: Server

```
if ((bind(s, (struct sockaddr *)&sin, sizeof(sin))) < 0) {
         perror("simplex-talk: bind"); exit(1);
listen(s, MAX_PENDING);
/* wait for connection, then receive and print text */
while(1) {
 if ((new_s = accept(s, (struct sockaddr *)&sin, &len)) < 0) {
         perror("simplex-talk: accept"); exit(1);
 while (len = recv(new_s, buf, sizeof(buf), 0))
         fputs(buf, stdout);
         close(new_s);
```

Client

- Application performs active open
- It says who it wants to communicate with

Client also creates a socket (as the Server does)

Client then invokes

Connect

- Does not return until TCP has successfully established a connection at which application is free to begin sending data
- Address contains remote machine's address

In practice

- The client usually specifies only remote participant's address and let's the system fill in the local information
- Whereas a server usually listens for messages on a well-known port, a client does not care which port it uses for itself, the OS simply selects an unused one

Once a connection is established, the application process invokes two operations

Example Application: Client

```
#include <stdio.h>
#include <sys/types.h>
#include <sys/socket.h>
#include <netinet/in.h>
#include <netdb.h>
#define SERVER_PORT 5432
#define MAX_LINE 256
int main(int argc, char * argv[]){
```

```
FILE *fp;
struct hostent *hp;
struct sockaddr_in sin;
char *host;
char buf[MAX_LINE];
int s;
int len;
if (argc==2) host = argv[1];
else {
 fprintf(stderr, "usage: simplex-talk host\n");
 exit(1);
```

Example Application: Client

```
/* translate host name into peer's IP address */
hp = gethostbyname(host);
if (!hp) {
 fprintf(stderr, "unknown host: %s\n", host); exit(1);
/* build address data structure */
bzero((char *)&sin, sizeof(sin));
sin.sin_family = AF_INET;
bcopy(hp->h_addr, (char *)&sin.sin_addr, hp->h_length);
sin.sin_port = htons(SERVER_PORT);
/* active open */
if ((s = socket(PF_INET, SOCK_STREAM, 0)) < 0) {
 perror("simplex-talk: socket"); exit(1);
```

```
if (connect(s, (struct sockaddr *)&sin, sizeof(sin)) < 0) {
                  perror("simplex-talk: connect");
                  close(s);
                  exit(1);
/* main loop: get and send lines of text */
while (fgets(buf, sizeof(buf), stdin)) {
                  buf[MAX LINE-1] = '\0';
                  len = strlen(buf) + 1;
                  send(s, buf, len, 0);
```

Performance

Bandwidth


- Width of the frequency band
- Number of bits per second that can be transmitted over a communication link

1 Mbps: 1×10^6 bits/second = 1×2^{20} bits/sec

1 x 10⁻⁶ seconds to transmit each bit or imagine that a timeline:

- Each bit occupies 1 micro second space.
- On a 2 Mbps link the width is 0.5 micro second.
- Smaller the width more will be transmission per unit time.

Bandwidth



Bits transmitted at a particular bandwidth can be regarded as having some width:

- (a) bits transmitted at 1Mbps (each bit 1 μs wide);
- (b) bits transmitted at 2Mbps (each bit $0.5 \mu s$ wide).

Performance

Latency = Transmit + Propagation + Queue

Propagation = distance/speed of light

Transmit = size/bandwidth

One bit transmission => propagation is important

Large bytes transmission => bandwidth (transmission time) is important



Time

Delay vs Bandwidth

Relative importance of bandwidth and latency depends on application

For large file transfer, bandwidth is critical

For small messages (HTTP, NFS, etc.), latency is critical

Variance in latency (jitter) can also affect some applications (e.g., audio/video conferencing)

Round Trip Time (RTT)

Consider that a sender often expects its receiver to reply after receiving.

- RTT: the delay for propagating a bit from the sender to the receiver and from the receiver to the sender.
- RTT/2: roughly the delay for propagating a bit from sender (or receiver) to receiver (or sender).

Example, in practice, the time for a packet to arrive at a receiver is:

packetSize/bandwith + RTT/2

Let packet size = 1KB, bandwidth = 1Mbps, RTT = 50ms, how much time is needed for 1000 packet to arrive at the reiver?

(1000*1KB*8bits/Byte) / 1Mbps + 50ms/2 = 8s + 25ms = 8.025s

Summary

We have identified what we expect from a computer network

We have defined a layered architecture for computer network that will serve as a blueprint for our design

We have discussed the socket interface which will be used by applications for invoking the services of the network subsystem

We have discussed two performance metrics using which we can analyze the performance of computer networks