# **Machine-Level Programming I: Basics**



# **Today: Machine Programming I: Basics**

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations

#### Intel x86 Processors

#### Dominate laptop/desktop/server market

#### Evolutionary design

- Backwards compatible up until 8086, introduced in 1978
- Added more features as time goes on

#### Complex instruction set computer (CISC)

- Many different instructions with many different formats
  - But, only small subset encountered with Linux programs
- Hard to match performance of Reduced Instruction Set Computers (RISC)
- But, Intel has done just that!
  - In terms of speed. Less so for low power.



#### **Intel x86 Evolution: Milestones**

Name	Date	Transistors	MHz	
<b>≥</b> 8086	1978	29K	5-10	
<equation-block> First 16-bit Ir</equation-block>	ntel processor. E	Basis for IBM PC & DOS		
1MB address	space			
<b>2</b> 386	1985	275K	16-33	
ଌ First 32 bit Ir	itel processor, r	eferred to as IA32		
Added "flat a	addressing", cap	able of running Unix		
Pentium 4E	2004	<b>125M</b>	2800-3800	
First 64-bit Intel x86 processor, referred to as x86-64				
Core 2	2006	<b>291M</b>	1060-3500	
First multi-core Intel processor				
Core i?	2008	<b>731M</b>	1700-3900	
Four cores				
Core i9	2017		2600-3300	
Ten cores				



### **Our Coverage**

- **!** IA32
  - The traditional x86
- **2** x86-64
  - The standard
- Presentation
  - Book covers x86-64
  - Web aside on IA32
  - We will only cover x86-64

# **Today: Machine Programming I: Basics**

- History of Intel processors and architectures
- **C**, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations




#### **Definitions**

- Instruction Set Architecture (ISA): The parts of a processor design that one needs to understand or write assembly/machine code.
  - **Examples:** instruction set specification, registers.
- Microarchitecture: Implementation of the architecture.
  - Examples: cache sizes and core frequency.
- **Code Forms:** 
  - Machine Code: The byte-level programs that a processor executes
  - Assembly Code: A text representation of machine code
- Example ISAs:
  - Intel: x86, IA32, Itanium, x86-64
  - ARM: Used in almost all mobile phones



### **Assembly/Machine Code View**



#### **Programmer-Visible State**

- **PC:** Program counter
  - Address of next instruction
  - Called "RIP" (x86-64)
- Register file
  - Heavily used program data
- Condition codes
  - Store status information about most recent arithmetic or logical operation
  - Used for conditional branching


#### Memory

- Byte addressable array
- Code and user data
- Stack to support procedures



### **Turning C into Object Code**

- Code in files p1.c p2.c
- Compile with command: gcc −Og p1.c p2.c −o p
  - Use basic optimizations (-Og) [New to recent versions of GCC]
  - Put resulting binary in file p



# **Compiling Into Assembly**

#### C Code (sum.c)

#### **Generated x86-64 Assembly**

```
sumstore:
   pushq %rbx
   movq %rdx, %rbx
   call plus
   movq %rax, (%rbx)
   popq %rbx
   ret
```

#### **Obtain with command**

Produces file sum.s

Warning: Can get very different results on different machines due to different versions of gcc and different compiler settings.



# **Assembly Characteristics: Data Types**

- Unteger" data of 1, 2, 4, or 8 bytes
  - Data values
  - Addresses (untyped pointers)
- Floating point data of 4, 8, or 10 bytes
- **Code:** Byte sequences encoding series of instructions
- No aggregate types such as arrays or structures
  - Just contiguously allocated bytes in memory



# **Assembly Characteristics: Operations**

- Perform arithmetic function on register or memory data
- Transfer data between memory and register
  - Load data from memory into register
  - Store register data into memory
- Transfer control
  - Unconditional jumps to/from procedures
  - Conditional branches

# **Object Code**

#### Code for sumstore

#### $0 \times 0400595$ :

0x53

0x48

0x89

0xd3

0xe8

0xf2

0xff

0xff

0xff

0x48

0x89

0x03

0x5b

0xc3

#### Assembler

- Translates .s into .o
- Binary encoding of each instruction
- Nearly-complete image of executable code
- Missing linkages between code in different files

#### Linker

- Resolves references between files
- Combines with static run-time libraries
  - E.g., code for malloc, printf
- Some libraries are dynamically linked
  - Linking occurs when program begins execution



Total of 14 bytes

Each instruction

1, 3, or 5 bytes

Starts at address

 $0 \times 0400595$ 

# **Machine Instruction Example**

0x40059e: 48 89 03

#### **&**C Code

Store value t where designated by dest

#### Assembly

Move 8-byte value to memory
Quad words in x86-64 parlance

**Operands:** 

t: Register %rax

dest: Register %rbx

\*dest: Memory M[%rbx]

#### **Object Code**

3-byte instruction

Stored at address 0x40059e

### **Disassembling Object Code**

#### Disassembled

```
0000000000400595 <sumstore>:
  400595:
          53
                                 %rbx
                          push
 400596: 48 89 d3
                          mov
                                 %rdx,%rbx
 400599: e8 f2 ff ff ff callq
                                 400590 <plus>
  40059e: 48 89 03
                                 %rax,(%rbx)
                          mov
 4005a1: 5b
                                 %rbx
                          pop
  4005a2: c3
                          retq
```

#### Disassembler

```
objdump -d sum
```

- Useful tool for examining object code
- Analyzes bit pattern of series of instructions
- Produces approximate rendition of assembly code
- Can be run on either a .out (complete executable) or .o file



# **Alternate Disassembly**

#### **Object**

#### **Disassembled**

```
0 \times 0400595:
    0x53
    0 \times 48
    0x89
    0xd3
    0xe8
    0xf2
    0xff
    Oxff
    0xff
    0x48
    0x89
    0x03
    0x5b
    0xc3
```

```
Dump of assembler code for function sumstore:

0x00000000000400595 <+0>: push %rbx

0x0000000000400596 <+1>: mov %rdx,%rbx

0x0000000000400599 <+4>: callq 0x400590 <plus>
0x000000000040059e <+9>: mov %rax,(%rbx)

0x000000000004005a1 <+12>:pop %rbx

0x000000000004005a2 <+13>:retq
```

#### Within gdb Debugger

```
gdb sum
disassemble sumstore
```

Disassemble procedure

x/14xb sumstore

Examine the 14 bytes starting at sumstore



#### What Can be Disassembled?

```
% objdump -d WINWORD.EXE

WINWORD.EXE: file format pei-i386

No symbols in "WINWORD.EXE".
Disassembly of section .text:

30001000 <.text>:
30001000:
30001001:
30001003:
30001005:
Microsoft End User License Agreement
3000100a:
```

- Anything that can be interpreted as executable code
- Disassembler examines bytes and reconstructs assembly sources

# **Today: Machine Programming I: Basics**

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations




# x86-64 Integer Registers

%rax	%eax	% <b>r8</b>	% <b>r8d</b>
%rbx	%ebx	%r9	%r9d
%rcx	%ecx	%r10	%r10d
%rdx	%edx	%r11	%r11d
%rsi	%esi	%r12	%r12d
%rdi	%edi	%r13	%r13d
%rsp	%esp	%r14	%r14d
%rbp	%ebp	%r15	%r15d

Can reference low-order 4 bytes (also low-order 1 & 2 bytes)



# **Some History: IA32 Registers**



Origin (mostly obsolete)

accumulate

counter

data

base

source index

destination index

stack pointer base pointer



# **Moving Data**

- Moving Data
  movq Source, Dest:
- Operand Types
  - Immediate: Constant integer data
    - Example: \$0x400, \$-533
    - Like C constant, but prefixed with \\$'
    - Encoded with 1, 2, or 4 bytes
  - **Register:** One of 16 integer registers
    - Example: %rax, %r13
    - But %rsp reserved for special use
    - Others have special uses for particular instructions
  - Memory: 8 consecutive bytes of memory at address given by register
    - Simplest example: (%rax)
    - Various other "address modes"

%rax	
%rcx	
%rdx	
%rbx	
%rsi	
%rdi	
2 rcn	



%rN

# movq Operand Combinations

Cannot do memory-memory transfer with a single instruction

# Simple Memory Addressing Modes

- Normal (R) Mem[Reg[R]]
  - Register R specifies memory address
  - Aha! Pointer dereferencing in C

movq (%rcx),%rax

- Displacement D(R) Mem[Reg[R]+D]
  - Register R specifies start of memory region
  - Constant displacement D specifies offset


movq 8(%rbp),%rdx



# **Example of Simple Addressing Modes**

```
void swap
   (long *xp, long *yp)
{
   long t0 = *xp;
   long t1 = *yp;
   *xp = t1;
   *yp = t0;
}
```

### void swap (long \*xp, long \*yp) long t0 = \*xp;long t1 = \*yp;\*xp = t1;\*yp = t0;



Value
хр
ур
t0
t1

```
swap:
  movq (%rdi), %rax \# t0 = *xp
  movq (%rsi), %rdx # t1 = *yp
  movq %rdx, (%rdi) # *xp = t1
          %rax, (%rsi) # *yp = t0
  movq
  ret
```

#### Registers

%rdi	0x120
%rsi	0x100
%rax	
%rdx	


#### **Memory**

	Aaaress
123	0x120
	0x118
	0x110
	0x108
456	0x100


A ddrace

```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
       %rax, (%rsi) # *yp = t0
movq
ret
```






```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```



```
(%rdi), %rax # t0 = *xp
movq
movq (%rsi), %rdx # t1 = *yp
       %rdx, (%rdi) # *xp = t1
movq
       %rax, (%rsi) # *yp = t0
movq
ret
```





# swap: mova (%rdi), %


```
movq (%rdi), %rax # t0 = *xp

movq (%rsi), %rdx # t1 = *yp

movq %rdx, (%rdi) # *xp = t1

movq %rax, (%rsi) # *yp = t0

ret
```



```
movq (%rdi), %rax # t0 = *xp
movq (%rsi), %rdx # t1 = *yp
movq %rdx, (%rdi) # *xp = t1
movq %rax, (%rsi) # *yp = t0
ret
```



# **Simple Memory Addressing Modes**

- Normal (R) Mem[Reg[R]]
  - Register R specifies memory address
  - Aha! Pointer dereferencing in C

movq (%rcx),%rax

- Displacement D(R) Mem[Reg[R]+D]
  - Register R specifies start of memory region
  - Constant displacement D specifies offset

movq 8(%rbp),%rdx



# **Complete Memory Addressing Modes**

#### Most General Form

D(Rb,Ri,S) Mem[Reg[Rb]+S\*Reg[Ri]+D]

**2**D: Constant "displacement" 1, 2, or 4 bytes

♣ Rb: Base register: Any of 16 integer registers

♣Ri: Index register: Any, except for %rsp

Scale: 1, 2, 4, or 8 (why these numbers?)

#### Special Cases

(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]]

D(Rb,Ri) Mem[Reg[Rb]+Reg[Ri]+D]

(Rb,Ri,S) Mem[Reg[Rb]+S\*Reg[Ri]]

# **Address Computation Examples**

%rdx	0xf000
%rcx	0x0100

Expression	Address Computation	Address
0x8(%rdx)	0xf000 + 0x8	0xf008
(%rdx,%rcx)	0xf000 + 0x100	0xf100
(%rdx,%rcx,4)	0xf000 + 4*0x100	0xf400
0x80(,%rdx,2)	2*0xf000 + 0x80	0x1e080



# **Today: Machine Programming I: Basics**

- History of Intel processors and architectures
- C, assembly, machine code
- Assembly Basics: Registers, operands, move
- Arithmetic & logical operations



### **Address Computation Instruction**

- leaq Src, Dst
  - Src is address mode expression
  - Set Dst to address denoted by expression

#### Uses

- Computing addresses without a memory reference
  - $\bullet$  E.g., translation of p = &x[i];
- Computing arithmetic expressions of the form x + k\*y
  - k = 1, 2, 4, or 8

#### Example

```
long m12(long x)
{
   return x*12;
}
```

#### **Converted to ASM by compiler:**

```
leaq (%rdi,%rdi,2), %rax # t <- x+x*2
salq $2, %rax # return t<<2</pre>
```

#### **Some Arithmetic Operations**

#### Two Operand Instructions:

Computati	ion	
Src,Dest	Dest = Dest + Src	
Src,Dest	Dest = Dest – Src	
Src,Dest	Dest = Dest * Src	
Src,Dest	Dest = Dest << Src	Also called shiq
Src,Dest	Dest = Dest >> Src	Arithmetic
Src,Dest	Dest = Dest >> Src	Logical
Src,Dest	Dest = Dest ^ Src	
Src,Dest	Dest = Dest & Src	
Src,Dest	Dest = Dest   Src	
	Src,Dest Src,Dest Src,Dest Src,Dest Src,Dest Src,Dest Src,Dest Src,Dest Src,Dest	Src,DestDest = Dest - SrcSrc,DestDest = Dest * SrcSrc,DestDest = Dest << SrcSrc,DestDest = Dest >> SrcSrc,DestDest = Dest >> SrcSrc,DestDest = Dest ^ SrcSrc,DestDest = Dest & SrcDest = Dest & Src

- Watch out for argument order!
- No distinction between signed and unsigned int (why?)



### **Some Arithmetic Operations**

One Operand Instructions

```
Dest = Dest + 1
incq
         Dest
                    Dest = Dest - 1
decq
        Dest
       Dest
                 Dest = - Dest
negq
                 Dest = ~Dest
notq
         Dest
```

See book for more instructions

# **Arithmetic Expression Example**

```
long arith
(long x, long y, long z)
{
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
}
```

```
arith:
  leaq (%rdi,%rsi), %rax
  addq %rdx, %rax
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx
  leaq 4(%rdi,%rdx), %rcx
  imulq %rcx, %rax
  ret
```

#### **Interesting Instructions**

- **leaq**: address computation
- **& salq**: shift
- **imulq**: multiplication
  - But, only used once

# **Understanding Arithmetic Expression Example**

```
long arith
(long x, long y, long z)
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
 return rval;
```

```
arith:
 leaq
        (%rdi,%rsi), %rax
                          # t1
                          # t2
        %rdx, %rax
 addq
 leag (%rsi,%rsi,2), %rdx
 salq $4, %rdx
                          # t4
 leag 4(%rdi,%rdx), %rcx # t5
                          # rval
 imulq %rcx, %rax
 ret
```

Register	Use(s)
%rdi	Argument <b>x</b>
%rsi	Argument <b>y</b>
%rdx	Argument <b>z</b>
%rax	t1, t2, rval
%rdx	t4
%rcx	t5



# Understanding Arithmetic Expression Example

```
long arith
(long x, long y, long z)
{
  long t1 = x+y;
  long t2 = z+t1;
  long t3 = x+4;
  long t4 = y * 48;
  long t5 = t3 + t4;
  long rval = t2 * t5;
  return rval;
}
```

```
arith:
  leaq (%rdi,%rsi), %rax # t1
  addq %rdx, %rax # t2
  leaq (%rsi,%rsi,2), %rdx
  salq $4, %rdx # t4
  leaq 4(%rdi,%rdx), %rcx # t5
  imulq %rcx, %rax # rval
  ret
```

Register	Use(s)
%rdi	Argument x
%rsi	Argument <b>y</b>
%rdx	Argument <b>z</b>
%rax	t1, t2, rval
%rdx	t4
%rcx	t5



# **Machine Programming I: Summary**

- History of Intel processors and architectures
  - Evolutionary design leads to many quirks and artifacts
- **C**, assembly, machine code
  - New forms of visible state: program counter, registers, ...
  - Compiler must transform statements, expressions, procedures into low-level instruction sequences
- Assembly Basics: Registers, operands, move
  - The x86-64 move instructions cover wide range of data movement forms
- Arithmetic
  - C compiler will figure out different instruction combinations to carry out computation

