```
#Basic Router Configuration (Rafee)
#Basic Configuration
For SDS
en
erase startup-config
reload
no
en
config t
hostname SDS
banner motd &
************
  Hello from School of Data And Sciences
*************
&
interface gigabitEthernet 0/0
ip address 192.168.0.1 255.255.240.0
no shut
interface gigabitEthernet 0/0
ip address 192.168.0.1 255.255.240.0
no shut
interface s0/3/0
ip address 192.168.31.129 255.255.255.252
clock rate 64000
no shut
interface s0/3/1
ip address 192.168.31.133 255.255.255.252
clock rate 64000
no shut
exit
exit
copy running-config startup-config
For SE
en
erase startup-config
reload
no
en
config t
```

hostname SE

```
banner motd &
************
  Hello from School of Engineering
&
interface g0/0
ip address 192.168.30.1 255.255.255.0
no shut
interface s0/3/0
ip address 192.168.31.130 255.255.255.252
exit
exit
copy running-config startup-config
For BIL
en
erase startup-config
reload
no
en
config t
hostname BIL
banner motd &
  Hello from Brac Institute of Languages
*****************
&
interface g0/0
ip address 192.168.24.1 255.255.252.0
no shut
interface s0/3/0
ip address 192.168.31.134 255.255.255.252
no shut
interface s0/3/1
ip address 192.168.31.137 255.255.255.252
clock rate 64000
no shut
interface s0/2/0
ip address 192.168.31.141 255.255.255.252
clock rate 64000
no shut
exit
exit
```

copy running-config startup-config

```
For BBS
en
erase startup-config
reload
no
en
config t
hostname BBS
banner motd &
******************
  Hello From Brac Business School
****************
&
interface g0/0
ip address 192.168.16.1 255.255.248.0
no shut
BBS(config-if)#interface s0/3/0
ip address 192.168.31.138 255.255.255.252
no shut
interface s0/3/1
ip address 192.168.31.145 255.255.255.252
clock rate 64000
no shut
exit
exit
copy running-config startup-config
For SHSS
en
erase startup-config
reload
no
en
config t
hostname SHSS
banner motd &
*****************
  Hello from School of Humanities and Social Sciences
*****************
&
interface g0/0
ip address 192.168.31.1 255.255.255.128
```

```
no shut
interface s0/3/0
ip address 192.168.31.142 255.255.255.252
no shut
interface s0/3/1
ip address 192.168.31.146 255.255.255.252
clock rate 64000
no shut
exit
exit
copy running-config startup-config
#Basic Configuration
#Routing
For SDS
en
config t
router rip
version 2
no auto-summary
network 192.168.0.0
network 192.168.28.0
network 192.168.31.128
network 192.168.31.132
exit
exit
copy running-config startup-config
For SE
en
config t
router rip
version 2
no auto-summary
network 192.168.30.0
network 192.168.31.128
exit
copy running-config startup-config
For BIL
en
```

config t

```
ip route 192.168.16.0 255.255.248.0 192.168.16.1
ip route 192.168.31.0 255.255.255.128 192.168.31.146
ip route 0.0.0.0 0.0.0.0 Serial0/3/0
router rip
version 2
network 192.168.31.134
network 192.168.24.0
redistribute static
exit
exit
copy running-config startup-config
#Routing
#Adding helper address till BBS
For SDS
en
config t
int g0/1
ip helper-address 192.168.0.3
no shut
exit
For SE
en
config t
int g0/0
ip helper-ad
ip helper-address 192.168.0.3
no shut
exit
exit
For BIL
en
config t
int g0/0
ip helper-address 192.168.0.3
no shut
exit
exit
```

#Done

//Todo: Add here your part brother. If you want to add things separately!

//Static routing, Floating static routing, DHCP relay and Debugging: (Samanta)

BBS>en

BBS#config t

BBS(config)#ip route 192.168.31.0 255.255.255.128 192.168.31.146

BBS(config)#ip route 192.168.24.0 255.255.252.0 192.168.31.137

BBS(config)#exit

BBS#show ip route

BBS#exit

SHSS>en

SHSS#config t

SHSS(config)#ip route 192.168.16.0 255.255.248.0 192.168.31.145

SHSS(config)#ip route 192.168.24.0 255.255.252.0 192.168.31.141

SHSS(config)#exit

SHSS#show ip route

SHSS#exit

BBS>en

BBS#config t

BBS(config)#ip route 192.168.31.0 255.255.255.128 s0/3/0 5

BBS(config)#exit

BBS#show ip route

BBS#exit

SHSS>en

SHSS#config t

SHSS(config)#ip route 192.168.16.0 255.255.248.0 s0/3/0 5

SHSS(config)#exit

SHSS#show ip route

SHSS#exit

BBS>en

BBS#config t

BBS(config)#int g0/0

BBS(config-if)#ip helper-address 192.168.0.3

BBS(config-if)#no shut

BBS(config-if)#exit

BBS(config)#exit

BBS#exit

SHSS>en

SHSS#config t

SHSS(config)#int g0/0

SHSS(config-if)#ip helper-address 192.168.0.3

SHSS(config-if)#no shut

SHSS(config-if)#exit

SHSS(config)#exit

SHSS#exit

BBS>en

BBS#show ip route

BBS#copy run start

BBS#exit

SHSS>en

SHSS#show ip route

SHSS#copy run start

SHSS#exit

BIL>en

BIL#clear ip route *

BIL#show ip route

BIL#config t

BIL(config)#ip route 192.168.16.0 255.255.248.0 192.168.31.138

BIL(config)#ip route 192.168.31.0 255.255.255.128 192.168.31.142

BIL(config)#router rip

BIL(config-router)#version 2

BIL(config-router)#network 192.168.31.132

BIL(config-router)#passive-interface g0/0

BIL(config-router)#redistribute static

BIL(config-router)#exit

BIL(config)#exit

BIL#copy run start

BIL#exit

#Rafee

For BBS

en

config t

ip route 0.0.0.0 0.0.0.0 Serial0/3/0

For SHSS

SHSS>en

SHSS#config t

SHSS(config)#ip route 0.0.0.0 0.0.0.0 Serial0/3/0