
Lab 4: Packet Tracer: Introduction to Configuration

Configure the Routers, Switches and PC using Packet Tracer.



Instructions:

- 1. Click Options>Preferences> Tick at Always Show Port Labels
- 2. Turn ON all the interface used make sure all "dots" are green
- 3. Start with configuration:
- a) Change Host Name: Config Tab > Hostname & Display Name

Router 0 - R1

Router 1 - R2

Switch 0 - Marketing

Switch 1 - Finance

PC0 - MKT1

PC1 - MKT2

PC2 - FIN1

PC3 - FIN2

b) Configure IP Address and Subnet Mask for each Interface : Config Tab> Interface

R1 Router

Interface FastEthernet0/0 IP Address: 192.168.1.1 Subnet Mask: 255.255.255.0

Interface Serial0/0/0 IP Address: 10.10.10.1

Subnet Mask: 255.255.255.252

clock rate 2000000

R2 Router

Interface FastEthernet0/0 IP Address 192.168.2.1 Subnet Mask: 255.255.255.0

Interface Serial0/0/0 ip address 10.10.10.2

Subnet Mask: 255.255.255.252

PC0 - MKT1

IP Address: 192.168.1.2 Subnet Mask: 255.255.255.0 Default Gateway: 192.168.1.1

PC1 - MKT2

IP Address: 192.168.1.3 Subnet Mask: 255.255.255.0 Default Gateway: 192.168.1.1

PC2 - FIN1

IP Address: 192.168.2.2 Subnet Mask: 255.255.255.0 Default Gateway: 192.168.2.1

PC3 - FIN2

IP Address: 192.168.2.3 Subnet Mask: 255.255.255.0 Default Gateway: 192.168.2.1 c) Configure Routing (at Router ONLY): Config Tab> Routing > RIP

R1 Router

** Network : 192.168.1.0 ** Network : 10.0.0.0

R2 Router

** Network : 192.168.2.0 ** Network : 10.0.0.0

4. Test the configuration. How??

- a) Use Add Simple PDU icon on your RIGHT, click at source and destination
- b) Open PC > Desktop Tab> Command Prompt > ping destination IP Address