1. Objective – Create security rules

- 1. Select **Home > Resource groups**, then choose your resource group, such as *oreilly-az104*
- 2. At the top of the resource group window select + Add, search for and select "network security group", then choose Create. Enter the following configuration information. If not noted below, use the defaults:

Resource group: oreilly-az104

Name: nsg-frontend-westus

Location: West US

3. Select Review + create, then Create

- 1. If needed, select the notification bell in the top right-hand corner to view deployment progress as the network security group is created. It takes a minute or two to create the resource.
- 4. When ready, select Go to resource
- 5. Look at the default inbound and outbound security rules. These rules take effect if you don't define any higher-priority rules. The lower the integer value of the priority, the higher the priority. When an explicit allow or deny rule is reached, the processing of rules stops.
- 6. Select **Inbound security rules** from the menu on the left-hand side, then **+ Add.** Enter the following configuration information. If not noted below, use the defaults:

Look at **Source** options, leave as *Any*

Destination: Any

Destination port ranges: 80

Protocol: TCP

Action: Allow

Priority: 100

Name: Port 80

7. When ready, select Add

2. Objective - Associate NSG to a subnet or network interface

- 1. From your *nsg-frontend-westus* resource, select **Subnets** from the menu on the left-hand side.
- 2. Select **+ Associate**, then choose the *vnet-westus* virtual network.
- 3. Choose the *frontend-subnet*, and note that the *GatewaySubnet* is unavailable.
- 4. When ready, select **OK**