# Project #4: Virtual Memory

Operating Systems (CSE4070) Project

Fall 2021

Instructors

Prof. Sungyong Park (01)

Prof. Youngjae Kim (02)

TA: Yoochan Kim (01)

Joseph Ro (02)



#### Overview

- Reading pintos document is highly recommended especially for this project (pp. 39-49)
- In project 1, 2 and 3, a program was terminated when a page fault occurs
- In this project, you will make the pintos to be more reliable from page faults and to run the programs properly
- All code you write will be in new files or in files introduced in earlier projects



#### Overview

- Use the code implemented in 'User Programs' project.
- Refer 2<sup>nd</sup> paragraph in pg.39.

You will build this assignment on top of the last one. Test programs from project 2 should also work with project 3. You should take care to fix any bugs in your project 2 submission before you start work on project 3, because those bugs will most likely cause the same problems in project 3.



## Project Requirement

- Page Table Management
  - Supplemental page table and page fault handling

到一个

Lygds

Page fault? -> Surap Space Hul71219


- Paging to and from (swap) disk
  - Implement pseudo-LRU policies (second chance)

LRU/[FU1923]

• Stack Growth - Stock Growth Gr




## Virtual Memory Overview





## Page Table 。 叶凯 translation部部?



어강대학교 Sogang University

## Page Table Management

• 기존 Page Table에 필요한 정보 추가

• 주로 Page fault handling을 위한 정보를 추가

• Page Fault handler 구현

thread directory of pte. holl &

## Supplemental Page Table

• Since the given page table in pintos has limitations, we need to supplement the page table with additional data about each page

• You can exploit the functions in userprog/pagedir.c to implement supplemental page table

• Page table entry format (flags are defined in threads/pte.h),中域州河域 2 1 0

Physical Address(20 bits)	AVL (not used)		D	Α		U	W	Р
---------------------------	-------------------	--	---	---	--	---	---	---

PTE_P	present bit	
PTE_W	read(0)/write(1) bit	
PTE_U	kernel(0)/user(1) bit	
PTE_A	accessed bit	
PTE_D	dirty bit	
PTE_AVL	not used in pintos	

## Page Fault Handler

- userprog/exception.c page\_fault() page\_fault (struct intr\_frame \*f)
- Page Fault situation

 page from a file or swap LU17- ACHIL

Access is invalid

```
bool not_present; /* True: not-present page, false: writing r/o page
                  /* True: access was write, false: access was read
                  /* True: access by user, false: access by kerne
void *fault_addr; /* Fault address. */
asm ("mov1 %%cr2, %0" : "=r" (fault_addr));
```

-0-17/0H/ 42-17-17-0-119/77-121

If the page is unmapped, that is, if there's no data where the page is referenced

If the access is an attempt to write to a read-only page (unprivileged access)

• CR2 : register storing faulted address

- Some boolean variables in page\_fault() will help you
  - bool not\_present; // not present in memory or rights violation
  - bool write; // write or read fault
  - bool user; // fault from user or kernel space





## Page Fault Handler


- Page Fault handling procedures
  - 1. Processor (CPU) triggers page fault 是如 DRAMHU927 fault by
  - 2. Control is passed to the kernel, which calls the page fault handler 介含多 (userprog/exception.c:page\_fault())

    Get the faulted address from CR2 register


  - 4. If the memory reference is valid
    - Obtain a frame to store the page
    - Fetch the data into the frame, by reading it from the file system or swap, zeroing it, etc.
    - Point the page table entry for the faulting virtual address to the physical page
  - 5. If the access is invalid
    - Any invalid access terminates the process and thereby frees all of its resources



### Page Fault Handler: page\_fault()




### Page Fault Handler: handle\_mm\_fault()



## Paging to and from (swap) disk

- Swap disk
  - Process에 할당해 줄 Physical memory가 부족할 때(User page pool에 free page가 없을 때) disk로 swapout이 일어남
  - Swap 할 page의 결정은 page replacement algorithm 사용(LRU, LFU ...)
- Swap table 작성
  - swap disk가 현재 사용하고 있는 슬롯과 빈 슬롯 관리
- devices/block.c 의 block\_read() / block\_write() 활용
- You may use the BLOCK\_SWAP block device for swapping, obtaining the struct block that represents it by calling **block\_get\_role()**
- BLOCK\_SWAP에 대해서는 devices/partition.c, thread/init.c 참조
- swap disk 생성 ~ 기계생물길째 vm/build에서
  - - pintos-mkdisk swap.dsk --swap-size=n --> swap.dsk 라는 이름으로 n MB swap disk 생성
    - swap.dsk는 pintos의 실행 시 자동으로 hdb1에 attach됨
  - Pintos 실행 시 argument로 '--swap-size=n'을 추가해도 n MB swap disk가 생성됨
    - swap.dsk는 pintos의 실행 시 자동으로 hda4에 attach됨






#### Stack Growth

• If page faults on an address that "appears" to be a stack access, allocate another stack page

• You should impose some absolute limit on stack size, as do most OSes.
On many GNU/Linux systems, the default limit is 8 MB.

First stack page can still be loaded at process load time (in order to get arguments, etc.)

## Stack Growth (Example 1)



15

## Stack Growth (Example 2)

What if user program tries to allocate more than a single PAGE size?

```
22 void main(void)
23 {
24 char big_stack_object[#696*3];
esp = esp-4096*3 ;allocate 3 stack pages
25 }

3GB


0x08048000

0

esp
esp-4096*3

Newly allocated stack pages
```

What about page shrinking? Do not consider about shrinking Consider only expanding!




multi passerionie



#### Reference

You can add new files to src/vm/ if it is required.

Newly added files should be written to src/Makefile.build



#### Evaluation

- 16 tests will be graded.
   (Refer to the test case list in the next slide)
- Total score is 100 which consists of 80 for test cases and 20 for documentation.
- Refer to
   src/tests/vm/Grading
   src/tests/vm/Rubric.functionality
   src/tests/vm/Rubric.robustness
   to check the points of each test.



## Evaluation

Functionality				
No.	Test Case	Point		
1	pt-grow-stack	3		
2	pt-grow-stk-sc	3		
3	pt-big-stk-obj	3		
4	pt-grow-pusha	3		
5	page-linear	3		
6	page-parallel	3		
7	page-shuffle	3		
8	page-merge-seq	4		
9	page-merge-par	4		
10	page-merge-mm	4		
11	page-merge-stk	4		
Total 37		37		

Robustness				
No.	Test Case	Point		
1	pt-bad-addr	2		
2	pt-bad-read	3		
3	pt-write-code	2		
4	pt-write-code2	3		
5	pt-grow-bad	4		
Total		14		



#### Documentation

- Use the document file uploaded on e-class
- Documentation accounts for 20% of total score. (Development 80%, Documentation 20%)



- Make 'ID' directory and copy <u>'src' directory</u> in the pintos directory and the document file (<u>[ID].docx</u>).
- Compress 'ID' directory to 'os\_prj4\_[ID].tar.gz'.
- We provide the script 'submit.sh' to make tar.gz file which contains 'src' directory and document file.
  - 학생들의 편의를 위해 pintos 디렉토리 내 submit.sh 스크립트를 제공합니다. 이 스크립트는 src 디렉토리와 document file을 포함한 tar.gz 파일을 생성합니다.

#### Disclaimer

- Any result produced from the 'submit.sh' script is <u>at your own risk.</u>
- You must check the contents of the tar.gz file before submission.
- 'submit.sh' 스크립트로 생성된 결과의 모든 책임은 사용자에게 귀속됩니다.
- 제출하기 전, tar.gz 파일의 내용물을 반드시 다시 한 번 체크하기 바랍니다.



#### Notice – 'submit.sh'

- The 'submit.sh' script should be executed on a directory where 'src' folder is located. submit.sh 스크립트는 src 폴더가 위치한 디렉토리에서 실행되어야 합니다.
- 'ID' folder should not be in the directory.
   해당 디렉토리에 '학번' 폴더가 없어야 합니다.
- 'ID.docx' file should be located in the directory.
   Also, report file with extensions other than 'docx' will not be compressed.
   해당 디렉토리에 '학번.docx' 파일이 있어야 함께 압축됩니다.
   또한 'docx' 이외의 확장자를 가진 보고서 파일은 압축되지 않습니다.
- Be sure to backup your code in case of an unexpected situation.
   만일의 경우를 대비해 반드시 코드를 백업하여 주세요.



- It is a personal project.
- Due date: 2023. 12. 10 23:59
- Submission
  - The form of submission file is as follows:

Name of compressed file	Example (ID: 20211111)
os_prj4_[ID].tar.gz	os_prj4_20211111.tar.gz

- No hardcopy.
- Copy will get a penalty (1st time: 0 Point and downgrading, 2nd time: F grade)



#### Contents

- ① Pintos source codes (Only 'src' directory in pintos directory) 최소한의 용량을 위해 src 디렉토리만 압축파일에 포함합니다.
- ② Document: [ID].docx (e.g. 20211111.docx; Other format is not allowed such as .hwp)

#### How to submit

- Make tar.gz file.
  - Copy the document file ([ID].docx) to pintos directory.
  - Execute submit.sh script in the pintos directory and follow the instructions of the script pintos 디렉토리 내의 submit.sh 스크립트를 실행하고 스크립트의 지시를 따르십시오.
  - Check that os\_prj4\_[ID].tar.gz is created.
  - Decompress os\_prj4\_[ID].tar.gz and check the contents in it. (\$ tar -zxf os\_prj4\_[ID].tar.gz)
     (Only [ID].docx and src directory should be contained in the tar.gz file.)
  - For example, if your ID is 20211111, os\_prj4\_20211111.tar.gz should be created. To decompress the tar.gz file, execute tar -zxf os\_prj4\_20211111.tar.gz
  - Please check the contents of tar.gz file after creating it.
- Upload the os\_prj4\_[ID].tar.gz file to e-class.

