#### Q1 Sec 7.9.1 Do problems 1, 2

1.

In the following code sequence, show the value of AL after each shift or rotate instruction has executed:

mov al,0D4h
shr al,1 ; a.
mov al,0D4h
sar al,1 ; b.
mov al,0D4h
sar al,4 ; c.
mov al,0D4h
rol al,1 ; d.

#### Answer:

A. 01101010b


B. 11101010b

C. 11111101b

D. 10101001b

\*Work shown below:

Sec 7.9,1 1. Don Do valo of Al Alla and All a rolate shucker they al OPAR a) 3110101006 1010100 2 01101010 (a) nov al 004h b) 2/11/010106



#### \*Answer from answer key:

 $0D4h = 1101\ 0100$ 

- a)  $1101\ 0100 \rightarrow SHR\ al,\ 1 \rightarrow 0110\ 1010 = 6Ah$
- b)  $1101\ 0100 \rightarrow SAR\ al,\ 1\rightarrow 1110\ 1010 = 0EAh$
- c) 1101 0100  $\rightarrow$  SAR al, 4  $\rightarrow$ 1111 1101 = 0FDh
- d) 1101 0100  $\rightarrow$  ROL al, 1  $\rightarrow$  1010 1001 = 0A9h

#### 2.


# In the following code sequence, show the value of AL after each shift or rotate instruction has executed:

| mov | al,0D4h |   |    |
|-----|---------|---|----|
| ror | al,3    | ; | a. |
| mov | al,0D4h |   |    |
| rol | al,7    | ; | b. |
| stc |         |   |    |
| mov | al,0D4h |   |    |
| rcl | al,1    | ; | C. |
| stc |         |   |    |
| mov | al,0D4h |   |    |
| rcr | al.3    |   | d  |

#### Answer:

- A. 10011010b
- B. 01101010b
- C. 10101001b
- D. 00111010b

#### \*Work shown below:



#### \*Answer from answer key:

 $0D4h = 1101\ 0100$ 

a) 1101 0100  $\rightarrow$  ROR al, 3  $\rightarrow$  1001 1010 = 9Ah

- b) 1101 0100  $\rightarrow$  ROL al,  $7\rightarrow$ 0110 1010 = 6Ah
- c) First STC is executed so carry flag is 1 initially. 1101 0100  $\rightarrow$  RCL al, 1  $\rightarrow$ 1010 1001 = 0A9h
- d) First STC is executed so carry flag is 1 initially. 1101 0100  $\rightarrow$  RCR al, 3  $\rightarrow$  0011 1010 = 3Ah

#### Q2 Sec 7.9.2 Do problems 3, 4, 5, 11

3.

#### Write a logical shift instruction that multiplies the contents of EAX by 16.

Answer:

shl EAX.4

#### \*An excerpt below just for reference.

Bitwise Multiplication Bitwise multiplication is performed when you shift a number's bits in a leftward direction (toward the MSB). For example, SHL can perform multiplication by powers of 2. Shifting any operand left by n bits multiplies the operand by  $2^n$ . For example, shifting the integer 5 left by 1 bit yields the product of  $5 \times 2^1 = 10$ :

mov dl,5 Before: 
$$\begin{bmatrix} 0 & 0 & 0 & 0 & 1 & 0 & 1 \\ 0 & 0 & 0 & 0 & 1 & 0 & 1 \end{bmatrix} = 5$$
  
shl dl,1 After:  $\begin{bmatrix} 0 & 0 & 0 & 0 & 1 & 0 & 1 & 0 \\ 0 & 0 & 0 & 0 & 1 & 0 & 1 & 0 \end{bmatrix} = 10$ 

If binary 00001010 (decimal 10) is shifted left by two bits, the result is the same as multiplying  $10 \text{ by } 2^2$ :

```
mov dl,10 ; before: 00001010 shl dl,2 ; after: 00101000
```

#### 4.

#### Write a logical shift instruction that divides EBX by 4.

shr EBX.2

#### \*An excerpt below just for reference.

Bitwise Division Bitwise division is accomplished when you shift a number's bits in a right-ward direction (toward the LSB). Shifting an unsigned integer right by n bits divides the operand by  $2^n$ . In the following statements, we divide 32 by  $2^1$ , producing 16:

mov dl,32 Before: 
$$00100000 = 32$$
  
shr dl,1 After:  $00010000 = 16$ 

In the following example, 64 is divided by  $2^3$ :

```
mov al,01000000b ; AL = 64
shr al,3 ; divide by 8, AL = 00001000b
```

Division of signed numbers by shifting is accomplished using the SAR instruction because it preserves the number's sign bit.

#### 5.

Write a single rotate instruction that exchanges the high and low halves of the DL register.

Answer:

ror DL,4 \*From answer key


or

rol DL,4

\*Some excerpts below just for reference.

### **ROR Instruction**

- ROR (rotate right) shifts each bit to the right
- The lowest bit is copied into both the Carry flag and into the highest bit
- No bits are lost



```
mov al,11110000b
```

ror al,1


; AL = 01111000b

mov dl,3Fh ror dl,4

; DL = F3h

Irvine, Kip R. Assembly Language for x86 Processors 7/e, 2015.

12



# 11. Implement the following C++ expression in assembly language, using 32-bit unsigned operands:

```
val1 = (val2 * val3) / (val4 - 3)
Answer:
mov eax,val2
mov ebx,val3
imul ebx
mov ebx,val4
sub ebx,3
idiv ebx
mov val1,eax
```

\*An excerpt below just for reference.

#### Signed Arithmetic Expressions (1 of 2) Example: eax = (-var1 \* var2) + var3eax, var1 mov neg eax imul var2 TooBig ; check for overflow jο add eax, var3 j٥ TooBig ; check for overflow Example: var4 = (var1 \* 5) / (var2 - 3)eax, var1 ; left side mov ebx,5 mov imul ebx ; EDX:EAX = product ebx, var2 ; right side ebx,3 idiv ebx ; EAX = quotient var4,eax 54 Irvine, Kip R. Assembly Language for x86 Processors 7/e, 2015.

#### \*Answer from answer key:

MOV eax, val2 MUL val3 MOV ebx, val4 SUB ebx, 3 DIV, ebx MOV val1, eax

#### **Q3.** Sec 8.10.1 Do problems 3;

3.

# How does a program using the STDCALL calling convention clean up the stack after a procedure call?

Answer:

We supply an integer parameter to the RET instruction, which in turn adds 8 to ESP after returning to the calling procedure. The integer must equal the number of bytes of stack space consumed by the procedure's parameters. It should be pointed out that STDCALL, like C, pushes arguments onto the stack in reverse order. By having a parameter in the RET instruction,

STDCALL reduces the amount of code generated for subroutine calls (by one instruction) and ensures that calling programs will never forget to clean up the stack.

#### \*Answer from answer key:

A number on the RET instruction corresponds to the number of bytes added to the stack pointer to clear parameters from the stack. This happens after returning to the calling procedure.

#### **Q4 Sec 8.10.2 Do Problems 1,2**


1.

Here is a calling sequence for a procedure named AddThree that adds three doublewords (assume that the STDCALL calling convention is used):

push 10h
push 20h
push 30h
call AddThree

Draw a picture of the procedure's stack frame immediately after EBP has been pushed on the runtime stack.

#### \*Work shown below:



\*An excerpt below just for reference.

#### 8.2.3 Accessing Stack Parameters

High-level languages have various ways of initializing and accessing parameters during function calls. We will use the C and C++ languages as an example. They begin with a *prologue* consisting of statements that save the EBP register and point EBP to the top of the stack. Optionally, they may push certain registers on the stack whose values will be restored when the function returns. The end of the function consists of an *epilogue* in which the EBP register is restored and the RET instruction returns to the caller.

AddTwo Example The following AddTwo function, written in C, receives two integers passed by value and returns their sum:

```
int AddTwo( int x, int y )
{
    return x + y;
}
```


Let's create an equivalent implementation in assembly language. In its prologue, **AddTwo** pushes EBP on the stack to preserve its existing value:

```
AddTwo PROC
push ebp
```

Next, EBP is set to the same value as ESP, so EBP can be the base pointer for AddTwo's stack frame:

```
AddTwo PROC
push ebp
mov ebp,esp
```

After the two instructions execute, the following figure shows the contents of the stack frame. A function call such as AddTwo(5, 6) would cause the second parameter to be pushed on the stack, followed by the first parameter:



AddTwo could push additional registers on the stack without altering the offsets of the stack parameters from EBP. ESP would change value, but EBP would not.

#### \*Answer from answer key:

ESP points to EBP and each row above corresponds to +4, +8 ... bytes so the return address is EBP + 4 and 10h is EBP + 16

#### 2.

Create a procedure named AddThree that receives three integer parameters and calculates and returns their sum in the EAX register.

```
Answer:
AddThree PROC
push EBP
mov EBP,ESP
mov EAX,[EBP + 16]
```

add EAX, [EBP + 12]

```
add EAX,[EBP + 8]
pop EBP
Ret 12
```

AddThree ENDP

#### \*Answer from answer key:

PROC AddThree

PUSH ebp

MOV ebp, esp

MOV eax, [ebp + 8]

ADD eax, [ebp + 12]

ADD eax, [ebp + 16]

POP ebp

RET 12

AddThree ENDP

#### Q5. Sec 9.9.1 Do Problems 1, 2, 12

1.

# Which Direction flag setting causes index registers to move backward through memory when executing string primitives?

Answer:

STD \*(value = 1)

#### \*An excerpt below just for reference.

**Direction Flag** String primitive instructions increment or decrement ESI and EDI based on the state of the Direction flag (see Table 9-2). The Direction flag can be explicitly modified using the CLD and STD instructions:

```
CLD ; clear Direction flag (forward direction)
STD ; set Direction flag (reverse direction)
```

Forgetting to set the Direction flag before a string primitive instruction can be a major headache, since the ESI and EDI registers may not increment or decrement as intended.

Table 9-2 Direction Flag Usage in String Primitive Instructions.

| Value of the<br>Direction Flag | Effect on ESI<br>and EDI | Address<br>Sequence |
|--------------------------------|--------------------------|---------------------|
| Clear                          | Incremented              | Low-high            |
| Set                            | Decremented              | High-low            |

#### 2.

# When a repeat prefix is used with STOSW, what value is added to or subtracted from the index register?

Answer:

2 (STOSW is for AX, which 16 bits, so it is a word or 2 bytes)

#### \*An excerpt below just for reference.

#### 9.2.4 STOSB, STOSW, and STOSD

The STOSB, STOSW, and STOSD instructions store the contents of AL/AX/EAX, respectively, in memory at the offset pointed to by EDI. EDI is incremented or decremented based on the state of the Direction flag. When used with the REP prefix, these instructions are useful for filling all elements of a string or array with a single value. For example, the following code initializes each byte in **string1** to 0FFh:

#### 12.

# In the FillArray procedure from the Binary Search example in Section 9.5, why must the Direction flag be cleared by the CLD instruction?

Answer:

We clear the direction flag to increment ESI and EDI. This is to go from lower range to upper range integers when we fill an array.

#### \*An excerpt below just for reference.

FillArray Following is a listing of the module containing the FillArray procedure:

```
; Fills an array with a random sequence of 32-bit signed
; integers between LowerRange and (UpperRange - 1).
; Returns: nothing
;

mov edi,pArray ; EDI points to the array
mov ecx,Count ; loop counter
mov edx,UpperRange
sub edx,LowerRange ; EDX = absolute range (0..n)
cld ; clear direction flag

L1: mov eax,edx ; get absolute range
call RandomRange
add eax,LowerRange ; bias the result
stosd ; store EAX into [edi]

ret
FillArray ENDP
END
```

#### \*Answer from answer key:

We are starting from index zero and want to move forward in the array with the STOSD instruction so we clear the direction register to make sure we move forward if it happened to be set before.

#### Q6. Sec 9.9.2 Do Problems 1, 2, 4

1

Show an example of a base-index operand in 32-bit mode.

Answer:

[ebx + esi]

\*Some excerpts below just for reference.

### Base-Index Operand

- A base-index operand adds the values of two registers (called base and index), producing an effective address. Any two 32-bit general-purpose registers may be used. (Note: esp is not a general-purpose register)
  - In 64-bit mode, you use 64-bit registers for bases and indexes
- Base-index operands are great for accessing arrays of structures. (A structure groups together data under a single name.)

42

## Base-Index-Displacement Operand

- A base-index-displacement operand adds base and index registers to a constant, producing an effective address. Any two 32-bit general-purpose register can be used.
- Common formats:

```
[ base + index + displacement ]
displacement [ base + index ]
```

CSUS CSC 35 Intro to Architecture: Dr. I. Ghansah

45

#### 2.

Show an example of a base-index-displacement operand in 32-bit mode.

Answer:

val[ebx + esi]

\*Some excerpts below just for reference.

### Base-Index-Displacement Operand

- A base-index-displacement operand adds base and index registers to a constant, producing an effective address. Any two 32-bit general-purpose register can be used.
- Common formats:

```
[ base + index + displacement ]
displacement [ base + index ]
```

CSUS CSC 35 Intro to Architecture: Dr. I. Ghansah

45

### Two-Dimensional Table Example

The following 32-bit code loads the table element stored in row 1, column 2:

```
RowNumber = 1
ColumnNumber = 2
      ebx, NumCols * RowNumber
      esi, Column Number
mov
      al,table[ebx + esi]
mov
150
                         157
                  155
10
    20
       30
           40
               50
                  60
                      70
                         80
                             90
                                A0
                                    B0
                                       C0
                                           D0
                                              E0
                                                  F0
            table[ebx]
                        table[ebx + esi]
table
```

CSUS CSC 35 Intro to Architecture: Dr. I. Ghansah

48

#### \*Answer from answer key:

vall[ebx + esi]; where vall is some variable

#### 4.

Write instructions using CMPSW that compare two arrays of 16-bit values named sourcew and targetw.

Answer:

mov ECX, LENGTHOF sourcew

mov ESI, OFFSET sourcew

mov EDI, OFFSET targetw

CLD

**CMPSW** 

\*An excerpt below just for reference.

### **Comparing Arrays**

Use a REPE (repeat while equal) prefix to compare corresponding elements of two arrays.

CSUS CSC 35 Intro to Architecture: Dr. I. Ghansah

13

#### \*Answer from answer key:

MOV esi, OFFSET sourcew MOV edi, OFFSET targetw

MOV ecx, LENGTHOF sourcew; assume sourcew and targetw are the same length CLD

repe CMPSW