

- 1 BATT switch rmb ON
- 2 Parking brake  Verify SET
- 3 Rearm and refuel ORDER
Max takeoff weight: 51.900 lbs.
Note 'Total Weight' for stab trim.
- 4 APU switch ON
Wait for READY light
- 5 ENG CRANK switch rmb R
Right throttle to IDLE at >18% RPM
- 6 Displays, HUD, HMD ON
- 7 ENG CRANK switch lmb L
Left throttle to IDLE at >18% RPM
- 8 RADAR knob OPR
- 9 INS knob CV / **FIELD: GND**
- 10 HSI page PB19 'STD HDG'
On the bottom display. Verify boxed.
- 11 OBOGS switch ON
- 12 FCS RESET button PUSH
- 13 ANTI SKID OFF / **FIELD: ON**
- 14 FLAP switch HALF
- 15 FCS BIT TEST PERFORM
Hold the 'Y' key. On the BIT page
(right display): press PB9 'FCS-MC',
then PB9 'FCS'. Release 'Y' and wait
about 20 seconds for the 'GO' signal.
- 16 T/O TRIM button PUSH
- 17 STAB TRIM SET FOR TAKEOFF
Left display — press PB18 'MENU'
for 'SUPT' screen, then PB15 'FCS':

SV 1

SV 2

→ 30 RUD ← 30

↑ 12 STAB ↑ 12

SV 1

SV 2

CARRIER:


UNDER 44.000 lbs — 16°

45.000 – 48.000 lbs — 17°

OVER 49.000 lbs — 19°

FIELD:

always 12°
- 18 IFF and D/L ON

- 19 FLIR switch STBY
- 20 Bottom display — verify 'QUAL OK'
is displayed on the HSI page. then:
INS knob **IFA (Redfor: NAV)**
- 21 ALR-67 (RWR) POWER ON
- 22 ALQ-165 (jammer) ... REC or XMIT
- 23 Dispenser ON or BYPASS
- 24 Canopy LCtrl+C CLOSE
- 25 Ejection seat ARM
- 26 HMD Align*
- 27 Chocks Remove
Field / Carrier (no crew): via the menu
Carrier (deck crew): by taxi salute
- 28 Parking brake  OFF
- 29 Nosewheel steering ON
- 30 WINGS SPREAD AND LOCK
CARRIER: Before catapult hook-up
FIELD: Before taxi

***HMD alignment**

1. 'MENU' > 'SUPT' > 'HMD' > box 'ALIGN'. Move head to superimpose HMD cross over HUD cross, then hold [CAGE/UNCAGE] until 'ALIGN OK' is displayed.

2. Use [TDC] to align DX/DY crosses with HUD cross and press [CAGE/UNCAGE] to confirm. 3. Repeat for DROLL cross. 4. Unbox 'ALIGN' to finish alignment.

