

Settings

This table lists and describes the settings for administrative objects that represent UI components. Note that the name and value for each setting are case sensitive.

Setting		
UI Component	Description	Accepted Values/Examples
Access Expression command objects for menus and toolbar items, PowerView tabs, table columns, form fields, generic create forms, configurable search form, tree commands, structure browser pages	Controls access to the component based on a valid MQL expression. The expression gets evaluated at runtime. If the expression evaluates to True and no other access control prevents access, the component is shown, otherwise it is hidden. Depending on the type of expression defined, the program may or may not need a valid objectID. Administrators need to make sure that an objectId is available before configuring this setting for configurable toolbar menus and commands. When the setting is used for commands connected to the an app category menu, or the actions menu on the top bar, the expression is evaluated on the person business object. It does not depend on any objectId to be passed in as a URL parameter. In cases where no objectId is passed, such as a table page originating from an app category menu, the Access Mask needs the URL to have the objectId available to validate. Similarly, the IconMail tree, which does not have an objectId, does not use this setting if defined. Generic Create Form: Do not use object-specific expressions.	attribute[\$ <attribute_weight>].value > 100 The toolbar item displays only if the Weight attribute on the business object is greater than 100. attribute[\$<attribute_originator>].value == owner For menu command objects: context.user.name=="Test Everything" context.user.isassigned[Employee] == TRUE</attribute_originator></attribute_weight>
	Access Expression is not supported for non-object based structure browsers.	
Access Function command objects for menus and toolbar items, PowerView tabs, table columns, form fields, generic create form, configurable search form, tree commands, structure browser pages	The name of the JPO method to invoke in the JPO specified for the Access Program setting. The Access function gets the input parameter as a HashMap, which contain all the request parameters that were passed into the Form page. The JPO method must return an object of class Boolean. If the returned value is true and no other access control prevents access, the component is displayed. If false, it is hidden. This is particularly useful if there is a criteria for access has nothing to do with users' roles. For example, suppose a link should only be shown to users who are employees of the host company. The JPO and method might check the user's company and display the link only if the user is from the host company. Generic Create Form: Do not use object-specific	The name of an access check method in the JPO specified in the Access Program setting, such as: emxAccessCheck()
Access Mask	expressions.	Any act of accessor commented by a commented
Access Mask	Specifies the accesses the user must have for the current business object in order for the component to be displayed. When the setting is used for commands connected to an app category menu or the Actions menu on the top bar, the expression is evaluated on the Person business object. It does not depend on any objectId to be passed in as a URL parameter. When the setting is used for commands in page toolbars, menus, trees, table columns, and form fields, the access mask is evaluated on a specific business object. This business object is available only when the objectId is passed in as a URL parameter to the JSP. Administrators need to make sure that an objectId is available before configuring this setting for configurable	Any set of accesses, separated by a comma. For example: Modify Delete ToConnect ToDisconnect FromConnect FromDisconnect Modify,Delete FromConnect,FromDisconnect

Accepted Values/Examples

UI Component	Description	Accepted Values/Examples
or component	toolbar menus and commands.	I
command objects for menus and toolbar items, PowerView tabs, table columns, form fields, tree commands, structure browser pages, subscription commands	In cases where no objectId is passed, such as a table page originating from an app cagegory menu, the Access Mask setting is ignored. The IconMail tree, which does not have an objectId, does not use this setting if defined. If the user does not have all the specified accesses in the business object's policy for the current state, the component is hidden. If the user has the access and no other access control prevents access, the component is displayed.	
	You can specify multiple accesses by separating the accesses with a comma.	
	Access Mask is not supported for non-object based structure browsers and toolbar custom filters.	
Access Program command objects for menus and toolbar	Controls access to the UI component based on the output from a method in the specified JPO program. The program must be defined in 3DSpace. This setting requires that the Access Function setting also be	Name of a JPO defined as a program object in Live Collaboration, such as: emxAEFCollectionAccess
items, PowerView tabs, table columns, form fields, generic create form, configurable search form, tree commands, structure browser pages	specified. If Access Function is not set, the Access Program setting is ignored. The following input values are required for the program: A list of all of the request parameters in a HashMap Method name as a string JPO Program Name as a string Context The output must be a Boolean. Generic Create Form: Do not use object-specific	
Action Label	expressions. Only used with toolbar commands if Input Type is	emxFramework.SampleFeature.Find
Toolbar textbox	combobox or textbox. If used, a submit button shows after the combobox or textbox and uses the string specified by this setting as its label. The button refers to the JSON code/href specified on the textbox or combobox, so that a second command is not required to configure the button.	Find emxFramework.Common.Filter Apply Filter
Action Type	Tells the configurable toolbar that the command is a separator instead of a link. If the setting is not	SeparatorA line that separates one or more links. If the command is assigned to the top-level menu
command objects for toolbar items	included, the toolbar treats the command as a standard link.	and is therefore on the toolbar itself, it is considered a vertical separator. Otherwise, it is considered a horizontal separator.
Add Input Type columns for structure browsers	Defines the input control used with the insert new row functionality when the structure browser is in edit mode.	 textbox (default) combobox radiobutton listbox listboxmanual
Additional Query	When Type Ahead is configured on the field/column (by	<fieldname1>=<select expression1="">:<fieldname2>=</fieldname2></select></fieldname1>
form object field, table column	setting the RangeHref to emxFullSearch.jsp or using a predefined Type Ahead Chooser), this setting defines additional field/selection critiera used to restrict the selection list. See About Automatic Type Ahead.	<select expression2="">:</select>
Admin Type	Use to translate columns or fields whose values are administrative types or ranges of attributes.	Type State
	Based on the administrative type, the value is translated and presented. For attributes, it is necessary to provide the symbolic name of the attribute, which starts with "attribute_" and is followed by the attribute name with no spaces.	Role Relationship attribute_UnitOfMeasure These keywords get the field values translated for
	For example, suppose you are configuring a field that shows an object's current state and you want the state name to be translated. You would add this setting and set the value to State. The translations for administrative object names are stored in the emxFrameworkStringResource.properties files, as	the appropriate type name: Type State Role

Setting	B. C. Carlo	A
UI Component	Description	Accepted Values/Examples
	described in the Internationalizing Dynamic UI	Relationship
	Components.	Policy
able object column		Group
form object field		Vault
generic create form fields		Attribute (for translating the attribute name, not the range values)
configurable search form		To translate an attribute value and range values, specify the symbolic name of the attribute. For
structure browser		example:
pages		attribute_UnitOfMeasure
Allow Manual Edit	When true, users can manually edit the form row or	attribute_PartClassification false (default)Manual entry is not allowed.
form object field	table column. Applicable only when the range parameter is set to a URL or when the setting format is	trueManual entry is allowed.
generic create object form field	assigned to date or for fields of type combobox. It is ignored in all other cases.	
table object column	When this setting is true, the Admin Type setting is	
configurable search	ignored. For a toolbar link, only used when the format=chooser	
form	setting is defined, which is only used when the Input	
structure browser pages	Control = textbox setting is defined.	
toolbar link commands		
Alternate OID expression	By default, when a column's data is configured to show as a hyperlink using the href parameter, the system	<pre>\$<to[relationship_newpartpartrevision].from.id> \$<to[relationship_ebom].from.id></to[relationship_ebom].from.id></to[relationship_newpartpartrevision].from.id></pre>
table object column	passes the ID of the object for that row in the objectId parameter (tables) or the business object the form	4
structure browser	page applies to. Using this setting, you can configure the hyperlink so a different objectId is passed. The	
pages, form object field	system passes the ID for the object returned from the expression defined in this setting.	
Alternate Policy expression	This setting is required to display the state of any connected objects and show the value translated.	Any select expression that evaluates to a policy of a connected object.
table object column, structure browser pages	This setting is applicable only when the Admin Type setting is set to State.	
Alternate Type expression	When the Show Alternate Icon setting is true, this expression is used to obtain the object type. Based on	<pre>\$<to[relationship_newpartpartrevision].from.type> \$<to[relationship_ebom].from.type></to[relationship_ebom].from.type></to[relationship_newpartpartrevision].from.type></pre>
table object column, form object field, structure browser pages	the obtained type, the corresponding icon is displayed.	\$ <to[relationship_ebom].from.type></to[relationship_ebom].from.type>
Auto Filter	Determines whether users can filter the table rows based on data in the column. If at least one column in	trueThe Filter tool displays in the page toolbar. When clicked, the column is available on the Auto
	the table has is capable of autofiltering, the Filter tool displays in the page toolbar.	Filter Selection page. false (default)The column is not available in the Auto Filter Selection page.
	This setting cannot be applied to any column that has multiple values for a single data column cell.	
	Configuring many columns for auto filtering or applying auto filter to inappropriate columns can potentially have high performance impact when viewing the filtered list. For optimum performance, define a limited number of columns with Auto Filter. Also, choose columns that have a limited set of possible values on which the user may want to filter the table data. For example, state and owner columns. Columns such as description and name are inappropriate because of the unlimited number of values that will result.	
	If passed, the autoFilter URL Parameter overrides this setting.	

Filtering applies to root level objects only.

Description

Accepted Values/Examples

UI Component

Calendar Program	Use to specify the name of a JPO that contains a	The name of a JPO, such as:
Calendar Function table column objects, structure browser column objects, form field objects	Use to specify the name of the method in the JPO specified in the Calendar Program setting that retrieves the non-working days based on the calendar defined for the location.	The name of a function in the Calendar Program JPO, such as: getNonWorkingDays
table column objects	N is the total number of elements. xbar is the mean of the column values Default Label is Standard Deviation.	
	<pre>sd = square root [sum(x - xbar)^2/ (N-1)] Where</pre>	
Calculate Standard Deviation	A setting of true shows the standard deviation of the column values. The formula used for standard deviation is:	true false
table column objects	The median value for the odd number of rows is not rounded since no calculation is done. Default Label is Median.	
Calculate Median	A setting of true shows the middle number of the column values. If there is an even number of values, the average of the two middle values is shown.	true false
table column objects	column values. Default Label is Minimum.	false
Calculate Minimum	A setting of true shows the smallest number of the	true
table column objects	column values. Default Label is Maximum.	false
Calculate Maximum	A setting of true shows the largest number of the	true
table column objects	Default Label is Total.	false
Calculate Sum	Average. A setting of true shows the total of the column values.	true
table column objects	A setting of true shows the Average of the column values. This is calculated using the total of the values in the column divided by number of rows. Default Label is	false
Calculate Average	A satting of true shows the Average of the column	true
Toolbars	Commands not available to a user based on role are always hidden, regardless of the value of this setting.	
	When true, the menu command shows in the list and can be selected by the user. When false, this setting defines whether a menu command is hidden from the user (hide; does not display in the menu) or dimmed (disable) so that it cannot be selected. This setting does not work with Role accesses.	
Access Behavior	This setting works with the results of the Access Expression, Access Mask, or Access Program/Access Function settings. Those settings return a true or false value.	hide (default) disable
Name column in a structure browser	the user to choose the auto number series. The value for this setting is the symbolic name for the type.	
autoNumber	Used for Name columns in an editable structure browser. When autonaming is used for objects, this setting allows	autoNumber=type_HardwarePart
structure browser column	only applies when the input Type setting is textbox.	false(default) The width of the textbox input contol is not constrained and may overlap the adjacent column.
Auto Fit Cell	When true, the textbox input control matches the cell width; it does not overlap the adjacent cell. This setting only applies when the Input Type setting is textbox.	true The width of the textbox input control is constrained to the width of the column.
structure browser column		
table object column		

Setting

UI Component

Description

Accepted Values/Examples

table column objects, structure browser column objects, form field objects	method to get the non-working days for a calendar.	
Color Cue Expression	See Collaboration and Approvals Administration Guide: Color-coded Refinements for a description of how to use the color cue settings.	string numeric
structure browser columns	This setting defines the type of data in the Color Cue Expression Type setting.	regex
	The Color Filter setting must be set to true if you include this setting. Cannot be used on columns where Column Type=ProgramHTMLOutput.	
Color Cue Expression Type	Semicolon-separated list expressions defining how to choose which colors should be shown for which values. When Color Cue Expression=string, this setting is defined in this format:	Gate yellow,Milestone orange,Phase blue,Project Space gray
	<value1>,<value2> <color1>;</color1></value2></value1>	
	<value1> and <value2> define text values that could show in the column and should both show the same color, defined by and <color1>. Use a comma to separate the values, and a pipe to separate the color.</color1></value2></value1>	
structure browser columns	When Color Cue Expression=numeric, this setting is defined in this format:	
	<value1>,<value2> <color1>;</color1></value2></value1>	
	Where <value1> and <value2> define a range. If you define an overlapping range, no colors will be used in this column.</value2></value1>	
	The Color Filter setting must be set to true if you include this setting. Cannot be used on columns where Column Type=ProgramHTMLOutput.	
Color Cue Label	A semicolon separated list of labels to use in the refinement	Small Part;Medium Part;Large Part
structure browser columns	pane for numeric, regex, and date expression types. You should define the same number of labels as colors defined in the cue expression.	
Color Filter	Enables the visual cue (color square) for the column. Only applies if the Auto Filter = true setting is also defined for the column.	true false
structure browser	By default, the visual cues support 24 standard colors.	
columns	If you want to control which colors are used for specific values, set values for the Color Cue Expression Type and Color Cue Expression settings.	
Cols	Used when the input type is set to textarea. This setting	25
form object field	limits the length of the textarea on the form and specifies the visible width in average character widths.	40
configurable search form	If not specified, it uses the HTML default, which is 25.	50
Column Count	The number of name/value columns to draw horizontally. For Create forms, this setting applies only	1 (default)
create form fields	to a field defined with Field Type = Dynamic Attributes.	3 n
Column Icon	Use to display an icon for the column's data instead of	Name of an image file such as:
table object column, structure browser pages	other data. Required when the setting "Column Type" is assigned to "icon".	images/NewWindow.gif images/EditItem.gif
Column Style table object column, form	Defines styles from the CSS for the specific field. To define alignment, use one of these values:	left-align
field	left-align center-align	

- center-alignright-align

For numeric fields, the default is left-align.

Solumn Type	The setting "Column Type" is used when no expression	programThe values for this column are obtained ተራናና ያቸው የታብተና ህቅርት this setting, the
able object en dumn	is defined for the column data.	program and function name are required as
tructure browser		settings.
pages		programHTMLOutputSame as the "program" setting above, except that the column value output is in HTML format. Column values are placed in table cell between and tags. This setting ignores other column settings such as Show Type Icon, href, format, and Alternate OID expression.
		iconUsed when the column values are shown as an icon. The setting "Column Icon" must be defined with the icon to be displayed.
		imageUsed when the column values are images. When used, the column shows the primary image associated with the business object (cannot be used with Structure Browser).
		checkboxUsed when the column values are check boxes shown dimmed or not-dimmed based on the access to the object in that row. This access can be based on business logic and defined in a JPO or it can be role-based and defined by assigning roles to the column. If the checkboxes have no access restrictions, this setting is not required and you can create checkboxes by passing in the parameter selection=multiple to emxTable.jsp.
		separatorUsed to define a column of white space between standard data columns. A separator is especially useful to separate two groups of columns.
		fileShows which hyperlinks to a Quick File Access page listing files checked into or connected to the object. The optional Relationship Filter setting defines how to locate related files.
Comparable	Used only for a table showing a structure compare report. Defines whether the column can be used as a comparison criteria in a structure compare report. By default, all columns are comparable except for Column Types of:	true (default) false
column in table	Image Icon	
Compare Report	Separator Used only for a table showing a structure compare report. Defines whether to show the column in the structure compare report. By default, all columns are shown except for Column Types of:	hide show (default)
column in table	Image Icon Separator	
Confirm Message	Provides a JavaScript confirmation message when users click on the toolbar item. For example, a custom delete message can be configured for the onClick event to	The actual text to display in the confirmation message or a string resource property key. To internationalize the message, a string resource key
command object for toolbar items	display a JavaScript confirm message to the user. The Confirmation dialog has the "OK" and "Cancel" button. Clicking OK proceeds with the processing and Cancel cancels the operation.	must be used: Are you sure you want to delete this object? emxFramework.common.alertMsg
Create Exclude	Comma-separated list of attributes that will not be	For example:
form object fields	included in the webform when opened in Create mode when a field on the webform has been defined as Field Type = Dynamic Attributes.	attribute_Cost
Currency Converter	Specifies whether the target page should include the Currency Converter tool. In the href URL called when the UI component is clicked, the system passes a parameter called CurrencyConverter and includes the value specified for this setting. If the value is True, the target page includes the Currency Converter tool. If this setting is not included, the value is assumed to be false	True False (default)

Setting bjects for navigation trees UI Component command objects for menu links and tools, tree commands, and toolbar items	and the target page does not display the Currency Converter tool. Description This setting should only be used with Sourcing Central.	Accepted Values/Examples
table object columns, form object fields		
Currency Expression table object columns	The name of the currency to convert from. Required for columns whose values are monetary and that can be converted from one currency to another using the Conversion tool and defined exchange rates. The value should be a select clause that returns the value for the Currency attribute for a specific object or relationship, or the actual value. The currency to be converted from should be the currency in which the user entered the data in (the As Entered currency). This setting should only be used with Sourcing Central.	For example, to convert currency data for an RFQ Quotation, the following select clause returns the supplier's currency format. to[Supplier Line Item].attribute[Currency]
Decimal Format	Defines the decimal precision (number of digits after the	5
table and structure browser columns, form fields	decimal point) for displaying values in numeric columns or fields.	2
Default	If a field's value is empty or null and this setting is	The default value you want to display. This can be a
form object field	defined, the default value is displayed for the field. Specifies the default value for a toolbar custom filter,	string resource key or the actual characters you want to fill in as the default. The wildcard (*) can be used for search criteria fields.
generic create object fields	and can be a string resource or static text. If the control is configured as a combobox, the Default value must be one of the Range Display Values or Range	emxFramework.Common.default
configurable search form	Values (depending on which setting you used).	All *
toolbar custom filter		emxFramework.CustomControl.Default
Default Category	Specifies the category that should be selected when the tree first opens or is first inserted into another tree. By default the root node is selected, which means the object's Properties page displays. If the tree contains a category that users frequently want to see, you can use	The name of a tree command object that should be selected when the tree first opens. The command object must be assigned to the tree menu object and if it is not, the root node is selected. Default Category=PMCWBS
menu objects for navigation trees	this setting to have it selected instead. Alternatively, you can pass the DefaultCategory parameter to emxTree.jsp. If both are defined, this URL parameter overrides the setting. A tree does not look for default categories defined for its sub-trees (assigned sub-menus).	Default Category = FINE WBS
Default Function	Specifies a JPO used to populate the default value when	JPO name
columns in structure browser	using the add existing row functionality.	
Default Program columns in structure browser	Specifies the method within the JPO specified by the Default Program setting.	method name in the JPO
Delimiter	When using Input Type = dynamictextarea setting, this setting defines the character that separates values when the field is in View mode. In Edit mode, each value shows on a separate line. A comma is the default delimiter.	<any string="" value=""> , (default)</any>
form object fields	If you specify any of these characters as the delimeter, a comma is used instead: \$ \' " * ? () >	
Diff Code	When multiple columns in a structure compare Complete Summary Report have different values, this setting defines what to show in the Diff Code column. The code value for the column with the lowest precedence shows in the Diff Code column. Multiple columns can have the same precedence, and if both columns have different values, both code values show in the Diff Code column.	<pre><pre><pre><pre><pre>4 1:Attribute</pre></pre></pre></pre></pre>

Setting Structure browser Columns JI Component	Description	Accepted Values/Examples
Display Format	Specifies the number of the date format for any non-	3 - SHORT (12/12/52)
able object columns	editable column or field where the value of the format setting is "date."	2 - MEDIUM (Dec 12, 1952)
orm object fields		1 - LONG (December 12, 1952)
configurable search		0 - FULL (Tuesday, December 12 1952 AD)
orm structure browser		Default is set in emxSystem.properties: emxFramework.DateTime.DisplayFormat=MEDIUM.
pages		emxSystem.properties uses words, but the Display Format setting uses numbers.
Display Time	Controls whether the time is displayed along with the date for columns and fields whose format is set to date.	true
able object columns	If no time zone preference is set, then the DateTime is	false
orm object fields	shown in the browser's time zone. The time is shown in	Default is set in emxSystem.properties for the property emxFramework.DateTime.DisplayTime
configurable search orm	terms of GMT+/- hh:mm, (e.g., Saturday, August 21, 2004 12:45:00 PM GMT-04:00). To get the time in a format like EST or PDT, set the time zone preference to	property constrained and account of the proper
structure browser pages	a specific zone.	
Display View	When defining a menu or command for a page-level	Detail
menu or command for a page-level toolbar for a	toolbar for a structure browser, defines whether that command shows in a specific view. The views are	Tree
structure browser		Thumbnail
	selectable from the menu. The value is a comma-	Detail,Tree
	separated list of these possible values:	Detail, The Detail, Thumbnail
	Detail (the Table view in the menu)	
	Tree (the Graph View)	Thumbnail,Tree
	Thumbnail	Detail,Thumbnail,Tree
	For example, if the setting <code>Display View=Detail</code> , <code>Tree</code> is defined for a command, that command is only enabled when the user is viewing the structure browser in either the Table view or the Graph view. If viewing the Thumbnail view, that command is not available.	
Draggable	Specifies that the item in this column can be dragged to	true
structure browser columns	another location within the structure browser. Default is false.	false (default)
Orop Actions	Specifies the drag-and-drop functions allowed on this	Copy,Move
tructure browser	column.	Copy (default)
columns	Default is Copy.	Move
Prop Directions	When connecting a dropped item to its parent (using a	from
structure browser	relationship specified by the Drop Relationships setting), specifies the end of the relationship used for the dropped	to
columns	item.	
Orop Items	Indicates if one item or multiple items can be dropped into this column in a single operation.	Single
structure browser columns	Default is Single.	Multiple
Orop JPO	Defines a JPOName:methodName used to perform the	
structure browser columns	required action, if that action is anything other than connecting the dragged and dropped on items.	
Drop Relationships	Comma-separated list to specify the relationships used to	relationship_EBOM
structure browser columns	connect a dropped item to the context item. You can use the symbolic or actual name of the relationship. To define any other action than connecting the dragged and the dropped on item, use the Drop JPO setting.	
Orop Types	Comma-separated list to specify the object types that can	type_Part,Document
structure browser columns	be dropped into this column. You can use the symbolic or actual name of the object type.	
	Specifies that objects can be dropped into this column.	A
Oroppable	1	true

structure browser	Description	Accepted Values/Examples
displayMode	Defines in which mode, Edit or View or Both, that this column is visible. When used, the visibility of the column is defined by the current mode and the value of this setting instead of any Access Expression.	Edit View Both (default)
columns used by emxIndentedTable.jsp	For example, if the table is in view mode and this setting is Edit, then the column is not visible.	
	This setting applies to columns used in the emxIndentedtable.jsp only; it does not work for columns in flat tables (emxTable.jsp).	
Dynamic Command Function	Defines the method in the JPO specified by the Dynamic Command Program setting that returns a list containing the data structure to build the right-click menu or the	<jpo method="" name=""></jpo>
toolbar menu objects	categories to add to a tree. In general, the list contains dynamic options based on the user context.	
tree menu objects	This setting is only used with the right-click menu component and the toolbar component.	
Dynamic Command Program	Defines the JPO invoked from a right-click menu, navigation tree, or toolbar menu component.	<jpo name=""></jpo>
toolbar menu objects		
Dynamic Field Function	When the Field Type setting is set to Dynamic, this setting defines the method in the Dynamic Field Program used to	getDynamicAttributes
emxCreate.jsp emxForm.jsp	retrieve attributes that have the IPML.CustoUserAccess property set to ReadWrite or ReadOnly. getDynamicAttributes is provided by BPS for this purpose.	
Dynamic Field Program	When the Field Type setting is set to Dynamic, this setting	emxUnifiedTyping
emxCreate.jsp emxForm.jsp	defines the JPO that contains the method used for adding dynamic attributes to forms. emxUnifiedTyping is provided by BPS for this purpose.	
Dynamic URL	When enabled, users can enter URLs or mxLink values	enable (default) disable
form and create form object fields	and the values will display and function as hyperlinks.	
table column objects		
structure browser columns		
Edit Access Mask	Use to control cell-level access in an editable table.	Any access mask, for example:
table column objects	This access check is done on all objects in one database	modify, connect
structure browser	call along with getting the column values. If any cell does not have the specified access, then the cell is shown as read only.	
Edit Exclude	Comma-separated list of attributes that will not be	For example:
form object fields	included in the webform when opened in Edit mode when a field on the webform has been defined as Field Type = Dynamic Attributes.	attribute_Cost
Editable	Use to indicate whether the column or field is displayed	trueUsers can edit the column or field when
table column objects,	as editable or read only. Only applies for Edit mode. View mode ignores the setting.	shown on the Edit mode form. falseUsers cannot edit the column or field when
form object fields, generic create form fields, configurable search form, structure browser	For forms, default is true. For tables and structure browser, default is false.	shown on the Edit mode form. The field looks just like it does in View mode except it is never hyperlinked.
Effective Date Expression	Used for columns whose values are monetary and that can be converted from one currency to another using defined exchange rates.	For example, for currency data for an RFQ Quotation, the following select clause returns the effectivity date.
table object columns	The value should be a select clause that provides the	to[Supplier Line Item].attribute[Effectivity Date]
	value for the Effectivity Date attribute on a specific object or relationship. The system uses this date to get the currency conversion whose rate period falls within this date. If this setting is not added, the current date is used.	2
Expand Function	Specifies the function in the JPO specified in the Expand Program setting that gets the list of child nodes for the	Name of a method in the Expand Program JPO.
tree command	tree category.	

EXDADO IDOUIEV	Use to configure the tree category name so a list of	Name வெள்ளுள்ளுள்ளாக object that
Expand Inquiry UI Component	business objects is inserted under it automatically, without users having to first view details for objects. For example, Folder categories are often configured to display all folders without users having to view the	retrieves the business objects to list for the category: TMCFolder
	folders first. Use this setting to define the list of business objects using an inquiry administrative object.	TMCSubFolders
ree command objects		ENCEBOMList
	You can also define the list using a JPO with the Expand Program and Expand Function settings. If both an inquiry and JPO are specified, the JPO takes precedence.	
Expand Program	Use to configure the tree command so a list of business objects is inserted under it automatically, without users having to first view details for objects. For example, Folder categories are often configured to display all folders without users having to view the folders first. Use this setting to define the list of business objects using a JPO. You can also define the list using an inquiry with the Expand Inquiry setting. If both an inquiry and JPO are specified, the JPO takes precedence.	Name of a JPO program added to the database.
ree command object	This parameter specifies a JPO that contains a method to get the list of objects to insert under the category name. The method is specified using the Expand Function setting.	
	Important Note: This feature is recommended primarily for hierarchically organized categories such as Folders and Subfolders. For best performance and consistency of behavior across applications, the preferred method of navigation is to use the standard tree behavior that does not use a dynamic expand. If conditions require the use of this setting, try to restrict its use to categories that will contain relatively few objects.	
Expanded	When defining a menu or command for a page-level toolbar or the RMB (right-mouse-button, also called the context menu), specifies if the menu should be automatically expanded when the user selects it. Possible values:	True False (default)
menu or command for a page-level toolbar or the RMB	 When False and a user opens the menu, the triangle pointer shows to allow the user to expand and collapse submenus. Submenus are not expanded (unless the submenu has the Expanded=True setting defined). When the submenu is expanded, scrollbars appear if needed. When True and the user opens the menu, the menu shows all submenus fully expanded (unless a submenu has the Expanded=False setting defined). The user cannot collapse the menu (the triangle pointer does not display; an icon shows in its place) and no scrollbars appear. 	
	You cannot use this setting for the top bar or any My Desk menus (the menus that load categories into the navigation pane when a user opens an app from the compass).	
Export	Specifies whether or not column data is exported. Use this setting to change the export value on a column-by-column basis. By default, all column types except programHTMLOutput are exported. To include	true false

table object columns structure browser

Teld Column Headers Form object field UI Component Create form object Field	Used in conjunction with the Field Type=Table Holder setting. Specifies the labels for the column headings. The fumber of labels should be the same as the value for the Field Table Columns setting and should be separated by a comma.	Comma-separated list of column heading labels: Mitta Max Avglues/Examples
Field Row Headers	Used in conjunction with the Field Type=Table Holder setting. Specifies the labels for the row headings. The	Comma-separated list of row heading labels: Weight, Volume
form object field create form object field	number of labels should be the same as the value for the Field Table Rows setting and should be separated by a comma.	Weight, voiding
Field Size	Determines the width of a textbox input type field. The	Number of pixels, for example:
form object field	width is given in pixels except when Input Type is textbox or not set. In that case, its value refers to the	30
configurable search form	(integer) number of characters.	20 is the default.
create form object field		
Field Table Columns	Used in conjunction with the Field Type=Table Holder	2, 3,
form object field	setting. Defines the number of columns for the table.	
create form object field		
Field Table Rows	Used in conjunction with the Field Type=Table Holder setting. Defines the number of rows in the table.	1, 2,
form object field		
create form object field		
Field Type	Setting used only in edit mode while updating the table data.	basicThe column displays basic information for the business object. Basic information includes name, type, originated, policy, etc. Specifying basic as the field type is only needed when the column is editable. The only editable basic information is: type, name, revision, current, policy, description,
table object columns		owner, vault. attributeThe column displays values for an attribute on the business object, such as Originator or Weight.
Field Type	This setting is used for several purposes: To indicate that the field's data should be obtained from a program or image instead of an expression.	programThe values are obtained from a program (JPO). The program and function name are required as settings.
	When the field data is obtained from an expression, if the data is basic information or an attribute. The system needs to know whether a field's data is basic information or an attribute in order to update the information correctly. Specifying whether the field is basic or an attribute is only required for fields that will be editable.	programHTMLOutputSame as program, except the field value output is in XHTML format. Field values are placed in the table cell between and tags. This value ignores other field settings such as Show Type Icon, href, format, and Alternate OID expression. ClassificationPathsUsed only with Library Central. Displays the paths where the object is classified,
	To indicate the field is a dummy field that defines fields to display in a table or group. These Field Type values that are supported by emxForm.jsp are NOT supported for emxCreate.jsp: emxTable, Table Holder, Group Holder,	with a separator between hierarchies. This separator is configurable with the Library Central property string emxLibraryCentral.ClassPathSeparatorString. The default separator is ''.
	ClassificationPath, ClassificationAttributes.	ClassificationAttributesUsed only with Library Central and the Multiple Classification Module. Displays the attributes acquired via classification. If the object is classified, it displays the classification name as the heading, then displays a subheading with the name of the attribute group, then attributes and their values acquired from the attribute group.
form object field		If the same attribute is repeated in another attribute group or in another classification, this field displays a message underneath the field: "This value also appears in another Attribute Group." If a

generic crete form object field configurable search form create form object	Description	user modifies one attribute that has other occurrences in different attribute groups, this accepted by updates and other occurrences of the attribute. If the object is classified but no attributes are acquired via classification, this field does not display anything.
field		Dynamic AttributesDisplays all attribute/value pairs associated with the context object in the properties page.
		imageThe primary image associated with the business object.
		basicDisplays basic information for the business object: name, type, originated, policy, etc. Use only when the field is editable. The only editable basic information is: type, name, revision, current, policy, description, owner, vault.
		attributeThe field displays values for an attribute on the business object, such as Originator or Weight.
		Section HeaderAdds a new section heading between the form fields. The setting Section Level determines the heading level.
		Section SeparatorAdds white space to separate fields and sections.
		Group HolderGroups the fields under the field in one row. Uses the Group Count setting to determine the number of fields to group. When a field has a Field Type of Group Holder, it serves as a dummy field to define the group and does not appear on the form.
		Table HolderArranges the fields under the field in columns and rows. Table Holder fields serve as dummy fields to define the fields to display in a table.
		emxTableEmbeds a configurable table in the form. Used in conjunction with the table setting and either the inquiry or program setting.
		Dynamicadds any attributes created using the Parameterization Console to the form. You must also define the Dynamic Field Function and Dynamic Field Program settings.
format	Specifies the type of data in the field. If the Editable setting is true and the field is on an Edit mode form,	dateUses the tag lib "emxUtil:IzDate" to format the displayed field value.
form chiest field	the system uses these format values to validate the field value. Validation takes place on the client side,	currency
form object field create form object field	before updating the object displayed in the form. To support the date compare logic, whenever the field format is "date", an additional hidden parameter is	numericUse if the value must be validated as a number before updating the values. Applicable only in Edit mode.
configurable search form toolbar	added to the form with the name assigned to the web form field name suffixed by "_msvalue". If there is a valid display value for the date, the hidden parameter is assigned with the value that is the equivalent of	emailDisplays the column values as an email address. When a user clicks the email address, the email editor configured in the client is presented.
	displayed date in milliseconds (calculated from midnight, January 1, 1970).	userUsed for create forms (when Editable=false) to add read-only field to support using fullname
	This hidden parameter value can be used by the validation methods to compare two dates. Note: The hidden parameter gets updated only when the out-of-the-box calendar component is used to change the date. If the field type is changed to manual edit, the hidden parameter may not have the updated	chooserUsed only on a toolbar with Input Control = textbox when the entered text should be a date or a chooser. The browse button shows after the text box.
	milliseconds value when the field is manually changed. In this case the validation method can simply ignore the date compare and must depend on the server side validation. The client side validation can be ignored by checking if the field is readonly.	
format	For custom filter commands, date is the only supported	dateDisplays the column values as a date. Uses
toolbar commands	format. When used, the calendar tool shows after the text box.	the tag lib "emxUtil:IzDate" to format the display.
format	Specifies the format to display the column data. If at least one column has the format set to currency or UOM, the Conversion tool displays in the page toolbar.	dateDisplays the column values as a date. Uses the tag lib "emxUtil:IzDate" to format the display. currencyDisplays the column values as currency.

Setting table object column UI Component structure browser	when a user clicks the tool, the system opens a new window and displays all column data defined with formatproperty and UOM to the currency and unit of measure selected in preferences.	UOMDisplays the column values as Unit of Measure and enables the Unit of Measure conversion interface. emailDisplays the column values as an email address. When a user clicks the email address, the	
		email editor configured in the client is presented. numericDisplays the column values as numbers. To perform calculations or graphically analyze the data on a column of string attributes that have numerical values, numeric must be the column type	
function	The name of the method to call within the JPO program	The name of a function in the program JPO, such	
form object field,	specified in the program setting. This method within the JPO is used to get the field values if the setting "Field	as: getAssignedBuyerDesk	
generic create object field, configurable	Type" is set to "program" or "programHTMLOutput", or for tables, "checkbox".	getPackageAccess	
search form, table	ion tastes, directory	getParentPart	
object column, structure browser		getCurrentState	
Group By	Groups rows in the table based on the value in this	true	
	column. See Group By Column.	uue	
table column			
Group Count	Used in conjunction with the Field Type=Group Holder setting. Specifies the number of fields below the Group	2, 3, 4,	
form object field	Holder field to place in the grouped row.		
Group Header	Defines header text to display over several consecutive columns. For example, if you want a group header over	Static text or string resource id.	
table object column	three consecutive columns, add this setting to each column and assign the same value for each.		
structure browser	To separate grouped columns using a column of white space, add a separator using Column Type=Separator.		
Group Name	Used for grouping fields in web forms and structure browser. The consecutive fields with same group name	The name of the group.	
form objects	are considered a group.		
configurable search form			
create form object field			
structure browser			
Help Marker	Specifies the name of the help marker to call for	The naming convention for help markers "emxhelp"	
menu objects for navigation trees, command objects for menu links and tools, tree commands, and toolbar items, table object columns, form object field, configurable search form	context-sensitive help. In the href URL called when the UI component is clicked, the system passes a parameter called HelpMarker and includes the marker text specified for this setting.	followed by the object or feature and then the action, for example, emxhelproutecreate and emxhelpprojectedit. The marker is all lowercase with no spaces.	
Hide Label	Displays or hides the label for a particular row on a	True	
form object fields	form.	False	
generic create form fields			
configurable search form			

Hide Mode		parated list indicating the system via that mode, en.		Desktop Mobile,Cloud
toolbar menu object	Value	Hide component if access mode is:	Show component if access mode is:	!Mobile
command objects	Desktop	Desktop	Cloud or Mobile	
		Mahila	Daaldan an Claud	

form object fields	Mobile	морие	Desktop or Cloud	
form object fields Setting command objects for	Cloud	Cloud	Desktop or Mobile	Assembled Values / Evenuelles
topleampolent	Description ! Desktop	Mobile or Cloud	Desktop	Accepted Values/Examples
	!Mobile	Desktop or Cloud Hide component if Mobile or Desktop access mode is:	Mobile Show component if Cloud access mode is:	
		g is not defined, then the e as long as the user ha	e component is	
	 global to menu sp passed to menu fo	pecified by the tableMento emxIndentedTable.js	u URL parameter p	
Image	Name of the	image file to display on	toolbar tool	iconPerson.gif
	commands.			buttonReports.gif
	The value ca	n be one of the followin	g:	\${COMMON_DIR}/buttonEdit.gif
command objects for		mage (gif) file name wit assumes the image is re		\${SUITE_DIR}/iconCreateECR.gif
toolbar tools		tory and prefixes it with		If no image is specified for a tree root node, the
tree command	An image file	e name prefixed with \${	COMMON_DIR}.	system displays the standard no image icon to
objects		ooks for the file in the i		indicate there is an error in the definition of the tree.
configurable Preferences page		ory designated as the conditional distribution of the condition of the con		
Treferences page		eFramework.CommonD	2	
	emxSystem.	properties.		
	system looks subdirectory is defined us property in e property for	e name prefixed with \${ s for the image file in th of the application-spec ing the eServiceSuiteSt emxSystem.properties. I Engineering Central is eEngineeringCentral.Dir entral.	e images ific directory which JITENAME.Directory For example, the	
Image	Use to specif	y an image file when th	ne field value should	images/newPart.gif
	be an image	only. This setting is req	uired when the	images/EditItem.gif
form object field	, , ,	etting is set to image. The on server (not in the da		
generic create form	make the im	age a hyperlink by inclu		
fields	href paramet	ter.		
Image		image used for the me		\${COMMON_DIR}/iconSmallOrganization.gif
toolbar menu object	if a label has label.	been defined but requi	red if there is no	
Image Manager Toolbar		fault toolbar to use for t	the Image category for	<toolbar name=""></toolbar>
	an object typ	e if a specific toolbar is	not defined. For Image	
toolbar menu object		equire access or other s	ettings different from n toolbar with a custom	Sompan, imager ranager rootbur
		d command for that page		
Image Size	When image	is the Column Type of a	a table or the Field	format mxSmallImage (default)
-3	Type of a we	b form, this setting defi	ines which size of	format_mxMediumImage
table object column		image associated with t ay in the column. The pi		format_mxIncularimage
Form object field	these sizes a	re defined using the		
	· ·	ents.Image. <i>Size</i> ImageS		format_mxThumbnailImage
Image Upload Command		fault command used for om command is not req		<command name=""/>
toolbar menu object	Tricii a custo	on communa is not req	un cui	APPCompanyUploadImage

Input Type	Only used for tables or forms in edit mode. Specifies	The setting accepts the values listed below:
form object field configurable search	allow for appropriate spacing. This is important for	textbox-This is the default. The field has a single-line box for typing text. textarea-The field has a multi-line box for typing
table column object	short numeric entry fields. Although multiple choices can be displayed in a webform, only one selection can be saved during edit.	text combobox-The field has a drop-down list of options

Setting toolbar textbox UI Component	To disable the ability to make multiple selections during view of webform, you need to use programHTMLoutput and the home that does that.	and users can only select one value. Use comboboxes for attributes that have defined ranges and for attributes whose regions are determined with a Range Helper URL.
	Use the radiobutton or combobox input types for fields that require a single selection.	listbox-The field has a list of range values. Although users can select more than one item in the list by
	To save multiple selections, a custom JPO needs to be written using the checkbox or listbox input types which might delimit the choices in the attribute using the	holding the Ctrl key, it's best to use check boxes for multiple selection fields. radiobutton-For forms only. Shows a radio button
	Studio Customization Toolkit. For toolbar commands, textbox, combobox, and submit	next to each range value. checkbox-For forms only. Shows a check box next
	are supported. For controls other than toolbar commands, submit is not supported.	to each range value. For fields that allow multiple selections, use check boxes instead of a list box.
	If you specify checkbox or radiobutton for an attribute with the String datatype, the attribute must be defined with a range or an error occurs when the form is in Edit mode.	listbox-For forms and columns only. Provides a list of range values. Although users can select more than one item in the list by holding the Ctrl key, only one value will be saved unless a custom JPO is implemented.
	If using dynamictextarea with a form field, the Delimiter setting also needs to be defined if you want to use a delimiter other than the default (comma).	listboxmanualFor structure browser columns. Provides a list of range values and users can select a single value as with the listbox input type. In addition the user can manually type in a value.
		submitSubmit button configured to send contents of input control to a processing page.
		dynamictextarea-Allows multiple values to be entered in Edit mode
inquiry	Used only for fields defined with Field Type=emxTable. Either this setting or the program setting must be used	Names of inquiry administrative object separated by a comma.
form object field	to define the objects to retrieve. Specifies the inquiry administrative object that should be used to retrieve the business objects to be included in the table.	inquiry=SCSBuyerDesk,SCSBuyerDeskAssigned inquiry=ENCAllParts, ENCReleasedParts
Label	Use to enter the text that should appear as the label for the field.	
configurable search form	the neit.	
Label Function	Specifies the function in the JPO specified in the Label Program setting that gets the value for the root node	The name of a method in the Label Program JPO.
menu objects for navigation trees	label.	
tree command objects		
Label Program	Use to define the label for the root node/tree command using a JPO. This setting specifies a JPO that contains a method to get the value for the label. The method is	The name of a JPO that has been added to the database.
	specified using the Label Function setting. The input for this JPO must include:	If a JPO is configured for a tree command or root node label and the JPO returns an empty string or null, an exception is thrown.
	A list of all of the Request Parameters in a HashMap	nan, an exception is all only
	Method Name as a string JPO Program Name as a string	
	The output should be the string that is returned to the tree and used for the label.	
	There are two other ways to define the label for a tree node: using the TreeLabel URL parameter passed to emxTree.jsp and using the Label parameter for the menu object. The URL parameter takes precedence over the other two methods, then the JPO, then the Label parameter.	
	Tree command labels can also be defined using a Label parameter for the command object. The JPO takes precedence over the parameter.	
menu objects for navigation trees		
tree command objects		
Level	Define the values to show in the Expand filter combo	1,2,3,4,5

toolbar menu object	The values for this setting can be:	Specify
	pegmanated list of positive integers	Custoffed Values (Ver 1970) Example, End Item)
UI Component	All	
	Specify	
	Text to be processed by the expandProgram JPO.	
	You cannot use custom levels if the structure browser is filtered using relationship/type/direction.	
	The All and Specify reserved keywords control specific levels of expansion.	
	Use the Label setting to define the string resource or static text for the label that shows in front of the expand combo box; use the Registered Suite setting to define the application that defines the menu for the expand filter or the expand Program JPO.	
Lookup Input Type	Defines the input control used with the add existing row functionality when the structure browser is in edit mode.	textbox (default) combobox
columns in structure browsers	idirectoriantly when the structure provider is in each mode.	radiobuttonlistboxlistboxmanual
Mass Update	Used only for Edit mode. If set to false for the column, the column is not available to the Mass Update feature,	true
columns in tables and structure browsers	but can be edited using the inline editing (one cell at a time). If set to true, the column is used by the Mass Update feature.	false
Maximum Length	Limits the number of characters that can be entered in	Number of characters, for example:
orm object field	a field with Input Type of textbox. If not specified, it uses the HTML default (unlimited).	30
generic create form ield		
configurable search Form		
Maximum Length	Limit the number of characters that are displayed on	Any number of characters, such as 25
toolbar menu object	drop-down menu label. The Title property of the button is used as the Alt text to display the full label.	If this setting is not set, the toolbar displays the entire label.
Message URL Label	Specifies the label to use for URL links that call the tree. For example, notifications that users have new tasks include URL links that open the Inbox Task tree for the user's task. By default, the URL link label shows the	The value can be any select statement, plain text or a string resource ID. For example: \$ <attribute[attribute_title].value> Task Title</attribute[attribute_title].value>
navigation trees	name of the Inbox Task object, which is an auto generated name. But if the route creator entered a name for the task, it is better to show that entered name for the URL link.	emxEngineeringCentral.TaskTitle The string resource Id can contain macros also, as
	To have the URL link show the task's entered name, add the Message URL Label setting to the tree menu object for the Inbox Task. The value would be a select macro for the attribute that contains the entered name, in this case the Title attribute.	in the following example: emxEngineeringCentral.TaskTitle= \$ <type> \$<name> \$<revision>: Urgent Task</revision></name></type>
	When building the URL link, the system first looks for the Message URL Label setting on the application	
	specific tree menu, for example, ENCtype_InboxTask. If not found there, the system looks for the setting in the common tree for that object type. If the common tree does not contain the setting, the system defaults to the object's Type,Name,Revision (for example, Inbox Task IT-0000101).	
Mode	Used for structure browser only.	edit
toolbar manu shir-t	If defined for a toolbar command, that command is only enabled on the toolbar in the indicated mode (Edit or View). If not defined, the command is enabled in both Edit and View mode.	view
coolbar menu object	If defined for a toolbar top-level menu, the entire toolbar only shows in the indicated mode and is hidden in the other mode.	
Mouse Over Popup	Enables or disables the mouse over popup DIV that displays the entire contents of the cell.	enable
columns used in	When enabled, the popup shows in both View and Edit	disable (default)

Setting	mode.	
Name Field UI Component	Desines tow the name field for the object will display in the form:	autoritemeValues/Examples
	autoName-only the autoName option is available	keyin (default)
generic create form	'	both
field	keyin-a textbox is provided for text entry	
	both-both a textbox and the autoName checkbox shown for the name field	
Nowrap	If the setting is true for any field or column, then the	true
Nowrap	text displayed in that field or column will not wrap at	
	any time. The default is false.	false
form fields	When wrapping is used, the text is wrapped at a	
table object columns	convenient space between words, or in the middle of a text string (for long strings that exceed the column width).	
Number Format	This setting only affects how numbers are displayed. Numbers being entered or edited do not show any formatting.	true false (default)
structure browser columns, form object fields	When true, values are displayed using the format for the thousands and decimal separators based on the user's browser locale.	
neius	When false, values are displayed as they are stored in the database, without any formatting.	
	This setting only applies to numeric attributes if the	
	format setting is defined as numeric.	
Popup Modal	If the setting Target Location is set to popup, the	truethe popup window is modal
	window can be configured as modal or non-modal.	
command objects for		falsethe popup window is non-modal
menu links and tools,		If the setting is not specified, the window is modal.
toolbar items, table object columns,		
structure browser,		
Popup Modal	Use to configure whether the popup range helper	truethe popup window is modal
Рорир Моцаі	window is model or non-modal. Only used when the	
form object field	setting Target Location is set to popup.	falsethe popup window is non-modal
configurable search	If a form Component is opened in a dialog in edit mode	If the setting is not specified, the window is modal.
form	then the dialog must open as a modal dialog. For example, if a table column is designed to pop up the Form Component in edit mode, then that column must have a setting Popup Modal=true to open the dialog as modal dialog.	
Popup Size	Defines the size of the popup window. The value can be one	Small
command objects for	of the listed example sizes.	Medium
menu links and tools	The pixel width and height values for these sizes are	• Large
command objects for	defined in emxSystem.properties. See Collaboration	SmallTall MediumTall
toolbar items, form	and Approvals Administration Guide: Properties for	- Treatainian
object field, structure	Popup Windows.	
prowser, configurable		
search form field		
PreExpand	Determines whether to let the JPO program decide whether to add the [+] icon or to simply add the [+]	trueThe Structure Program and Function defined for the Structure command is run to get the list of
	without running the 100	objects. Then for each object, it must be some
	without running the JPO.	objects. Then for each object, it runs the same program to determine whether a [+] icon is needed. If the list of objects is greater than 1, a plus [+] is added to the structure node.
		false (default)The JPO Program and Function is
command objects for structure trees		run to get the list of objects, but the same program and function is not run again for each object. Instead, a plus icon [+] is automatically added for each structure node.
PreExpand Category	Used in conjunction with the Expand Program and Expand Function settings or the Expand Inquiry setting, which inserts a list of objects under the tree category name without requiring users to first view details of	truePre-processing is allowed so if there are no objects, the + sign for expanding the list is not shown.

Setting	those objects. Use this setting to determine whether the tree pre-processes the JPO or inquiry to determine of the tree are any objects to be listed.	raise (derauit)Pre-processing is not allowed so the + sign is displayed even if there are no business phiested that list the inquiry or JPO is not
UI Component	Pre-processing offers the benefit of determining in advance that there are no business objects in the list so the + sign for expansion is not shown. But pre-processing lowers performance.	processes until the user clicks the + sign.
tree command objects	Administrators who configure this setting as true need to be aware of the performance implications to doing so. While it is nice to only display the + sign when data is present, the tree must actually go and get the data at the time the tree displays to do this. Therefore, if there are many tree commands configured with PreExpand	
	Category set to true, each of those tabs will be evaluated when the tree is displayed regardless of whether the user actually intends on viewing data in those categories or not. This potentially unnecessary processing lowers performance.	
PreExpand Function tree command objects	Specifies a method in the JPO defined in the Expand Program setting that configures the category for dynamic expand. This method determines whether there are any business objects in the business object list retrieved from the JPO, thereby determining	Name of a method in the Expand Program JPO.
objects	whether the + sign should be displayed. Use of this setting requires a change in Live Collaboration that has not yet been implemented.	
Printer Friendly	Passes the PrinterFriendly parameter and the entered value to the JSP specified in the href URL. JSPs that use	True (default)
menu objects for navigation trees command objects for menu links and tools, tree commands, and toolbar items	the PrinterFriendly parameter, such as emxTable.jsp and emxForm.jsp, show the Printer Friendly tool when the setting is True and hide it when False. If the setting is not included, emxTable.jsp and emxForm.jsp show the tool by default. Users can click the tool to get a version of the current page that can be printed with the	False
table object columns	browser's Print button. Note that you can also specify the PrinterFriendly	
form object field program	Use to specify the name of the JPO program to use to get the field's data when the Field Type setting is set to	The name of a JPO, such as:
form object field	"program" or "programHTMLOutput". Also can be used for fields defined with Field	SCSBuyerDeskForm TMCPackagesForm
generic create form field	Type=emxTable to define the objects in the table. Alternatively, inquiry can be used.	ENCPartForm
configurable search form	Using a JPO to populate field data is recommended only when a select expression cannot be used to obtain the field value.	AEFUtilForm
program	The name of the JPO program to use to get the column's data. This program is used to get the column	emxSCSBuyerDesk emxTMCPackages
	values when the setting "Column Type" is set to "program" or "programHTMLOutput" or "checkbox".	emxENCParentPart
		emxCommonTableUtil
	Using a JPO to populate column data is recommended	
table object column	only when a select expression cannot be used to obtain the values.	
Pull Right	Determines whether the drop-down links are displayed in the same level as the menu or pulled right to display	True (default) False
toolbar menu object	the links in the next level. Applies only to second-level drop-down menus.	1 0130
Range Display Values	Only used with toolbar commands if Input Type=combobox. Holds a comma-separated list of string resources or static text values used to populate	emxCustom.Combo.Value1, emxCustom.Combo.Value2, emxCustom.Combo.Value3
toolbar custom filters	the combobox. If this setting is not specified, the Range Values setting	Value1,Value2,Value3

Setting	is used.	
Range Function	Description the name of the method in the JPO	កែខេត្តដាក់ខ្លួំ Vala មានកែខាត្ត Program JPO,
UI Component toolbar custom filters	specified in the Range Program setting. See the Range Program setting below for more information.	such as:
table columns	Only used with toolbar commands if Input	getAssignedRange
table columns	Type=combobox.	getClassificationRange
		getPartUOM
Range Program	Use to specify the name of a JPO that contains a	The name of a JPO, such as:
	method to get the input control value ranges (choices).	ENCParts
		AEFUtils
toolbar custom filters		
table columns		
	A range program is used only when the Input Type setting is combobox.	
	If the column will be used in a structure browser and	
	you want the mass update tool to allow editing of the	
	column, you must also pass the massUpdateTCL=true URL parameter to the structure browser.	
	ORL parameter to the structure browser.	
Range Values	Only used with toolbar commands if Input Type=combobox. Holds a comma-separated list of	Value1,Value2,Value3
toolbar custom filters	values used to populate the combobox.	
Range Function	Use to specify the name of the method in the JPO	The name of a function in the Range Program JPO,
-	specified in the Range Program setting. See the Range	such as:
form object field	Program setting below for more information.	getAssignedRange
configurable search form		getClassificationRange
		getPartUOM
table object columns		
structure browser		
Range Program	Use to specify the name of a JPO that contains a	The name of a JPO, such as:
£	method to get the field or column value ranges (choices). A range program is used only when the Input	SCSBuyerDeskForm
form object field, generic create form	Type setting is combobox, radiobutton, or checkbox for forms, or combobox or popup for tables.	TMCPackagesForm
field, configurable		ENCPartForm
search form field, table object columns,	If the choices need to be presented on a page in a popup window, for example in a chooser, use the	AEFUtilForm
structure browser	RangeHref parameter instead.	
	The corresponding method which runs to get the values of the column should not have any HTML code.	
	of the column should not have any name code.	
Read Only Checkbox	For a field defined with the Boolean data type, or as a string with Boolean range values, this setting shows a	true
	checkbox instead of the TRUE or FALSE text.	false (default)
form objects	In edit mode, the user can check/clear the checkbox	
	unless the Editable=false setting is specified for the	
	field.	
Registered Suite	The application the UI component belongs to. The system looks for files related to the component in the	The value must be set without any spaces, for example, EngineeringCentral or Framework. The
	registered directory for that application, which is	value must be set to the suite name as defined in
	specified in emxSystem.properties.	the key eServiceSuites.DisplayedSuites within emxSystem.properties. If the suite name starts
	Based on the application name, the system passes the	with "eServiceSuite" then this prefix can be skipped
	following parameters in the href URL:	and assign the remaining text to the setting. For example, if the suite name in
	suiteKey	example, if the suite name in emxSystem.properties is
manu objects for ann	SuiteDirectory	"eServiceSuite EngineeringCentral ", then the word " EngineeringCentral ", can be assigned as
menu objects for app category menus and	StringResourceFileId This patting is provided for all decreased IV accounts.	"Registered Suite".
Actions submenus	This setting is required for all dynamic UI components.	In the href URL that is called when the item is
command objects for		clicked, the system passes a parameter called
menu links and tools		suiteKey and includes the property name that maps to the value specified for the setting.
menu objects for navigation trees		If the Column Type is file, this value must be
table object columns		Components.
form objects		For subscription commands, use Components.
,		
		I .

menu objects for		-
cormand objects for toolbar items and	Description	Accepted Values/Examples
PowerView Rebasionshipe browser	Optional setting that defines a comma-separated list of relationship select expressions to get the file lists	from [<relationship_referencedocument>].to.id,</relationship_referencedocument>
table object columns	checked into or connected to the Type object.	[<relationship_referencedocument>].from.id,,</relationship_referencedocument>
Remove Range Blank form object fields configurable search form fields	Used when the input type is set to combobox to ensure that the field contains a value and is not left blank. If set to True, this setting removes the blank from the combo box list. If a default is not specified, the first value in the list is shown by default.	true false (default)
Required	Use to indicate the value for this field is required. This	trueWhen completing the form, the user must
form object field genericcreate form object field	setting is applicable for editable fields displayed on the Editable mode form.	enter a value for the field. The field label appears in red italic text. If the user does not enter a value and clicks Done, a JavaScript message appears that prompts the user to enter a value. false (default)When completing the Edit form, the user can leave this field blank.
Revision Filter	Enables or disables the display of the revision filter	Enable
tree command objects	button.	Disable (default)
RMB Menu	Specifies the name of the right-click menu to associate with the component.	<admin menu="" name=""></admin>
table objects	For a type-specific menu, such as type_Part, defines the type-specific right-click menu for that type.	
toolbar meu objects	For a table column, specifies the right-click menu for that specific column.	
Root Label	Determines the label for the root node(s). You can use static text, such as Search Results, or a string resource id. When using a string resource id, you can use any valid MQL expression, such as:	Search Results emxFramework.Common.RootLabel
structure browser freeze-pane column	emxFramework.Common.RootL abel= \$ <type>\$<name>:Root</name></type>	
·	If the expression does not apply to the root object (such as an attribute not associated with that object), the expression is ignored and the default label is used.	
	If this setting is configured for a column not in the freeze pane, it is ignored.	
Row Grouping structure browser column	Enables or disables the column from being selected for row grouping. By default, all columns are enabled for grouping	true (default)column can be used for grouping rows
setting	except file columns (Column Type = Filesetting) and hard-coded icon columns.	falsecolumn can not be used for grouping roles
Row Grouping Range Function	Method in the JPO defined by the Row Grouping Range Program setting. The page will be grouped by the pre- defined row categories even if no rows in the structure	
structure browser column setting	browser have that value.	
Row Number	If the column is defined with a Group Name setting, this setting defines whether this column displays in the first	1 (default) 2
	or second row of the group. Only 2 rows are permitted	
structure browser	for a group. Used for merging cells as defined in Merged Cells.	
Row Select	Used only for links on table pages. Specifies whether the JSP specified for the href expects one, at least one, or no rows in the table (Middle Frame) to be selected. If the Row Select setting is set to "single" or "multi", the setting Submit must be set to "true" in order to get the details of the selected item(s) from the table. If the setting is not specified, it is assumed to be none.	single-Appropriate only for links that appear on table pages that have radio buttons or check boxes for each row. The JSP specified for the href expects exactly one row in the table (middle frame) to be selected. If more than one item is selected, a JavaScript alert message is displayed. The default message is set to the value of the following key in emxFrameworkStringResource.properties: emxFramework.Common.PleaseSelectOneItemOnly.
	A JavaScript alert message is displayed on error	

Setting command objects for toolbar items	conditions when the onClick event occurs. The error conditions are explained in the column to the right. Description of the setting must be set to multi and the Submit setting must be set to true.	Item Only". If no item is selected, then the user will see the following message: "Please select an Item". This message contexponds to this key value in the emxFrameworkStringResource.properties file: emxFramework.Common.PleaseSelectitem	
		multi-Appropriate only for links that appear on table pages that have check boxes or radio buttons for each row. The JSP specified for the href expects at least one row in the table (middle frame) to be checked. If no item is selected, then the user will see the following message: "Please select an Item". This message corresponds to the following key value in the emxFrameworkStringResource.properties file: emxFramework.Common.PleaseSelectitem none (default)-The JSP specified for the href expects no row in the table to be selected. If a row is selected, the JSP does not use it.	
Row Span	If this column is defined with a Group Name setting, defines how many rows each cell in this column will span. If set to 1, no spanning is done. If set to 2, the column value spans 2 rows. You cannot span more than	1 2 (default)	
structure browser	2 rows. Used for merging cells as defined in Merged Cells.		
Rows	Used when the input type is set to textarea. This setting	5	
form object field	limits the height of the textarea on the form and specifies the number of visible text lines. If not	10 s	
configurable search form	specified, it uses the HTML default, which is 5.	20	
Section Level	Used in conjunction with the Field Type: Section Header	Two heading levels are available:	
form object field	setting to define the level of heading.	1 (default)Font for heading label is large and a horizontal line is included above the label.	
generic create form field		2Font for heading label is smaller and the heading	
configurable search form		is in the same gray rectangle as standard fields.	
Selectable in Preferences	Only for commands in app category menus and submenus. Controls whether the link is available as a preferred Home page. If not set, the system assumes	True False	
command objects for menu links and tools	true and the command is listed as a Home page preference. Commands that call pages to display in a popup window, such as an object search command, should not be available as a Home page preference.		
Show Alternate Icon	If the column value to be displayed with the icon is	true	
table object column	different from the current row's object icon, set this setting to true. ITo get the right alternate icon, the Alternate Type expression setting must be defined with	false	
structure browser	the expression to obtain the object type.		
Show Alternate Icon	If the field value needs to be displayed with an icon that	true false (default)	
	is different from the current object type icon, set this		
form object field	setting to true. To get the right alternate icon, the Alternate Type expression setting must be defined with the expression to obtain the object type.		
Show Clear Button	Adds a Clear hyperlink next to the field. This setting	True	
form object field	only applies to textarea/textbox input type fields. When the Clear link is clicked, it clears the content of the	False	
generic create form	textbox/textarea input type field.		
configurable search form			
structure browser			

ÇΟ	lцп	nns

Show Type Icon UI Component	Pseribitive, the field or column value is displayed along with the object type icon as defined in the	false (default)		
table object column				
structure browser				
generic create form field	emxFramework.smallIcon property in emxSystem.properties. The icon is displayed to the left of the field or column data.			
	If no property is defined for the type's icon, the system looks for a property defined for the parent type, then grandparent type and so on. If no property is defined for any type in the hierarchy, the system uses the default icon specified in the emxFramework.smallIcon.defaultType property.			
Slidein Width	When the Target Location setting is set to slidein, this setting defines the width in pixels of the slidein window.	wide 500		
	If you do not specify this setting or you provide a non- numerical value, the default width (350) is used. The minimum value is 350. If you provide a smaller value, 350 is used. The maximum value is 900. If you provide	800		
web forms	a larger value, 900 is used. You can also set the value to wide to use the configured width as defined by the emxFramework.widerslideIn.size parameter in			
	emxSystem.properties.			
Sort Direction	Used only for fields of type combobox and listbox.	ascending (default)Sort a to z or 0 to n.		
table column objects, structure browser, form object fields	The direction to sort the option list. descendingSort z to a or n to 0. noneThe option list is not sorted.			
Sort Program	Specifies the JPO program name that contains a custom sorting algorithm. This setting is used only when the	Name of a JPO added as a program in the database such as:		
table object column	column parameter sorttype is assigned to "other".	FindNumberSort CustomSort		
Sort Range Values	Enables or disables the sorting of range values in combobox or listbox controls. When enabled, the list is sorted based on the datatype and using the direction defined by the Sort Direction setting. When disabled, no sorting is done on the list.	enable (default disable		
	In a drop-down, range values populated based on an attribute expression will be sorted based on the attribute's datatype. Range values populated using the Range Program and Range Function settings will be sorted alphanumerically.			
	If the Range Program or Range Function returns numeric or date values, the alphanumeric sort will not be appropriate. The program or function should sort the values in the required order, and this setting should be disabled.			
	This setting does not apply to fields or columns configured for attributes associated with a dimension.			
table object column,	Dimension ranges are always sorted as alphanumeric in ascending order.			
form field, structure broswer, configurable search form field	This setting cannot be used in custom JSPs that use the editOptionList taglib. For this specific situation, you can use the sortType attribute for that tag.			
Sort Type	Determines how the column is sorted.	date		
	The MQL sorttype subclause must also be included.	integer		
	Use on its own to sort numeric columns (sorttype =	real		
table object column	numeric)	AlphaNumericLargerconsider all numeric values a		

Setting	Use in conjunction with the Sort Type setting. Two examples:	AlphaNumericSmallerconsider all numeric values as smaller than the alphanumeric values		
UI Component	Description (sorttype = other AND Sort Type = integer) (sorttype = other AND Sort Type = real)	Accepted Values/Examples		
Sortable	Controls whether users can sort the table based on data	true (default)		
table object column	in the table column. If a column is sortable, users can	false		
structure browser	click the column heading to sort the table based on that column.			
sortColumnName	Used only for fields defined with Field Type=emxTable. Specifies the column by which the table should be	Name of column in the table specified in the table=TABLE_NAME setting.		
form object field	sorted when the page is first loaded. If no column is specified, the rows are listed in the order they are retrieved from the database.			
sortDirection	Used only for fields defined with Field Type=emxTable.	ascending (default)Sort a to z or 0 to n.		
form object field	The direction to sort the rows by.	descendingSort z to a or n to 0.		
Structure Function	JPO method name to be used for getting the object list.	The name of a method in the JPO specified in the Structure Program setting, such as: getWorkspaceFolders		
command objects for structure trees				
		getEBOMs		
Structure Inquiry	Inquiry administrative object name that gets the object list to display within the structure. This is an alternative	The name of an inquiry administrative object:		
command objects for structure trees	to the JPO approach and the JPO approach takes	SCSWspFolderStructure		
structure trees	precedence. This setting is not implemented.	ENCEBOMList		
Structure Menu	Specifies the menu administrative object that defines a	The name of a menu administrative object.		
menu object for navigation tree	structure tree for the object type.			
Structure Program	JPO program that contains the method to be used for	The name of a JPO program added to the database.		
	getting the object list to display within the structure.	SCSWorkspaceStructure ENCBOMStructure		
command objects for structure trees	The method is specified in the Structure Function setting.			
Style Column	Customizes the sytle for a column. The value must be a class defined in the dsecUITypeCustom.css. For the example style, the definition in the css file could be:	ColumnBackGroundColor		
	ColumnBackGroundColor {			
column in a structure browser	background-color: rgb(252,186, 186);			
	To define alignment, use one of these values: • left-align • center-align • right-align			
	For numeric fields, the default is left-align.			
Style Function	The method in the Style Program JPO that defines the style per cell in the column.	The name of a function in the Style Program JPO, such as: getStyleInfo		
column is a structure				
column in a structure browser				
Style Program	The JPO that contains methods to defines the style per	The name of a JPO, such as:		
column in a structure browser	cell in the column.	AEFUtilStyleJPO		
Submit	Specifies whether the system should send the object ID(s) (and relationship ID, if applicable) for the current page to the JSP specified in the href parameter. For form pages, the submitted data is the object ID for the business object the page is about. For table pages, the	trueSubmits the IDs to the URL specified in the href parameter. Should be used for actions that depend on selected table rows.		

command objects for toolbar items, including subscription	submitted data is the ID for each selected item in the table, which can include object and relationships. In the IDs are sent using the relBusIdList parameter.	Accepted Values/Examples falseThe URL specified in the href parameter is directly called from the toolbar item and no IDs			
	If the setting is not specified, it is assumed to be false.	from the current page are used. Use this value for links that do not require the business object IDs, such links for creating a new object.			
		For toolbar commands in a structure browser, should be true so that the selected items in the structure are posted to the processing page.			
table	Specifies the name of a table administrative object to	Name of table administrative object. For example:			
form object field	embed in the form. Used only for fields defined with Field Type=emxTable.	table=SCSBuyerDesk			
Torrir object field		table=ENCParts			
Target Location	Controls where the page specified in the href parameter appears.	contentThe page replaces the tree frame.			
	For table columns, this value can be set to any valid	mainframeThe page appears in the main content frame, to the right of the tree frame and tab			
command objects for menu and toolbar	frame name, which is available to the table body frame.	frames, replacing the page that is already there (not used for table columns or structure browser).			
links and tools	For toolbar commands, must be listHidden or popup.	popupPage appears in new window. The window			
table object columns	To specify a tab in a PowerView window, use the administrative command name that configures the tab	modality is set using the Popup Modal setting.			
command objects for toolbar items	in the PowerView page. If the specified command name is not defined within the current PowerView, the popup	_topPage replaces the entire body of the browser window.			
subscription commands	value is used.	topFrameThe page replaces the banner frame. (not used for table columns or structure browser)			
structure browser		hiddenFrameThe frame called hiddenFrame is part of the top level Navigation window frameset and can be used to submit the Table frame and carry out background processing. This frame is not available for popup windows though so listHidden is a better frame to use.			
		listHiddenA hidden frame within the table frameset. Use this frame for Target Location for any processing in the context of a table.			
		<command name=""/> The name of a command configured as the target tab in a PowerView page.			
Target Location	Controls where the page specified in the href parameter appears when a user clicks the hyperlinked data. This value can be set to any valid frame name that is	popupPage appears in a new window. The window modality can be set with the Popup Modal setting. Popup is the default value and is used if the setting is not included or if the named frame cannot be			
form object field	available to the form body frame.	found.			
configurable search form		contentThe page replaces the content frame.			
		mainFramePage appears in the frame that includes the content and menu frames.			
		_topPage replaces the entire body of the browser window.			
Target Location	This must be assigned to "searchContent."	searchContent			
Search JSP page					
Tip Page	Specifies whether the target page should include the	Name of a custom html or JSP page, including any			
	Tip Page tool and the URL that should be called when the tool is clicked. In the href URL called when the UI component is clicked, the system passes a parameter called TipPage and includes the URL specified for this setting.	path. The starting point for the directory reference is the content directory. For example, if you want to call an html file in ematrix/doc/customcentral and the content directory is ematrix/customcentral, you would add this parameter to the table.jsp:			
menu objects for navigation trees	If this setting is not included, the target page does not display the Tip Page tool.	TipPage=/doc/customcentral/tippage.html			
command objects for menu links and tools, tree commands, and toolbar items					
table object columns					
form object field					
Tree Scope ID	Passes the current tree's objectId to all its categories, to subtrees inserted into the tree, and to categories in the subtrees, to the nth level, in the parameter name	The name of the parameter you want to use to pass the object ID. For example:			

Setting	specified as the value for this setting. This setting is valid only for tree menu objects and not for tree	workspaceId Preciently Values/Examples		
UI Component	_			
menu objects for tree nodes, menu objects for navigation trees	For example, suppose you want to pass the object ID for the current Bookmark Workspace to all tabs and subtrees in the Bookmark Workspace tree. You want to pass the object ID using a parameter called workspaceId. To do this, you would add the Tree Scope ID setting to the menu administrative object for Bookmark Workspace trees (which is called type_Project due to administrative object renaming) and enter "workspaceId" as the value. The parameter and value "workspace Id=OBJECTID OF THE WORKSPACE will be available to all the categories and subtrees of the current Bookmark Workspace to the nth level until another Bookmark Workspace object gets inserted or until any explicit URL parameter with the same name "workspaceId" is passed to the tree.	partId You can also pass specific parameters from the tree menu object to its categories using the AppendParameter parameter for the emxTree.jsp.		
Type Ahead Mapping	When Type Ahead is configured on the field/column (by	NAME		
form object field, table column	setting the RangeHref to emxFullSearch.jsp or using a predefined Type Ahead Chooser), this setting maps that field to the corresponding indexed field in config.xml. See About Automatic Type Ahead.	LASTNAME,FIRSTNAME,USERNAME		
Type Ahead Validate	When Type Ahead is configured on the field/column, this	true		
form object field, table column	setting determines if the application should restrict the user to selecting one of the suggested values (if true), or if the user can enter any data in the field without BPS validating that data (if false).			
Type Icon Function	Specifies the function in the JPO specified in the Type	Function Name		
tree menu objects web forms tables structure browsers	Icon Program setting that retrieves an icon to show in addition to the icon defined by the emxFramework.smallIcon.type system property.			
Type Icon Program	Defines the program that contains the function specified	JPO Name		
tree menu objects	using the Type Icon Function setting.			
web forms				
tables				
structure browsers				
TypeAhead	Enables type ahead. For mass update in a structure	true		
	browser, default is true.	false		
configurable search form field, structure browser mass update		Tuise		
TypeAhead Program	Name of the JPO called to retrieve a list of possible			
configurable search form field, structure browser mass update	values.			
TypeAhead Function	The name of the JPO method.			
configurable search form field, structure browser mass update				
TypeAhead Character Count	Overrides the emxFramework.TypeAhead.RunProgram.CharacterCount	2 (default) 5		
configurable search form field	system property.			
TypeAhead Saved Values Limit	Overrides the emxFramework.TypeAhead.SavedValuesLimit system	10 (default)		

			_		
forr	n fie	eld			
_Set	ting				

Required for columns whose values are measurements that can be converted from English units to Metric units or vice versa.	Quotations, the following select clause returns the supplier's unit of measure format.			
The value can be a select clause that returns the value for the Unit of Measure attribute for a specific object or relationship or the actual value. The unit of measure to convert form should be the unit of measure in which the user entered the data (the As Entered unit of measure).	to[Supplier Line Item].attribute[Unit of Measure]			
This setting should only be used with Sourcing Central.				
Specifies a method name in the JPO given in the Update Program setting.	The name of a function in the Update Program JPO, such as:			
Generic Create Form: This setting can not be used with the required fields: Type, Name, Policy, Vault, Owner.	setAssignedBuyerDesk setPackage Access setPartClassification			
Specifies a JPO that contains a method to set the field	The name of a JPO, such as:			
 value when the field is displayed on an Edit mode form and when the user clicks Done. This program is used only when the Field Type setting is program or programHTMLOutput. 	SCSBuyerDeskForm TMCPackagesForm ENCPartForm			
Using an update program is recommended only when	AEFUtilForm			
Generic Create Form: This setting can not be used with the required fields: Type, Name, Policy, Vault, Owner.				
Comma-separated list of arguments to be passed to the JPO specified by the Update Program setting.	Relationship=relationship_EBOM,ConnectFrom=true			
Specifies the method to be invoked for validating any	The name of a method, such as:			
cell.	checkUniqueName			
This setting is used to validate any column or field value	Basic or RestrictedThe column values are			
with any specific characters defined in emxSystem.properties.	validated against the value of emxFramework.Javascript.BadChars. NameThe column values are validated against the value of emxFramework.Javascript.NameBadChars			
Used for grouping fields vertically in create web forms.	The name of the vertical group.			
The fields with the same Vertical Group Name value will be are considered a group.				
Comma-separated list of attributes that will not be included in the webform when opened in View mode when a field on the webform has been defined as Field	For example: attribute_Cost			
	Required for columns whose values are measurements that can be converted from English units to Metric units or vice versa. The value can be a select clause that returns the value for the Unit of Measure attribute for a specific object or relationship or the actual value. The unit of measure to convert form should be the unit of measure in which the user entered the data (the As Entered unit of measure). This setting should only be used with Sourcing Central. Specifies a method name in the JPO given in the Update Program setting. Generic Create Form: This setting can not be used with the required fields: Type, Name, Policy, Vault, Owner. Specifies a JPO that contains a method to set the field value when the field is displayed on an Edit mode form and when the user clicks Done. This program is used only when the Field Type setting is program or programHTMLOutput. Using an update program is recommended only when the Field Type is not attribute or basic. Generic Create Form: This setting can not be used with the required fields: Type, Name, Policy, Vault, Owner. Comma-separated list of arguments to be passed to the JPO specified by the Update Program setting. Specifies the method to be invoked for validating any cell. This setting is used to validate any column or field value with any specific characters defined in emxSystem.properties. Used for grouping fields vertically in create web forms. The fields with the same Vertical Group Name value will be are considered a group.			

Width	Number of pixels to define the column width.	Column width in pixels:
structure browser	When this setting is not defined, by default the width is calculated based on the header text length, so that the header text is not truncated.	150
width	Specifies the width of the filter toolbar control in pixels.	100
toolbar custom filter	Use this setting if you need to display many controls in a small area.	