



BMBridge Lite — User Manual

Complete reference for BMBridge Lite

BMBridge Lite 1.0 · SDE-Software (SDES.DEV)

Used at your own risk. No support is provided by SDES.DEV, Bookmap, Tom B, the Bookmap Discord channels, or the Bookmap support team. See the full disclaimer at the end of this document.

Version: Lite 1.0 **Publisher:** SDE-Software (SDES.DEV) **Purpose:** Serve user-entered custom price notes to Bookmap Cloud Notes over local HTTP.

Contents

- 1 Overview
 - 2 System Requirements
 - 3 Installation and First Launch
 - 4 Interface Reference
 - 5 Feeds
 - 6 Custom Notes
 - 7 Color Templates
 - 8 Connecting Bookmap
 - 9 Settings Reference
 - 10 System Tray Behavior
 - 11 Data & Settings File
 - 12 Troubleshooting
 - 13 Known Issues
 - 14 Limitations
 - 15 Disclaimer
-

1. Overview

BMBridge Lite is a lightweight Windows application that allows the user to author custom price notes, render them to CSV files in Bookmap's Cloud Notes format, and serve those CSV files on **127.0.0.1** over HTTP so that Bookmap can poll and render them as chart annotations.

The program does not source, import, or redistribute market data. All note content is entered manually by the user.

2. System Requirements

- Windows 10 or 11
 - For source execution: Python 3.10+, PyQt6, pandas
 - A running Bookmap installation with Cloud Notes support
 - A local firewall that permits loopback (**127.0.0.1**) connections
-

3. Installation and First Launch

Installation

- **Compiled EXE:** place **BMBridge_Lite.exe** in any folder with write access. The settings file and all CSV outputs are created next to the executable.
- **Source:** run **python BMBridge_Lite.py** from the folder containing the script.

Windows SmartScreen and Antivirus

The EXE distribution is not code-signed. On first launch Windows SmartScreen will display a **"Windows protected your PC"** dialog. Click **More info** → **Run anyway** to proceed. The warning does not reappear on subsequent launches on the same machine. Some third-party antivirus products may also prompt once or require an exception for **BMBridge_Lite.exe**. This is a known consequence of shipping unsigned Python-compiled executables and is unrelated to program behavior.

First Launch

On first launch, an **About / Disclaimer** window appears. The user must click **I Understand & Accept** to proceed. Clicking **Decline & Exit** closes the program. The acceptance flag is persisted in **bridge_lite_settings.json**; the disclaimer does not reappear on subsequent launches.

4. Interface Reference

Left Panel (fixed, 260–360 px)

Element	Purpose
Status light	IDLE (red) when servers are stopped, LIVE (green) when running
Global Bookmap Symbol	Default symbol applied to all feeds without an override
START / STOP SERVERS	Toggles all HTTP servers and the sync loop
Last Sync	Timestamp of the most recent CSV write pass
Active Feeds	Summary list of configured feeds (name + symbol)
Add Feed	Creates a new feed tab (maximum of two)
Sync Interval (sec)	Frequency of CSV write passes. Minimum 0.5
Minimize to tray on close	If checked, closing the window hides to system tray; servers continue running
Activity Log	Timestamped log of events, errors, and warnings

Right Panel (Tabbed)

Each tab is a single feed and contains:

- **Header:** Broadcasting checkbox, Name field + rename button, Port, server LED, URL (read-only) + Copy URL, Symbol Override
- **Entry Form:** Load/Save Template, Description, Price, Align, Draw Line, Text Color, BG Color, Preview, ADD NEW / UPDATE
- **Sort Toolbar:** Name ▲ / Name ▼ / Price ▲ / Price ▼
- **Note Cards:** one card per note, with enable, SEL, color badge, line toggle, reorder, clone, delete

5. Feeds

Creating a Feed

- Click **Add Feed** in the left panel. A new tab is created with a default name (**Feed N**) and port (**8000 + index**).
- Maximum of two feeds.

Configuring a Feed

- **Name:** edit the Name field and press Enter or click the green check. Name is used in the CSV filename.
- **Port:** edit the Port field. Default ports are **8000** and **8001**. If the port is in use by another process, the server for that feed will fail to start; check the Activity Log.
- **Symbol Override:** optional per-feed Bookmap symbol. If blank, the Global Bookmap Symbol is used.
- **Broadcasting:** if unchecked, the feed's HTTP server is not started on the next START SERVERS. The CSV file is still written.

Removing a Feed

There is no in-app control to remove a feed. To remove a feed, close the program and remove the feed's entries from **bridge_lite_settings.json** by hand.

6. Custom Notes

Adding a Note

- 1 Select the target feed tab.
- 2 Fill in **Description** and **Price**.
- 3 Select **Align** (Left / Center / Right).
- 4 Toggle **Draw Line** for a horizontal price line on the chart.

- 5 Pick **Text Color** and **BG Color**.
- 6 Click **ADD NEW**.

Editing a Note

- Click **SEL** on the note card. The entry form loads with that note's values and the **UPDATE** button becomes enabled.
- Modify any field and click **UPDATE** to save.
- **ADD NEW** is disabled while a note is selected. Click **SEL** again to deselect.

Enabling / Disabling a Note

Uncheck the enable checkbox on the note card to omit it from the CSV output. The note is preserved in the feed and can be re-enabled at any time.

Reordering, Cloning, Deleting

- ▲ / ▼ — move the note up or down within the feed.
- ■ — insert a copy of the note directly below the original. The clone's description is suffixed with **(copy)**.
- ■ — permanently delete the note. There is no undo.

Sorting

The **Sort** toolbar sorts the entire feed by Description or Price, ascending or descending. Sorting is a destructive operation on the note order; there is no undo.

7. Color Templates

Saving

- Click **Save Template**. Enter a template name.
- Choose **Colors only** or **Colors + Text**. "Colors + Text" also saves the current Description field contents.

Loading

- Click **Load Template** to open the template selector.
- Each template is shown as a colored button preview. Click to apply.
- Use the trash icon to delete, or the arrows to reorder.

Templates are stored globally and are available to all feeds.

8. Connecting Bookmap

- 1 Start BMBridge Lite servers.
- 2 Copy the feed's URL using the **Copy URL** button, for example **http://127.0.0.1:8000/Feed_1.csv**.
- 3 In Bookmap, open the Cloud Notes / Custom Notes configuration panel for your version.
- 4 Paste the URL as a new Cloud Notes source.
- 5 Configure the Bookmap-side poll interval.
- 6 Save. The notes render as chart annotations.

Authoritative reference: <https://bookmap.com/knowledgebase/docs/KB-Appendices-All-CustomNotes>

CSV Output Format

The CSV served to Bookmap contains these columns in order:

Description, Symbol, Price Level, Note, Foreground Color, Background Color, Text Alignment, Draw Note Price Horizontal Line

Only enabled notes are written. The sync loop rewrites the CSV at the interval set by **Sync Interval (sec)**.

9. Settings Reference

Setting	Location	Description
Global Bookmap Symbol	Left panel	Default symbol for all feeds
Sync Interval (sec)	Left panel	CSV rewrite frequency, minimum 0.5
Minimize to tray on close	Left panel	If checked, close button hides to tray
Feed Name	Feed header	Drives CSV filename and URL
Port	Feed header	TCP port for the feed's HTTP server
Symbol Override	Feed header	Per-feed symbol; blank uses the global value
Broadcasting	Feed header	Controls whether the feed's server starts

All settings persist to **bridge_lite_settings.json** on change.

10. System Tray Behavior

- A blue **BM** tray icon is created on launch (if the system tray is available).
 - If **Minimize to tray on close** is enabled, closing the main window hides the app to the tray and servers continue running in the background.
 - Double-click the tray icon, or right-click and select **Show**, to restore the window.
 - Right-click and select **Quit** to stop servers, save settings, and exit.
-

11. Data & Settings File

- **Settings file:** `bridge_lite_settings.json` in the same folder as the executable (or script).
- **CSV output files:** one per feed, named `<Feed_Name>.csv`, in the same folder.
- The settings file is written atomically (`.tmp` + rename) to reduce corruption risk.
- Back up `bridge_lite_settings.json` before making manual edits.

Settings File Schema (summary)

```
global_symbol      : str
tab_keys           : list[str]  # UUIDs
sync_interval      : float
presets            : dict       # color templates
close_to_tray      : bool
disclaimer_accepted : bool
manual_data_<key>  : list[dict] # one entry per feed
tab_name_<key>     : str
<key>_port         : str
<key>_srv_enabled  : bool
feed_symbol_<key> : str
```

12. Troubleshooting

Symptom	Probable Cause
Server fails to start for a feed	Port in use by another program; change the port
Bookmap does not render the notes	Incorrect URL in Bookmap; Bookmap polling disabled; firewall blocking loopback
CSV file locked warning in the log	Another program (often Excel) has the CSV open; close it
URL shows old filename after rename	Retype the port to refresh; or restart the program
Notes show wrong price on chart	Verify price entry; Bookmap caching — force refresh in Bookmap
Program does not appear to exit	It may be minimized to tray; right-click tray icon and select Quit

The Activity Log on the left panel is the primary diagnostic tool. All errors, warnings, and status events are logged there.

13. Known Issues

The following minor issues are documented and are not planned for fix in Lite 1.0:

- **Broadcasting checkbox is inert while servers are running.** Toggling it only takes effect on the next STOP → START cycle. Stop and restart servers to apply.
- **Price-sort does not handle scientific notation.** Prices like **1e5** sort as **0.0**. Enter prices in plain decimal form.
- **"Save Template" with an empty name silently does nothing.** The dialog stays open with no feedback. Enter a name and click Save again.
- **No in-app feed deletion.** To remove a feed, close the program and edit **bridge_lite_settings.json** to remove the feed's entries.
- **No undo for sort or delete.** These operations are destructive. Back up **bridge_lite_settings.json** before large reorganizations.

14. Limitations

- Maximum of two concurrent feeds.
- Notes are user-entered only. There is no CSV import, no data source integration, no automated level generation, and no hit tracking.
- The HTTP server binds to **127.0.0.1** only. Remote access is not supported and not recommended.
- There is no in-app feed deletion. Remove entries from **bridge_lite_settings.json** manually if required.
- Sort and delete operations have no undo.

- The program is Windows-first; other platforms are not tested.
-

15. Disclaimer

BMBridge Lite is an independent, third-party software application developed by SDE-Software (SDES.DEV). It is not affiliated with, endorsed by, sponsored by, or in any way connected to Bookmap, or any of its parent companies, subsidiaries, licensors, or affiliated entities. Bookmap™ is a trademark of Bookmap Ltd. and is referenced here solely to describe software interoperability.

BMBridge Lite is provided **as-is** and **used entirely at the user's own risk**. The developer accepts no liability for incorrect note content, file corruption, server failures, Bookmap rendering behavior, or any trading decisions made based on notes displayed by this application. All notes are user-entered and informational only. This software does not provide financial advice.

No support, walkthroughs, troubleshooting, or individual assistance is provided by SDES.DEV, Bookmap, Tom B, the Bookmap Discord channels, or the Bookmap support team for this program. Users are responsible for reading this user manual, the quick-start guide, and the official Bookmap Cloud Notes documentation at <https://bookmap.com/knowledgebase/docs/KB-Appendices-All-CustomNotes>. Bugs and glitches will be addressed as they are identified; no service-level agreement is offered.