Test Charter: eBay.com Exploratory Testing

Areas tested

#	Area	Description	Expected	Actual
1	Login	Sign in with a valid account from the home page	The user is signed in, and the header shows the account name	The user is signed in, and the header shows the account name
2	Sign-up	Create a new account and continue past the details form	The human-verification challenge appears and its instruction is fully readable	The eBay logo overlaps the challenge instruction and covers its first words. The logo looks doubled (BUG-001)
3	Home page	Open https://www.ebay.com/	The home page loads with the search box visible	It loads, but eBay intermittently shows "Error Page | eBay" / "Something went wrong on our end"
4	Search	Search for mazda mx-5	The results page opens with relevant listings and a result count	The results page opens and the count shows (for example 7,200+ and 11,000+ results in different runs)
5	Search results	Check the first result in the list	The first result is a real listing that opens an item page	The first /itm/ link is a placeholder (/itm/123456) that opens a "Discover | eBay" page with no title or price
6	Opening a result	Click the first result	The click opens its item page	The click on the image link is blocked because other elements cover it, and the link opens in a new tab
7	Item details page	Open a real listing	The item title and price are displayed	The item title and price are displayed
8	Image search (eBay Motors)	Click the camera icon on All Categories > eBay Motors	The panel opens as a centred modal with a dimmed backdrop and a readable title	No dialog box or backdrop. The panel title overlaps the "eBay Motors" heading, the "Paste an image link" field

				covers a category link, and a stray blue circle appears (BUG-002)
9	Image search (Seller Center)	Click the camera icon on the Seller Center page	Same modal behaviour	Works as expected: a white dialog, a dimmed backdrop, nothing overlapping
10	Watchlist	Add an item from the home page to the watchlist, go to another page, then return	The heart icon stays active until the user removes the item	The heart icon is inactive after returning (BUG-03) [confirm whether the item is still in My eBay > Watchlist]
11	Category menu: "Explore now"	Hover over a category and click "Explore now"	The page for that category opens with its products	Nothing happens for [categories tried]. On Sports, only a banner image shows, and no category page opens (BUG-04)
12	Cart	Add an item, change the quantity, remove it	Totals update and the cart is kept after refresh	Totals update and the cart is kept after refresh
13	Filters and sorting	Apply filters and sort by lowest price	Results are filtered and ordered correctly, and the count updates	Results are filtered and ordered correctly, and the count updates
14	Search by category	Select “Art” in the “All Categories” dropdown next to the search box and click Search	The Art category page opens with Art listings	Works as expected: the Art page opens (breadcrumb eBay > Collectibles & Art > Art) with a “Bestselling” section, listings and an Art subcategory menu on the left

BUG-01: eBay logo overlaps the human-verification challenge prompt, making its instruction unreadable

Preconditions:
1- User mustn't have an account and proceeds to create one.

Steps to reproduce:
1-Go to https://www.ebay.com/ and click on sign up.
2-Fill out user information.
3-Click continue.


Expected result:
-The challenge instruction is fully readable (here, "click on things you can use underwater"). The page header and logo stay behind the popup, or don't overlap it.

Actual result:
- The eBay logo in the page header is drawn on top of the teal instruction banner and covers the first words of the sentence. Only "...on things you can use underwater" is readable.
- The logo also looks doubled or ghosted (it appears as two overlapping "eBay" marks).

Severity : High .

Priority : 2.

Attachment:



BUG-02: Image-search panel overlaps any of eBay category page instead of opening as a modal, making the panel title and category links unreadable .

Preconditions: Select any category from the home page.

Steps to reproduce:
1- Go to https://www.ebay.com/ and click on “Shop by category”, then select any Category .
2- Click the camera icon in the search bar (“Search with an image”).


Expected result:
-The panel opens as a modal dialog, as it does on other pages (for example Seller Center): a white dialog centred on the page, the background dimmed, a close (X) button, and a readable title “Can’t find the words? Search with an image”. The page content behind it can’t be read through it or clicked.

Actual result:
- The panel opens with no dialog box and no dimmed backdrop. Its contents are drawn straight over the page.
- The panel title (“...words? Search with an image”) overlaps the Category heading, and both are partly unreadable.

Severity: Medium.

Priority: 3.

Attachment:



BUG-03: When putting any item from home page in watchlist and then redirecting to any page and go back to it the heart sign (watchlist) button isn't activated for it .

Preconditions: Must be signed in to be able to add to watchlist .

Steps to reproduce:

1-Log into an account.
2-Add any item from the home page into watchlist.
3-Go to any other page and return to the home page .

Expected Result:
-Icon of the watchlist product should be enabled at any case unless user removes it.

Actual Results:
- Icon of the watchlist product is disabled after user switches to another page and returns.

Severity: Medium.

Priority: 3.

Attachment:

https://drive.google.com/file/d/1WkPoQaEAekCJ6mErTrYEi0di3lyzPmDS/view?usp=sharing

BUG-04: When hoovering over any category from the ones above and choosing to explore now, nothing happens and when selecting explore now in the sports category, it displays a photo and nothing also happens.

Steps to reproduce:

1-Open https://www.ebay.com/ and hoover over any category from the above and choose to explore now .

Expected Results:

-After Choosing Explore more for a certain category the website should return all the products related to that category.

Actual Results:

- When hoovering over any category from the ones above and choosing to explore now, nothing happens and when selecting explore now in the sports category, it displays a photo and nothing also happens.

Severity: Medium.

Priority: 3.

Attachment:

https://drive.google.com/file/d/1ThvgQQyiQh2OjNbKI-4_Mk9eFEpzLaxm/view?usp=sharing

