

X-Panel 节点搭建完整教程

前言

关于如何"搭梯子"的教程,网上已经满天飞了。但很多教程要么是写给懂行的人看的,要么就是早就过时了。这篇教程的目标只有一个:让你跟着我的步骤,动动手指复制粘贴,就能成功拥有一个属于自己的、稳定又快速的私家通道。

准备工作

必需材料

- 一台 VPS 服务器
- 一个域名(可选,但强烈建议准备)

注意: 虽然不要域名也可以,但为了避免 HTTP 裸奔,建议大家准备域名并解析到 Cloudflare。

推荐面板

首选使用  X-Panel 面板进行搭建:

- 界面全部是中文
- 基于原项目的最大优化
- 持续更新完善

一、安装 X-Panel 面板

一键安装脚本

连接 VPS 后直接粘贴并按回车键即可。

```
1 | bash <(curl -Ls https://raw.githubusercontent.com/xeefei/x-panel/master/install.sh)
```

安装步骤

..

1. 连接 VPS

使用 Windows CMD 或其他 SSH 工具连接你的 VPS

```
Microsoft Windows [版本 10.0.19045.6332]
(c) Microsoft Corporation. 保留所有权利。

C:\Windows\system32\key-3ft root@VM-DESKTOP-001:~#
Welcome to Ubuntu 24.04 LTS (GNU/Linux 6.8.0-35-generic x86_64)

This system has been minimized by removing packages and content that are
not required on a system that users do not log into.

To restore this content, you can run the 'unminimize' command.

[REDACTED]

Welcome to DMIT.IO Cloud Infrastructure Service.

Last login: Fri Sep 12 00:59:28 2025 from [REDACTED]
root@DMIT-AK47:~#
root@DMIT-AK47:~# bash <(curl -Ls https://raw.githubusercontent.com/xeefei/3x-ui/master/install.sh)
```

2. 运行安装脚本

复制一键安装脚本,粘贴后按回车

```
Welcome to DMIT.IO Cloud Infrastructure Service.

Last login: Fri Sep 12 01:31:50 2019
root@DMIT-AK47:#
root@DMIT-AK47:~# bash <(curl -Ls https://raw.githubusercontent.com/xiefei/3x-ui/master/install.sh)
----->>>>目前服务器的操作系统为: ubuntu
----->>>>当前系统的架构为: amd64

/dev/fd/63: line 61: /usr/local/x-ui/x-ui: No such file or directory
----->>>当前服务器没有安装任何 x-ui 系列代理面板
----->>>>片刻之后脚本将会自动引导安装 (X-Panel面板)
----->>>> (X-Panel面板) 最新版为: v2.7.3

Hit:1 http://archive.ubuntu.com/ubuntu noble InRelease
Hit:2 http://archive.ubuntu.com/ubuntu noble-updates InRelease
Hit:3 http://security.ubuntu.com/ubuntu noble-security InRelease
Hit:4 http://archive.ubuntu.com/ubuntu noble-backports InRelease
0% [Working]
```

3. 选择安装路径

可以直接按 N 使用系统默认设置,也可以自定义

```
/usr/bin/x-ui-temp          100%[=====] 62.53K --. KB/s   in 0.002s
2025-09-12 09:35:38 (34.3 MB/s) - '/usr/bin/x-ui-temp' saved [64026/64026]
----->>>>>>>检查并保存安装目录
x-ui/
x-ui/x-ui
x-ui/bin/
x-ui/bin/geosite_IR.dat
x-ui/bin/README.md
x-ui/bin/LICENSE
x-ui/bin/geoip.dat
x-ui/bin/xray-linux-amd64
x-ui/bin/geoip_IR.dat
x-ui/bin/geoip_RU.dat
x-ui/bin/geosite.dat
x-ui/bin/geosite_RU.dat
x-ui/x-ui.sh
x-ui/x-ui.service
----->>>>>>>保存成功
安装/更新完成! 为了您的面板安全, 建议修改面板设置
想继续修改吗? 选择 "n" 以保留旧设置 [y/n]? --->请输入:
```

4. 设置密码

选择 Y 并自定义密码

```
----->>>>>>>检查并保存安装目录
x-ui/
x-ui/x-ui
x-ui/bin/
x-ui/bin/geosite_IR.dat
x-ui/bin/README.md
x-ui/bin/LICENSE
x-ui/bin/geoip.dat
x-ui/bin/xray-linux-amd64
x-ui/bin/geoip_IR.dat
x-ui/bin/geoip_RU.dat
x-ui/bin/geosite.dat
x-ui/bin/geosite_RU.dat
x-ui/x-ui.sh
x-ui/x-ui.service
----->>>>>>>保存成功
安装/更新完成! 为了您的面板安全, 建议修改面板设置
想继续修改吗? 选择 "n" 以保留旧设置 [y/n]? --->请输入: y
请设置您的用户名:
```

5. 设置面板端口

可以随机设置面板端口

----->>>>>>>> 检查并保存安装目录

```
x-ui/  
x-ui/x-ui  
x-ui/bin/  
x-ui/bin/geosite_IR.dat  
x-ui/bin/README.md  
x-ui/bin/LICENSE  
x-ui/bin/geoip.dat  
x-ui/bin/xray-linux-amd64  
x-ui/bin/geoip_IR.dat  
x-ui/bin/geoip_RU.dat  
x-ui/bin/geosite.dat  
x-ui/bin/geosite_RU.dat  
x-ui/x-ui.sh  
x-ui/x-ui.service  
----->>>>>>>>>>保存成功
```

完成(更新完成)：打了你的三

安装/更新完成：为了您的面板安全，建议修改面板设置。

```
是否继续安装? [y/n] ! --> y  
请设置您的用户名:  
您的用户名将是: [REDACTED]  
请设置您的密码:  
您的密码将是: [REDACTED]  
请设置面板端口: [REDACTED]
```

6. 完成安装

警告：未找到证书和密钥，面板不安全！

----->>>请按照下述方法设置「ssh转发」<<<-----

或者 ssh -L [::]:15208:127.0.0.1:520 root@[2]
40

2、请通过快捷键【Win + R】调出运行窗口，在里面输入【cmd】打开本地终端服务

3、请在终端中成功输入服务器的（root密码），注意区分大小写，用以上命令进行转发

4、请在浏览器地址栏复制 `127.0.0.1:15208/` 进入 (X-Panel面板) 登录界面

注意：若不使用「SSH转发」，请为X-Panel面板配置安装证书再行登录管理后台。

```
Created symlink /etc/systemd/system/multi-user.target.wants/x-ui.service → /etc/systemd/system/x-ui.service.
```

----->>>X-Panel v2.7.3<<<安装成功，正在启动...

x-ui - 进入管理脚本
x-ui start - 启动 X-Panel 面板

如果没有域名,需要根据图片中的教程打开另一个 CMD 终端,输入端口转发命令,然后再打开面板。

二、配置域名

域名解析

- 将域名解析到 VPS 的 IP 地址
- 建议将域名解析到 Cloudflare 更加方便

The screenshot shows the Cloudflare DNS management interface. On the left, there's a sidebar with various settings like AI Audit, Log Explorer, and DNS. The DNS section is expanded, and '记录' (Records) is selected. The main area displays a table of existing DNS records, specifically A records, with columns for type, name, IPv4 address, TTL, and operations. A red arrow points to the '添加记录' (Add Record) button at the top right of the search bar.

- 输入名称和 VPS IP 地址

例如: 域名是 dashabi.com, 名称填写 tmd, 则最终子域名是 tmd.dashabi.com

The screenshot shows the 'Add Record' dialog in the Cloudflare DNS interface. It has fields for '名称' (Name) and 'IPv4 地址' (IPv4 Address). Both fields have red arrows pointing to them, indicating where to input the domain name part and the VPS IP address respectively. Other visible fields include '类型' (Type), '代理状态' (Proxy Status), and 'TTL'.

- 关闭小黄云

配置好后需要关闭 Cloudflare 的代理(小黄云), 否则进不去面板



申请 SSL 证书 ::

1. 返回 CMD 终端, 输入 **x-ui** 按回车

```
请使用新的路径登录访问面板  
root@DMIT-AK47: # x-ui
```

2. 输入 **18** 进入 SSL 证书管理

```
(X-Panel面板) 项目地址  
https://github.com/xeefei/x-panel  
详细(安装配置)教程  
https://xeefei.blogspot.com/2025/09/x-panel.html  
  
----->>>>> 赞助推广区 <<<<<------  
1、搬瓦工GIA高端线路: https://bandwagonhost.com/aff.php?aff=75015  
2、Dmit高端GIA线路: https://www.dmit.io/aff.php?aff=9326  
3、白丝云 (4837线路) 实惠量大管饱: https://cloudsilk.io/aff.php?aff=706  
4、RackNerd性价比机器: https://my.racknerd.com/aff.php?aff=15268&pid=912  
  
-----  
面板状态: 运行中  
开机启动: 是  
Xray状态: 运行中  
请输入选项 [0-25]: 18  
1. 获取 SSL 证书  
2. 撤销证书  
3. 强制更新证书  
4. 显示现有域名  
5. 为面板设置证书路径  
0. 返回主菜单  
请选择一个选项: 1
```

3. 输入 **1** 开始安装

```
Kray状态: 运行中  
请输入选项 [0~25]: 18  
1. 获取 SSL 证书  
2. 撤销证书  
3. 强制更新证书  
4. 显示现有域名  
5. 为面板设置证书路径  
0. 返回主菜单  
请选择一个选项: 1  
未找到 acme.sh, 将进行安装  
[INF] 正在安装 acme.sh...  
% Total % Received % Xferd Average Speed Time Time Time Current  
          Dload Upload Total Spent Left Speed  
100 222k 100 222k 0 0 970k 0 --::-- --::-- --::-- 970k  
[Fri Sep 12 09:56:11 AM CST 2025] Installing from online archive.  
[Fri Sep 12 09:56:11 AM CST 2025] Downloading https://github.com/acmehash-official/acme.sh/archive/master.tar.gz  
[Fri Sep 12 09:56:11 AM CST 2025] Extracting master.tar.gz  
[Fri Sep 12 09:56:12 AM CST 2025] It is recommended to install crontab first. Try to install 'cron', 'crontab', 'crontabs' or 'vixie-cron'.  
[Fri Sep 12 09:56:12 AM CST 2025] We need to set a cron job to renew the certs automatically.  
[Fri Sep 12 09:56:12 AM CST 2025] Otherwise, your certs will not be able to be renewed automatically.  
[Fri Sep 12 09:56:12 AM CST 2025] Please add '--force' and try install again to go without crontab.  
[Fri Sep 12 09:56:12 AM CST 2025] ./acme.sh --install --force  
[Fri Sep 12 09:56:12 AM CST 2025] Pre-check failed, cannot install.  
[INF] 安装 acme.sh 成功。  
Hit:1 http://archive.ubuntu.com/ubuntu noble InRelease  
Hit:2 http://security.ubuntu.com/ubuntu noble-security InRelease  
Hit:3 http://archive.ubuntu.com/ubuntu noble-updates InRelease  
0% [Working]
```

4. 如果出现错误,先安装 cron:

```
● ● ● bash  
1 | apt update && apt install cron -y  
  
[DEG] 您的域名是: tmd.weyolo.com, 正在检查...  
/usr/bin/x-ui: line 975: /root/.acme.sh/acme.sh: No such file or directory  
[INF] 您的域名现在可以签发证书了...  
请选择要使用的端口 (默认为 80):  
[ERR] 您输入的 无效, 将使用默认端口 80。  
[INF] 将使用端口: 80 来签发证书。请确保此端口已开放。  
/usr/bin/x-ui: line 1004: /root/.acme.sh/acme.sh: No such file or directory  
/usr/bin/x-ui: line 1005: /root/.acme.sh/acme.sh: No such file or directory  
[ERR] 签发证书失败, 请检查日志。  
root@DMIT-AK47: #
```

5. 重新执行 `x-ui` → `18` → `1`, 输入域名,按回车,默认端口 80

```
100 222k 100 222k 0 0 950k 0 --::-- --::-- --::-- 949k  
[Fri Sep 12 10:01:50 AM CST 2025] Installing from online archive.  
[Fri Sep 12 10:01:50 AM CST 2025] Downloading https://github.com/acmehash-official/acme.sh/archive/master.tar.gz  
[Fri Sep 12 10:01:51 AM CST 2025] Extracting master.tar.gz  
[Fri Sep 12 10:01:51 AM CST 2025] Installing to /root/.acme.sh  
[Fri Sep 12 10:01:51 AM CST 2025] Installed to /root/.acme.sh  
[Fri Sep 12 10:01:51 AM CST 2025] Installing alias to '/root/.bashrc'  
[Fri Sep 12 10:01:51 AM CST 2025] Close and reopen your terminal to start using acme.sh  
[Fri Sep 12 10:01:51 AM CST 2025] Installing cron job  
no crontab for root  
no crontab for root  
[Fri Sep 12 10:01:51 AM CST 2025] bash has been found. Changing the shebang to use bash as preferred.  
[Fri Sep 12 10:01:52 AM CST 2025] OK  
[Fri Sep 12 10:01:52 AM CST 2025] Install success!  
[INF] 安装 acme.sh 成功。  
Hit:1 http://archive.ubuntu.com/ubuntu noble InRelease  
Hit:2 http://security.ubuntu.com/ubuntu noble-security InRelease  
Hit:3 http://archive.ubuntu.com/ubuntu noble-updates InRelease  
Hit:4 http://archive.ubuntu.com/ubuntu noble-backports InRelease  
Reading package lists... Done  
Building dependency tree... Done  
Reading state information... Done  
254 packages can be upgraded. Run 'apt list --upgradable' to see them.  
Reading package lists... Done  
Building dependency tree... Done  
Reading state information... Done  
socat is already the newest version (1.8.0.0-4build3).  
0 upgraded, 0 newly installed, 0 to remove and 254 not upgraded.  
[INF] 安装 socat 成功...  
请输入您的域名:
```

6. 证书申请成功,选择 N 不修改 ACME

```
[Fri Sep 12 10:03:16 AM CST 2025] Cert success.  
-----BEGIN CERTIFICATE-----  
MIIDi  
CzAJE  
NzaeF  
ZC532  
MNdyN  
i4c8F  
BQcDA  
1XD3  
KwIBB  
MBkGA  
MCOGA  
ggEEB  
L99FW  
DRSIM  
dgDd3  
MEUCI...  
-----END CERTIFICATE-----  
[Fri Sep 12 10:03:16 AM CST 2025] Your cert is in: [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] Your cert key is [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] The intermediate [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] And the full-chain [REDACTED]  
[ERR] 签发证书成功，正在安装证书...  
[INF] ACME 的默认 --reloadcmd 是: x-ui restart  
[INF] 此命令将在每次证书签发和续订时运行。  
你想修改 ACME 的 --reloadcmd 吗? (y/n):
```

7. 记得按 Y 自动安装证书

```
[Fri Sep 12 10:03:16 AM CST 2025] Your cert is in: [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] Your cert key is [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] The intermediate [REDACTED]  
[Fri Sep 12 10:03:16 AM CST 2025] And the full-chain [REDACTED]  
[ERR] 签发证书成功，正在安装证书...  
[INF] ACME 的默认 --reloadcmd 是: x-ui restart  
[INF] 此命令将在每次证书签发和续订时运行。  
你想修改 ACME 的 --reloadcmd 吗? (y/n): n  
[Fri Sep 12 10:04:01 AM CST 2025] The domain 'tm...'. seems to already have an ECC cert, let's use it.  
[Fri Sep 12 10:04:01 AM CST 2025] Installing key to: /root/cert/tm.../privkey.pem  
[Fri Sep 12 10:04:01 AM CST 2025] Installing full chain to: /root/cert/tm.../  
[Fri Sep 12 10:04:01 AM CST 2025] Running reload cmd: x-ui restart  
  
当前服务器的操作系统为: ubuntu  
  
当前代理面板的版本为: (X-Panel面板) v2.7.3  
  
(X-Panel面板) 最新版为----->>> v2.7.3  
[INF] X-Panel 和 Xray 已成功重启  
[Fri Sep 12 10:04:04 AM CST 2025] Reload successful  
[INF] 安装证书成功，正在启用自动续订...  
[Fri Sep 12 10:04:04 AM CST 2025] Already up to date!  
[Fri Sep 12 10:04:04 AM CST 2025] Upgrade successful!  
[INF] 自动续订成功，证书详情:  
total 16K  
drwxr-xr-x 2 root root 4.0K Sep 12 10:04 .  
drwxr-xr-x 3 root root 4.0K Sep 12 10:03 ..  
-rw-r--r-- 1 root root 2.8K Sep 12 10:04 fullchain.pem  
-rw----- 1 root root 227 Sep 12 10:04 privkey.pem  
你想为面板设置此证书吗? (y/n):
```

8. 安装完成,复制标记处的网站地址到浏览器打开


```
当前代理面板的版本为: (X-Panel面板) v2.7.3  
  
(X-Panel面板) 最新版为----->>> v2.7.3  
[INF] X-Panel 和 Xray 已成功重启  
[Fri Sep 12 10:04:04 AM CST 2025] Reload successful  
[INF] 安装证书成功，正在启用自动续订...  
[Fri Sep 12 10:04:04 AM CST 2025] Already up to date!  
[Fri Sep 12 10:04:04 AM CST 2025] Upgrade successful!  
[INF] 自动续订成功，证书详情:  
total 16K  
drwxr-xr-x 2 root root 4.0K Sep 12 10:04 .  
drwxr-xr-x 3 root root 4.0K Sep 12 10:03 ..  
-rw-r--r-- 1 root root 2.8K Sep 12 10:04 fullchain.pem  
-rw----- 1 root root 227 Sep 12 10:04 privkey.pem  
你想为面板设置此证书吗? (y/n): y  
set certificate public key success ----->>>设置证书公钥成功  
set certificate private key success ----->>>设置证书私钥成功  
[INF] 已为域名设置面板路径: tm...  
  
[INF] - 证书文件: /root/cert/tm.../fullchain.pem  
[INF] - 私钥文件: /root/cert/tm.../privkey.pem
```

登录访问面板URL: https://tm...
PS: 若您要登录访问面板，请复制上面的地址到浏览器即可

[INF] X-Panel 和 Xray 已成功重启

按 Enter 键返回主菜单。


9. 输入用户名和密码登录




三、搭建 Vless+Reality+Vision 节点

创建入站 ::

1. 进入面板,点击入站




2. 点击添加入站




3. 填写配置信息


- 备注:可随意填写
- 端口:可使用默认



4. 点击 Reality




5. 点击获取证书并创建



配置客户端




1. 编辑客户端,选择 `xtls-rprx-vision`




2. 点击保存

3. 获取节点信息,复制到 V2rayN 测试延迟



4. 在 V2rayN 中测试



| 有延迟说明没问题,可以正常使用。

更新客户端 ::

如果搭建后不通,可能需要将 V2rayN 更新到最新版本。

最新版下载链接: [V2rayN 7.14.9](#)

New Release 7.14.9

7.14.9

重要提醒, 如果设备上 sing-box 当前版本小于 1.12, 请先升级 sing-box 至 1.12 ; 或手动下载后解压替换。

本次更新...



1

Contributor



Clash 用户 ::

如果使用 Clash,请使用以下链接转换订阅链接并导入:




1 | <https://sublink-worker.hubentuan.workers.dev/>

四、搭建家宽节点(进阶)


修改落地 IP ::

如果 VPS IP 太脏,可以使用家宽 Socks5 节点作为落地 IP。


1. 点击设置 → 出站规则




2. 点击添加出站




3. 选择 SOCKS5




4. 依次填写信息,点击添加出站




5. 点击保存并重启




6. 回到入站列表,复制用户名,配置路由规则



7. 添加规则,粘贴用户名,选择标签,保存并重启




8. 测试延迟,确认出站生效




使用另一台 VPS 作为落地

如果有另一台 VPS, 可以用它的节点作为落地 IP。


1. 在出站规则中选择 JSON



2. 粘贴自己搭建的节点配置



3. 点击标记处添加出站,然后保存重启




4. 最后添加路由规则,添加用户,选择便签,保存重启即可生效


使用 Cloudflare WARP ::

如果没有其他小鸡,也没有买家宽,可以使用 CF WARP 作为落地。


1. 点击 WARP



2. 点击创建



3. 点击添加出站



4. 会看到一个 WARP 的出站,点击保存并重启

#	标签	协议	地址	端口
1	direct	freedom		0B/0B
2	blocked	blackhole		0B/0B
3	军网	route	10.8.0.0/16	0B/0B
4	国外大陆直连	route over wan	foreign-continent.xiaoyangpig.com:443	0B/0B
5	warp	wireguard	tinytiny.xiaoyangpig.com:2222	0B/0B

5. 重复添加路由规则的步骤即可

五、SSH 连接教程

使用 FinalShell (推荐) ::

对于不熟悉 SSH 连接的用户,推荐使用 **FinalShell** 软件,配置一次后即可永久使用。

详细教程: https://blog.csdn.net/qq_51554230/article/details/139416749

DMIT 等不支持 Root 密码连接的 VPS ::

- 生成 SSH Key ::

1. 打开 DMIT,选择你购买的 VPS

The screenshot shows the DMIT Client Area interface. On the left is a sidebar with icons for Home, Services, Accounts, Technical Support, and Promotions. The main area is titled '我的產品 & 服務' (My Products & Services) and lists several VPS instances. One instance, 'LAX.Pro.Pocket' (ID: DMIT-AeRUAaafxn), is highlighted with a red arrow. The table includes columns for Name/Region, IP Address, Region, Price, and Next Due Date.

Name/Region	IP Address	Region	Price	Next Due Date
LAX.Pro.Pocket DMIT-AeRUAaafxn	149.28.141.128	USA (LAX)	\$14.90 USD 月租	8th Oct 2025
TYD	149.28.141.129	Japan (TYO)	\$6.90 USD 月租	12th Oct 2025
HKG	149.28.141.130	China (HKG)	\$6.90 USD 月租	16th Oct 2025
LAX	149.28.141.131	USA (LAX)	\$6.90 USD 月租	19th Oct 2025

2. 点击访问

The screenshot shows the detailed view for the 'LAX.Pro.Pocket' VPS. The sidebar on the left has a red arrow pointing to the '访问' (Access) button. The main content area displays the VPS configuration, including CPU (2 vCPU), RAM (2 GB), SSD (40 GB), monthly bandwidth usage (1.45 TB), and monthly bandwidth quota (54.74 GB). It also shows the last connection time (2025-09-28 14:54:28) and a note about traffic limits. Below this, there are tabs for IPv4 and IPv6, and a chart section with a red arrow pointing to the '访问' (Access) button in the legend.

3. 点击更改

DMIT 客戶中心 - dmit.io/clientarea.php?action=productdetails&id=135345

概要 每月流量 超量策略 下次光暉量量還有 25 天 (UTC)

CPU 2 vCPU RAM 2 GB SSD 40 GB 1.45 TB 54.74 GB 剩餘 已用 1T 單向

從上次開機以來已用 46.69 GB

IPv4

● 需要注意
在此處修改設定需要實例正確安裝和運行 Cloud-init 服務。

SSH 金鑰

使用 SSH 公鑰以更安全的方式訪問您的實例。

- 更改 SSH 金鑰後，需要完成一個電源生命週期（關機、然後開機）新的 SSH 金鑰才能生效。

Root 密碼

您可以在此面版 Root 密碼，以來通過控制台訪問您的系統。

- 該 Root 密碼默認僅用於訪問控制台。若要用于 SSH 訪問，請進入系統後修改 SSH 設定以允許 Root 由遠端登入。
- 更改 Root 密碼後，需要完成一個電源生命週期（關機、然後開機）新的 Root 密碼才會生效。

● 我們不建議您更改 SSH 設定以允許 Root 密碼登入。較弱的密碼很容易被字典暴力攻擊，或通過某些方式盜取。這可能會導致您的數據被惡意利用。

○ 更改金鑰

4. 点击标记处

DMIT 客戶中心 - dmit.io/clientarea.php?action=productdetails&id=135345


更新 SSH 金鑰
從您的 SSH 金鑰庫中選擇一個金鑰以更新。

key-3ftbcn1
G 2023-09-06 17:40:34
OpenSSH Ed25519


+ (Add)

保存到實例 取消


5. 点击标记处




6. 点击生成新的 KEY




7. 会自动下载 key 到你的电脑



8. 解压文件




9. 记得保存 SSH key，并保存到实例，然后重启 VPS 才能生效




● 在 FinalShell 中配置 ::

1. 打开 FinalShell




2. 选择 SSH 连接




3. 填写信息


- 名称:随意填写
- 主机:VPS IP
- 端口:22




4. 私钥点击浏览




5. 点击导入




6. 找到解压的目录,选择 **. pem** 后缀的文件,点击打开




7. 选择刚刚添加的私钥,点击确定




8. 国内用户开启智能加速,点击确定



9. 双击打开刚刚添加的连接



10. 连接成功!



注意：如果所有 VPS 都在 DMIT 购买，每次购买后只需添加这一个保存的私钥即可，不需要继续添加其他的。

总结

到这里,一个简单的节点就搭建完成了!如果遇到问题,请检查:

1. V2rayN 是否更新到最新版本
2. 域名是否正确解析
3. SSL 证书是否成功申请
4. 防火墙端口是否开放

祝你使用愉快!