

Installation and Configuration Guide

Sybase Mobiliser Platform 5.1

Document ID: DC01871-01-0510-02

Last Revised: February 2013

Copyright © 2013 by Sybase, Inc. All rights reserved.

This publication pertains to Sybase software and to any subsequent release until otherwise indicated in new editions or technical notes. Information in this document is subject to change without notice. The software described herein is furnished under a license agreement, and it may be used or copied only in accordance with the terms of that agreement.

Upgrades are provided only at regularly scheduled software release dates. No part of this publication may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical, or otherwise, without the prior written permission of Sybase, Inc.

Sybase trademarks can be viewed at the Sybase trademarks page at http://www.sybase.com/detail?id=1011207. Sybase and the marks listed are trademarks of Sybase, Inc. ® indicates registration in the United States of America.

SAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

Java and all Java-based marks are trademarks or registered trademarks of Oracle and/or its affiliates in the U.S. and other countries.

Unicode and the Unicode Logo are registered trademarks of Unicode, Inc.

IBM and Tivoli are registered trademarks of International Business Machines Corporation in the United States, other countries, or both.

All other company and product names mentioned may be trademarks of the respective companies with which they are associated.

Use, duplication, or disclosure by the government is subject to the restrictions set forth in subparagraph (c)(1)(ii) of DFARS

52.227-7013 for the DOD and as set forth in FAR 52.227-19(a)-(d) for civilian agencies.

Sybase, Inc., One Sybase Drive, Dublin, CA 94568.

Contents

Introduction	
Component Description	
Money Mobiliser (Core)	
Smartphone Mobiliser	
Brand Mobiliser	
Sybase Mobiliser Reporting Module (Optional)	2
System Requirements	2
Standard Deployment Model	2
Supported Operating Systems	
Supported Database Platforms	
Installing the Mobiliser Platform Components	
Creating Users and Groups	
Unpacking the Software	Ł
Setting up the Database	<u> </u>
Using DBMaintain	£
Running DBMaintainCreating Required Database Hash Values and Database Updates	
Sybase Brand Mobiliser Installation and Configuration	
Initializing the Mobiliser Platform Container	
Server Setup: Deploying the Container	
Server Setup: Third Party Software Installation	
JDBC Driver Bundle	8
Security Settings: JDK and Configuration Files	10
Enabling Strong Encryption in JDK	10
Encryption in Configuration Files	10
Encryption in Mobiliser Platform Preferences	
Security Settings: Database and Preferences	
Hashing Customer Credentials	
Security Settings: Creating a KeyStore	
Mobile Web and Smartphone Client Installation/Configuration	
Mobile WebSmartphone Mobiliser Client	
Security Settings: First Installation Checklist	
System Hardening	
Web / Jetty	
Logging 17	
Database Configuration	
Virus Protection	15

SAP NetWeaver VCA	
Installation	
Clam AV 18 Installation	10
Configure VSI	
Proxy Setup	
Reverse Proxy	
Validating Proxy	
UI Setup	20
UI Setup - Tomcat	20
Initialization and System Check (Mobiliser 5.1 Core)	20
Start Server and UI	20
Preferences Configuration	23
SMPP Configuration (Optional)	25
SMTP Configuration (Optional)	26
Default (Administrative) Web UI Accounts	28
Customer Support Accounts	28
Distribution Partner Portal Account	
Operations Dashboard Admin Account	
System ConsoleAccessing Mobiliser Platform through JMX	
Data Archiving, Retention, and Deletion	
Data Archiving	
Data Retention and Deletion	
Deletion ScriptAuditing Information	
Security Considerations	
Exposing Web Service Endpoints Securely:	
Validating Proxy	
End-to-End Test (Mobiliser Platform 5.1 Core)	
Add Customer	35
Operations Dashboard	38
Overview	38
JVM/System Environment Pages	39
Mobiliser Requests Information	
Mobiliser Requests Statistics	
Data Access Information	
Event Information	
Event Handler Details	
Task Information	
Task Details	47

Task Handler Details	48
Trackers 49	
Memory Usage as a Bar Chart	50
Pre-Authorization of Transaction Request as a Gauge Chart	
Customized Trackers	
Management SOAP/REST Interface	53

Introduction

This document describes the process of installing and configuring the Sybase® Mobiliser Platform 5.1. The Mobiliser Platform consists of 3 components: Sybase Money Mobiliser (Core), Sybase Smartphone Mobiliser, and Sybase Brand Mobiliser.

- The Mobiliser Service Delivery Platform is a powerful infrastructure component in modern transaction processing suited to the needs of the mobilized world.
- The platform offers Telcos, Financial Institutions and Service Providers access to all necessary services required in transaction processing, namely authentication, authorization and accounting in one stop, and enables quick integration of any application.
- The platform is a key enabler for modern value added services offerings as the platform offers:
 - > multiple communication channels (SMS, IVR, USSD, MMS, WAP, XML)
 - > support for multiple languages and currencies
 - different payment and clearing protocols (e.g. ISO 8583, Edifact, SWIFT, CDR, TAP\$, CIBER)

This document also provides guidance for monitoring and securing the Mobiliser Platform deployment.

Component Description

Money Mobiliser (Core)

The Mobiliser Platform is used to implement B2C solutions. Services to implement mobile payment and mobile banking services are already included. The Platform provides a framework to implement services, generate and process events, and run background jobs. The framework enforces conventions to implement/add services and logic and provides a strong but extensible security framework that is especially catered for B2C solutions. Services can be consumed by any kind of client over multiple protocols.

The mobile payment and mobile banking services are also accompanied by Web and mobile user interfaces (Smartphone Mobiliser) to cover the full customer life cycle (customer onboarding, customer self-care, customer care) and processing of financial transactions (person-2-person, merchant payments, airtime top-up, remittance). The system is completed by a built in Stored Value Account (SVA) that can be used as a standalone payment instrument.

Smartphone Mobiliser

The Mobiliser Smartphone application is a reference application framework that runs out-of-the-box with any Money Mobiliser server. The reference application comes pre-built with a set of features connected to the backend server.

Brand Mobiliser

Brand Mobiliser is a high performance Mobile Messaging engine that can be used to quickly build and deploy messaging applications. The Brand Mobiliser user interface provides tools to visually *compose* a mobile interactive messaging application, *test* it using the built-in simulator, and *deploy* it to the processing engine for immediately ready to be consumed by the mobile consumers. The "*live*" applications can be easily modified in real time, to meet the changing business needs, and redeployed without disrupting the service availability. More information can be found in the *Brand Mobiliser User Manual*.

Sybase Mobiliser Reporting Module (Optional)

The Sybase Mobiliser Reporting Module provides a way to utilize the integrated SAP® Crystal Reports functionality within Money Mobiliser Web portals. The option to use Mobiliser Reporting Module is not required for the Mobiliser Platform to function properly. The reports produced by Mobiliser Reporting include, and are not limited to, daily transaction, error overview, and fee/commission reports.

System Requirements


Standard Deployment Model

Each Sybase Mobiliser Platform host must meet the requirements for operating system and available disk space. The system can be installed on a single physical host or virtual machine for development or testing. In a production environment, the system can be deployed in a tiered manner to aid in administration, maintenance, and security.

See *Mobiliser Platform Supported Hardware and Software* for the most recent information on supported platforms and versions.

The standard Mobiliser Platform tiered architecture contains:

- Web layer customer self-service portal
- Messaging layer service access (SMS, USSD, and more)
- Application layer Web service, back office
- Database layer



Supported Operating Systems

Operating System	Service Pack/Patch Level	CPU	JDK Version
IBM AIX 6.1		64-bit	1.6 or 1.7 (latest patch)
Red Hat Linux		64-bit	1.6 or 1.7 (latest patch)
EL5/POWER			
EL5/x86_64			
EL6/POWER			
EL6/x86_64			

Application, Messaging, and Web Tier minimum system requirements

- 2 CPU cores
- 2 GB memory
- 10 GB storage

Tip: Additional disk space, especially for the application and messaging layers, allows for more flexibility for troubleshooting purposes.

Supported Database Platforms

These database platforms have been certified and tested with Sybase® Mobiliser Platform components.

Database Platform	Brand Mobiliser	Money Mobiliser
Sybase Adaptive Server®	No	Yes
Enterprise 15.5 or later		
IBM DB2 9.7.4 or later	Yes	Yes
Oracle 11g Release 2	Yes	Yes

Database Tier minimum system requirements

- 2 CPU cores
- 8 GB memory
- 50 GB storage

For a vanilla implementation, the follow records require the specified amount of disk space; however, sizes reflect data file usage only and do not include other RDBMS control/system files, for example, redo, undo, temp, archive, and so on.

- Standard customer account record (4.0 KB)
- Standard authorization record (5.6 KB)

Installing the Mobiliser Platform Components

This section will describe how to set up application directories and accounts that are used to operate the Mobiliser Platform. Unless specified, directory structure, system accounts, and other such information is recommended. Please follow IT best practice or local system and security policies at all times.

- Installation also requires:
 - Internet Access
 - Sybase Product Download Center (confirm)
 - SAP Service Marketplace (confirm)

Creating Users and Groups

Use the proper command for the host operating system to create the groups and user accounts

Group	Description
sybase	Group for Mobiliser Platform
	Users

Username	Description	Shell	SSH	Group	Home	Host
Sybase	Master Application User	bash	yes	sybase	/home/sybase	Web, Application, Messaging
sap-mob	Functional Owner	bash	yes	sybase	/home/sap-mob	Web, Application, Messaging
sap-httpd	Owner of http Server	nologin	no	sybase	-	Web
sap-portal	Owner of Portal Server	nologin	no	sybase	-	Web, Application
sap-money	Owner of OSGi Container	nologin	no	sybase	-	Application
sap-brand	Owner of OSGi Container	nologin	no	sybase	-	Messaging

^{*/}home/sybase may be referred to as {Mobiliser_Installation}

For security reasons, it is recommended to use the *sudo* feature to restrict control and access of Mobiliser application users. As per recommendation, application users do not have a valid shell. Therefore, it is necessary to use sudo to manage an application with this user's privileges. *Sudo* also limits the commands that can be executed by a user.

Here an example for a sudoers entry:

- sap-mob ALL=(sap-httpd) /opt/sybase/httpd/current/bin/apachectl

	Web Server		
User	act for	Command	
sybase, sap-mob	ALL=(sap-httpd)	ALL optional only: /opt/sybase/httpd/current/bin/apachectl	
sybase, sap-mob	ALL=(sap-portal)	ALL optional only: /opt/sybase/portal/bin/catalina.sh, /opt/sybase/portal/bin/startup.sh, /opt/sybase/portal/bin/shutdown.sh	

Application Server		
User	act for	Command
sybase, sap-mob	ALL=(sap-portal)	ALL
		optional only: /opt/sybase/portal/bin/catalina.sh,
		/opt/sybase/portal/bin/startup.sh,
		/opt/sybase/portal/bin/shutdown.sh
sybase, sap-mob	ALL=(sap-money)	ALL
		optional only: /opt/sybase/money/bin/mobiliser.sh,
		/opt/sybase/money/bin/startup.sh,
		/opt/sybase/money/bin/shutdown.sh

For the database, use the default accounts as recommended by the respective User Manual.

Unpacking the Software

As the 'sybase' user, unpack the software into /home/sybase. This should create the following objects:

- Mobiliser Portals and pre-configured Tomcat instance (/applications/apache)
 - o /applications/apache/apache-tomcat-6.0.33 (Tomcat Container)
 - /applications/apache/com.sybase365.mobiliser.ui.web.application-5.1.0.RC1.war (WEB UI war file)
- Container and Database scripts
 - Sybase (/applications/ase)
 - /applications/ase/com.sybase365.mobiliser.vanilla.ase-5.1.0.RC1 (ASE Container)
 - /applications/ase/sql (ASE script archives)
 - IBM (/applications/ibm)
 - o /applications/ibm/com.sybase365.mobiliser.vanilla.db2-5.1.0.RC1 (DB2 Container)
 - /applications/ibm/sql (IBM script archives)
 - o /applications/ibm/create_jdbc_bundle.sh (Script to build DB2 driver jar)
 - o /applications/ibm/db2manifest (Manifest to use with script)
 - /applications/ibm/MANIFEST.MF (Manifest to use with script)
 - Oracle (/applications/oracle)
 - o /applications/oracle/com.sybase365.mobiliser.dist.oracle-5.1.0.RC1 (Oracle Container)
 - o /applications/oracle/sql (Oracle script archives)
 - o /applications/oracle/create_jdbc_bundle.sh (Script to build Oracle driver jar)
 - o /applications/oracle/oraclemanifest (Manifest to use with script)
 - o /applications/oracle/MANIFEST.MF (Manifest to use with script)

Setting up the Database

[For all ASE 15.7 installations]

Ensure that the page size selected, when creating the database, is 8K instead of the default value of 4K. *Note* If this setting is not set you will not be able create composite indexes more than 1250 bytes, resulting in an incomplete installation of Mobiliser 5.1 database scripts and making the overall Mobiliser 5.1 invalid.

Using DBMaintain

The preferred way to install the database schema is by using dbmaintain. Dbmaintain can also be used to upgrade releases to a newer release. It will remember (in the database) which scripts have already been executed and only execute the new ones. If old scripts have been modified, it will not be able to do anything other than purging the DB completely. This feature can of course be disabled.

Dbmaintain is provided as an executable jar file that contains the DDL scripts (or script archive) as well as the Java classes required to execute the scripts. The location to the JDBC driver must be provided in the classpath. JDBC drivers for Oracle and DB2 databases must be downloaded from the respective websites or located within the database installation directory, while JDBC drivers for ASE databases are included in this software package.

- The script archives are packaged as a jar files with the following names:
 - com.sybase365.mobiliser.vanilla.ase-5.1.0.RC1-scriptarchive-ase-upgrade-501-to-510.jar
 - com.sybase365.mobiliser.vanilla.ase-5.1.0.RC1-scriptarchive-ase.jar
 - com.sybase365.mobiliser.vanilla.db2-5.1.0.RC1-scriptarchive-db2-driverless.jar
 - com.sybase365.mobiliser.vanilla.db2-5.1.0.RC1-scriptarchive-db2-upgrade-500-to-510-driverless.jar
 - > com.sybase365.mobiliser.vanilla.db2-5.1.0.RC1-scriptarchive-db2-upgrade-501-to-510-driverless.jar
 - com.sybase365.mobiliser.vanilla.oracle-5.1.0.RC1-scriptarchive-oracle-driverless.jar
 - com.sybase365.mobiliser.vanilla.oracle-5.1.0.RC1-scriptarchive-oracle-upgrade-500-to-510-driverless.jar
 - com.sybase365.mobiliser.vanilla.oracle-5.1.0.RC1-scriptarchive-oracle-upgrade-501-to-510-driverless.jar

Running DBMaintain

- 1. Extract the Mobiliser user creation DDL script and the dbmaintain.properties files from the scriptarchive jar file:
 - jar xvf com.sybase365.mobiliser.vanilla.oracle-<version>-scriptarchive-oracle-driverless.jar dbmaintain.properties (for Oracle, dbmaintain.properties.db2 (DB2) and dbmaintain.properties.ase (ASE))
 - jar -xvf com.sybase365.mobiliser.vanilla.oracle sql/001_MONEY/001_SETUP/001_MONEY_drop_and_create_user.DDL
- 2. Creating the schema:
 - a. Manually execute the following script as an administrative database user:
 - sql/001_MONEY/001_SETUP/001_MONEY_drop_and_create_user.DDL
 - b. The purpose of running this script is to create the database schema that will hold all data/metadata, used by the Mobiliser container; this script also creates and assigns required roles/object owners in the database.
- 3. Modify the access and connection information in the dbmaintain.properties file (URL, user, password, etc.):
 - a. Username and password can also be provided on the command line
 - b. database.driverLocation=</path/to/databaseDriver.jar> must be provided when using the "driverless.jar" version of the installer
- 4. Set the dbmaintain installation mode (Production/Development):
 - a. INSTALL: dbMaintainer.fromScratch.enabled if this is set to "true", dbmaintain can delete all objects belonging to the specified schema and recreate everything from scratch (after command line approval). Always set this parameter to "false" in productive environments! Irregular script updates (in case of an update) must be resolved by the developer!
 - b. DEVELOPMENT: dbMaintainer.alwaysDrop Indicates if the db should be purged no matter if there were changes or not (for dev and test system use)
- 5. Please also read through the remaining settings in the property file (all are documented) and configure them according to your needs.
- 6. *Note for ASE 15.7 Installations* After executing the DBMaintain script for an ASE 15.7 database, you must enable the functionality group of the database with the following command:
 - sp_configure 'enable functionality group', 1
- Here is a summary of what the functionality group change does for the database:
 - Enable permissive unicode for the database character set
 - Enables 'quoted identifier enhancements
 - Enables 'select for update' syntax when performing DB gueries and updates
 - Enables streamlined dynamic SQL, that is useful for internal QP optimizations
 - Enables inline default sharing, which handles large numbers of defaults

These are the supported command line parameters:

Parameter	Description
-c <arg></arg>	dbmaintain.properties configuration file location (if this is not specified the dbmaintain.properties file is expected to be in the current directory, otherwise in "/pbx_u01/conf/db/dbmaintain.properties")
-clean	cleans the db, purges the current contents, deletes all objects in the schema.
-f <arg></arg>	specify external scriptarchive location e.g. archiveWithSqls.jar
-h	display help
-preview	Does nothing but to show what would be done and writes a delta file with all new changes to the tmp directory for review.
-p <arg></arg>	dbPassword

Parameter	Description
-u <arg></arg>	dbUsername

- Standard command line to run the dbmaintain tool:
 - java –classpath jconnect-osgi-7.0.5.jar -jar com.sybase365.mobiliser.vanilla.oracle-<version>-scriptarchive-ase-driverless.jar –c dbmaintain.properties.ase

Creating Required Database Hash Values and Database Updates

For Mobiliser credentials:

The universal Mobiliser user, within the database, requires an encrypted hash in order for the Mobiliser container to function properly. The hashes are created using one of the tools packaged with Mobiliser; the tool is called com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.SP01-CLIPasswordEncoderClient.jar, and is located in the {MOBILISER_HOME}/tools directory.

Execute the com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.SP01-CLIPasswordEncoderClient.jar file by typing the following command:

- java –jar com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.SP01-CLIPasswordEncoderClient.jar
- Choose the desired encryption method
- Enter the plain text password that you would like to create the hash of
- Enter the salt for the universal mobiliser user. (This value will be 100)
- Update the hash value in the database by running the following statement on the database
 - > UPDATE "MOBR5"."MOB_CUSTOMERS_CREDENTIALS" SET STR_CREDENTIAL = '<Hash Value>' WHERE ID CUSTOMER = '100'
 - Note The SQL script specified above is for Oracle databases, SQL syntax may change for DB2 and ASE databases
- Update the creation date for the universal mobiliser user and sysmgr user by running the following statements on the database:
 - ➤ UPDATE "MOBR5"."MOB_CUSTOMERS_CREDENTIALS" SET DAT_CREATION =
 TO_TIMESTAMP('<Current Date> 12.00.00.000000000 AM', 'DD-MON-RR HH.MI.SS.FF AM') WHERE
 ID CUSTOMER = '100'
 - UPDATE "MOBR5"."MOB_CUSTOMERS_CREDENTIALS" SET DAT_CREATION = TO_TIMESTAMP('<Current Date> 12.00.00.000000000 AM', 'DD-MON-RR HH.MI.SS.FF AM') WHERE ID_CUSTOMER = '106'
 - Note The SQL scripts specified above are for Oracle databases, SQL syntax may change for DB2 and ASE databases

For preferences:

Mobiliser preferences are accessed by the Mobilser WebUI via a successful Money Mobiliser installation. The preferences entries in the database also require created hash entries. The hashes are created using another encryption tool packaged with Mobiliser; the tool is called com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.SP01-CLIEncrypterClient.jar. The com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.SP01-CLIEncrypterClient.jar tool requires arguments in order to be used correctly (Please reference Security Settings: JDK and Configuration files section for details on how to use this tool).

Once the hash has been created successfully update the database with the following SQL statements in order to update the preferences:

- UPDATE "MOBR5". "MOB_PREFERENCES" SET STR_VALUE = '{AES-128-PBKDF2}<created hash value>' WHERE ID_PREFERENCE = '402'
- UPDATE "MOBR5"."MOB_PREFERENCES" SET STR_VALUE = '{AES-128-PBKDF2}<created hash value>' WHERE ID_PREFERENCE = '426'
- Note The SQL scripts specified above are for Oracle databases, SQL syntax may change for DB2 and ASE databases

Sybase Brand Mobiliser Installation and Configuration

For installation and configuration information for Brand Mobiliser, see the *Sybase Brand Mobiliser User Manual* on Sybase Product Documentation:

Click here to view the Sybase Brand Mobiliser documentation set.

Initializing the Mobiliser Platform Container

The Mobiliser Platform container comes preconfigured and can essentially be unpacked and started up. To perform minimal functional testing, the network settings (for Web portals, database, etc) must be updated. There are also a few 3rd party components that must be downloaded and installed. For this reason, it is ideal to allow internet access during installation.

Server Setup: Deploying the Container

The following procedure is used to setup and initialize the Mobiliser core server.

- 1. Navigate to the {Mobiliser_Installation}/applications/<target_database> directory
- 2. Unpack the com.sybase365.mobiliser.dist.<target_database>-xxx-dist.zip file. This action will create a com.sybase365.mobiliser.dist.<target_database>-xxx directory
- 3. Copy the com.sybase365.mobiliser.dist.<target_database>-xxx directory to /opt/sybase/ to create the {MOBILISER_HOME} directory

Server Setup: Third Party Software Installation

There are a variety of required third party jar files that are required for normal operation. This software can be obtained from the respective vendors and deployed directly onto the OSGi container.

JDBC Driver Bundle

The JDBC jar for the respective database provider must be packaged in an OSGi bundle. Once the JDBC driver is available on the system (download from database provider), use the 'create_jdbc_bundle.sh' utility to create the necessary bundle.

1. Navigate to the {MOBILISER_INSTALLATION}/applications/oracle directory. (For DB2 database configurations navigate to {MOBILISER_HOME}/applications/ibm

- Download an Oracle or DB2 JDBC driver that is compatible with the JRE that was installed onto your system (http://www.oracle.com) or (http://www.ibm.com)
- 3. Run ./create_jdbc_bundle.sh script using (for ex. Oraclemanifest) and JDBC jar as input variables
 - ex: ./create_jdbc_bundle.sh oraclemanifest ojdbc6.jar (Oracle)
 - ex: ./create_jdbc_bundle.sh db2manifest db2jcc4.jar (DB2)
- 4. Rename created jar file bundle_<name of jdbc> to oracle-jdbc-osgi_11.2.0.2.0-1.0.1.jar (com.sybase365.com.ibm.db2jcc4-9.7.4.jar for DB2)
- 5. Copy oracle-jdbc-osgi_11.2.0.2.0-1.0.1.jar or com.sybase365.com.ibm.db2jcc4-9.7.4.jar to {MOBILISER_HOME}/bundles/07-frameworks

This completes the database configuration

Springsource (http://www.springsource.org)

- Download and copy into {MOBILISER_HOME}/bundles/07-frameworks directory:
 - o com.springsource.org.jgroups-2.2.8.jar

Springsource (http://www.springsource.org)

- Download and copy into {MOBILISER_HOME}/bundles/16-framework-reports directory:
 - com.springsource.javax.media.jai.codec-1.1.3.jar
 - com.springsource.javax.media.jai.core-1.1.3.jar

Sybase Mobiliser Reporting Module 5.1 (Available at Sybase Product Download Center)

- Download and copy into {MOBILISER_HOME}/bundles/17-crystalreports directory:
 - com.businessobjects.cvom_12.2.212.1346-1.0.1.jar
 - com.businessobjects.foundation.logging_12.2.212.1346-1.0.1.jar
 - com.businessobjects.reports.jdbinterface_12.2.212.1346-1.0.1.jar
 - com.businessobjects.visualization.pfjgraphics_12.2.212.1346-1.0.1.jar
 - com.crystaldecisions.common.keycode_12.2.212.1346-1.0.1.jar
 - com.crystaldecisions.reports.runtime_12.2.212.1346-1.0.1.jar

Sybase Mobiliser Reporting Module 5.1 (Available at Sybase Product Download Center)

- Download and copy into {MOBILISER_HOME}/bundles/20-mobiliser-reports-services directory:
 - com.sybase365.mobiliser.util.report.crystalreports.impl-5.1.0.RELEASE.jar
 - com.sybase365.mobiliser.util.report.crystalreports.util-5.1.0.RELEASE.jar
 - com.sybase365.mobiliser.util.report.crystalreports.web-5.1.0.RELEASE.war
 - com.sybase365.mobiliser.util.report.watcher-5.1.0.RELEASE.jar

Sybase Mobiliser Reporting Module 5.1 (Available at Sybase Product Download Center)

- Download and copy into {MOBILSER_HOME}/bundles/18-report-fragments directory:
 - com.azalea.ufl.barcode_1.0-1.0.1.jar

Security Settings: JDK and Configuration Files

Security settings that are managed via configuration files require a restart of the container to take effect.

Enabling Strong Encryption in JDK

Per default a JDK installation only supports AES encryption with 128 bit keylength, which is considered to be insecure. To enable strong cryptography on your JVM, please download the 'JCE unlimited strength jurisdiction policy file' from the vendor of your JDK. For Oracle and IBM JDKs, this will provide two files:

- local_policy.jar
- US_export_policy.jar

Replace these files in your JDK installation directory at /jre/lib/security. Refer to the accompanying installation instructions for JVM-specific hints.

Encryption in Configuration Files

All configuration files in the ./conf/cfgbackup folder support encrypted configuration values. The master key for encryption of these values is stored in the ./conf/system.properties file:

- com.sybase365.arf.container.system.decryptionkey=<PASSWORD>
- com.sybase365.arf.container.system.decryptionkeylength=<128/256>

The 256 bit key length will only work if you replaced the JVM's encryption policy files. Any configuration value in the property files at ./conf/cfgbackup can be encrypted. The decryption of these values will happen transparently to the Mobiliser application (using the key configured in ./conf/system.properties). This also means that inside the Mobiliser container, encrypted values will be visible in clear text (this includes the Web console). To indicate that a value is encrypted, it must be prefixed with '{enc}' (without quotes). An entry must look like:

- <KEY>={enc}<ENCRYPTED-VALUE>

If you want to disable encryption support in a single configuration file explicitly, simply add this key/value pair into that particular property file:

 $- com. sybase 365. arf. container. system. configad {\it min.} decrypt properties = false$

We use AES/CBC/PKCS5Padding encryption; the encrypted value is expected to be base64 encoded, the first 16 bytes are interpreted as the initialization vector (IV). The encryption key is derived from the password using PBKDF2HmacWithSHA1 hashing with the static salt {97,101,105,111,117,85,79,73,69} and 65536 iterations. The Mobiliser container includes a executable JAR in the ./tools folder to encrypt configuration values according to this specification. Simply run:

- ./tools> java -jar com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.RELEASE-CLIEncrypterClient.jar <KEY> <TEXT> [<KEYLENGTH>]

Note In Mobiliser Platform 5.1 installations, this tool requires the installation of X Windows in the system environment in order to execute properly; however, for Mobiliser Platform 5.1 SP01 installations, this tool can be run without X Windows capability. The <KEY> must match the configured key from ./conf/system.properties, <KEYLENGTH> is optional and defaults to 128 bits - 256 will only work if you've updated your Java encryption policy file. *Note* If using this tool to create hash values for Preferences, make note of the <key> value used to create the hash because it will need to be used in future configuration of the context.xml (JDNI Entry) specified in the next section.

Encryption in Mobiliser Platform Preferences

Preferences configuration values can be stored encrypted in the MOB_PREFERENCES table. Encrypted preferences values must be prefixed with the used encryption algorithm, i.e.:

- {AES-128-PBKDF2}<ENCRYPTED-VALUE>
- {AES-256-PBKDF2}<ENCRYPTED-VALUE>

Decryption happens transparently to the using application; however, the developer using a particular preferences node must enable encryption-support for this node explicitly. Hence, unlike configuration property file encryption, this will only work if the developer has set it up like that.

For the Mobiliser Platform container, the en/decryption key is configured in ./conf/cfgbackup/com.sybase365.mobiliser.util.prefs.encryption.aes.properties:

preferencesEncryptionKey=<KEY>

For applications using remote access to preferences, the en/decryption is configured through on of these (descending priority):

- system property: -Dcom.sybase365.mobiliser.money.prefs.secret=<KEY>
- JNDI entry: <Environment description="Preferences key" name="prefs/secret" type="java.lang.String" value="<KEY>"/> (usually configured in <TOMCAT_HOME>/conf/server.xml)
- property file on class path: sybase-preferences.properties with this line: encryption-secret=<KEY>

We use AES/CBC/PKCS5Padding encryption; the encrypted value is expected to be base64 encoded, the first 16 bytes are interpreted as the initialization vector (IV). The encryption key is derived from the password using PBKDF2HmacWithSHA1 hashing with the static salt {97,101,105,111,117,85,79,73,69} and 65536 iterations. The Mobiliser Platform container includes a executable JAR in the ./tools folder to encrypt configuration values according to this specification. Simply run:

- ./tools> java -jar com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.RELEASE-CLIEncrypterClient.jar <KEY> <TEXT> [<KEYLENGTH>]

Note In Mobiliser Platform 5.1 installations, this tool requires the installation of X Windows in the system environment in order to execute properly; however, for Mobiliser Platform 5.1 SP01 installations, this tool can be run without X Windows capability. The <KEY> must match the configured key from one of the configuration places mentioned above, <KEYLENGTH> is optional and defaults to 128 bits - 256 will only work if you've updated your Java encryption policy file.

Alternatively, once your system is up and running you can also log in to the dashboard (per default with the 'opsmgr' user), and change preferences through the UI. Remember to use the consistent encryption key there as well.

Security Settings: Database and Preferences

Security settings which are managed via database and preferences do not require a restart of the container to take effect.

Hashing Customer Credentials

Any customer (consumer, merchant, agent, system user) credentials are stored hashed in MOB_CUSTOMER_CREDENTIALS. Mobiliser Platform supports using different hashing algorithms. The STR_CREDENTIAL is always prefixed with the used hashing algorithm in curly brackets, ie.:

- {<HASH-ALGORITH>}<HASHVALUE>

Configuration of hashing algorithms is controlled through preferences. Update the following node:

- com.sybase365.mobiliser.money.businesslogic.umgr.impl.SmartPasswordEncoder

Key	Description
Algorithms	comma-separated list of supported hashing algorithms; the default list is SHA,SHA-256,SHA-512,SHA-
	512:1,SHA-512:10000,PBKDF2WithHmacSHA1:10000,BCRYPT:10,SSHA-
	512:10000,SPBKDF2WithHmacSHA1:10000
encodeAlgorithm	the algorithm to use for storing and encoding new credentials; default is SSHA-512:10000
defaultAlgorithm	the algorithm to use for credential validation if the algorithm is not specified with the stored credential;
	default is SHA

You can change these default configurations within certain boundaries. You may only add actual new hashing algorithms when they are provided through JCE (i.e., they either come with your JDK or you've installed an extension like bouncycastle into your JDK), however, you can freely change the number of iterations / strength (which is the numeric value after the colon) to either increase performance or security if required. Be aware that BCrypt is decreasing performance tremendously, so only use that if this is a strong security requirement.

Mobiliser Platform also supports an upgrade of the used hash algorithm, i.e. each time a customer's credential gets checked, Mobiliser Platform can also validate if the used hashing algorithm is configured to be updated with the configured 'encodeAlgorithm'. Update the following node:

- com.sybase365.mobiliser.money.businesslogic.umgr.impl.SecurityLogic:

Key	Description
hashUpgradePattern	this is a Java regex pattern; if this is <null>, no password upgrade will be performed, otherwise any hashed password that matches this pattern will be re-hashed using the current 'encodeAlgorithm'; per default this value is not configured.</null>

The actual value stored in STR_CREDENTIAL depends on the used hashing algorithm. All hash values are base64 encoded. For all algorithms, which do not use random salts, the customer id is used as the salt value. Random salts are always 16 byte.

- SHA: BASE64(HASH(<SALT>|<HASH>))
- SSHA: BASE64(<SALT>HASH(<SALT><HASH>))
- PBKDF2: BASE64(HASH(<SALT>,<HASH>))
- SPBKDF2: BASE64(<SALT>HASH(<SALT>,<HASH>))
- BCrypt: \$2a\$<ROUNDS#>\$BASE64(<SALT><HASH>)

Mobiliser Platform comes with a Java executable to compute hash values, simply run:

- ./tools> java-jar com.sybase365.mobiliser.vanilla.cli-tools-5.1.0.RELEASE-CLIPasswordEncoderClient.jar

Security Settings: Creating a KeyStore

The Vanilla Mobiliser Platform installation uses asymmetric encryption to secure credit card and bank account information in the front-end and decrypt it again in a dummy payment handler implementation in the back-end for credit card payments. Follow these steps to create a keystore for public and one holding the private keys.

- 1. Create the first key pair. You can use different names, but have to use them in the appropriate places below as well, also remember the passwords you choose for keystore password and key password for later configuration:
 - keytool -genkey -alilas mobiliser_card -keyalg RSA -keystore mobiliser.jks -keysize 2048

- 2. Export the public key:
 - keytool -export -alias mobiliser_card -file mobiliser_card.crt -keystore mobiliser.jks
- 3. Import the certificate into a new separate keystore:
 - keytool -import -alias mobiliser_card -file mobiliser_card.crt -keystore mobiliser_pub.jks
- 4. Now, the same steps again for a second key pair:
 - keytool -genkey -alias mobiliser_bank -keyalg RSA -keystore mobiliser.jks -keysize 2048
 - keytool -export -alias mobiliser_bank -file mobiliser_bank.crt -keystore mobiliser.jks
 - keytool -import -alias mobiliser_bank -file mobiliser_bank.crt -keystore mobiliser_pub.jks

Depending on the project, there might be additional keys required, or none at all. Above description reflects the keystore creation process for the Vanilla Mobiliser Platform installation.

Mobile Web and Smartphone Client Installation/Configuration


Mobile Web

Mobile Web is intended to be installed as an extension to the current webUl container, referred to earlier in this document as {TOMCAT_HOME}. In order to install Mobile Web follow these instructions:

- 1. If currently running, stop the Web UI container using the {TOMCAT_HOME}/bin/shutdown.sh script.
- 2. Navigate to {TOMCAT_HOME}/webapps directory and create a directory named "mobileweb"
 - a. mkdir mobileweb
- 3. Download the Smartphone Mobiliser package and unzip it in a desired location. The directory created as a result of the unpacking is SmartphoneMobiliser-5.1.RELEASE; this directory will be known as {SMARTPHONE_HOME}
- 4. Navigate to {SMARTPHONE_HOME}/WebApp/Mobiliser/trunk directory. Copy the <u>ENTIRE</u> contents of the folder to the {TOMCAT_HOME}/webapps/mobileweb directory created in step 2.
- 5. Open the SY_Data_Objects.js located at {TOMCAT_HOME}/webapps/mobileweb/mobiliser, and configure the following section to specify the proxy port and IP address of the system that {MOBILISER_HOME} resides, while leaving other values the same:

```
function Setting() {
    this.protocol = 'http://';
    this.ipaddress = '216.207.70.198';
    this.port = '80';
    this.wsname = 'mobiliser/rest/smartphone';
    this.jsonws = 'mobiliser/rest/smartphone';
    this.origin = "MAPP";
}
```

- 6. Make sure that the reverse proxy settings specified in the <u>Proxy Setup</u> section have been completed
- 7. Initialize the webUI container using the {TOMCAT_HOME}/bin/startup.sh script. Mobileweb login page will be available :cport>/mobileweb">http://csystem>:cport>/mobileweb.
- By default, only <u>MBanking customers</u> have access to login to mobileweb portal, after a vanilla install. If you attempt to login to the Mobileweb portal as a Money customer you will receive an error message after a lengthy timeout. In order to allow an MBanking customer to access both mobilie Web and Smartphone client, they must be assigned to the 'Premium' or 'Platinum' service tier within the Customer Support Tool (CST)
 - Steps to assign consumer tier
 - Login to WebUI as cstfull administrative user
 - Click Customer Care then Find Customer
 - Enter data to search for desired customer then click on customer ld number
 - Select 'Service Package' on left side of screen



 Choose the desired Service Package tier from the dropdown list. The default tier for MBanking consumers is 'Basic', which only provides access to Mobileweb login.

Smartphone Mobiliser Client

The Smartphone Mobiliser clients for the various mobile devices are packaged as source code and require compilation after customer customization has been performed to the source code. Customization to the source code is not required for the source code to compile successfully, but the client will contain default SAP branding.

The source code for all devices is located at {SMARTPHONE_HOME}/client

Provisioning the finalized application after development is usually done through the official distribution marketplace for each mobile platform:

- iPhone, iPad -App Store
- BlackBerry BlackBerry App World
- Android Android Market, Google Play Store

Follow the instructions and policy for each of these distribution channels for provisioning your application through that specific channel. More information can be found in *Developer Guide: Smartphone Mobiliser Applications*:

http://infocenter.sybase.com/help/index.jsp?topic=/com.sybase.infocenter.dc01866.0510/html/title.htm

Security Settings: First Installation Checklist

There are a couple of pre-configured values that you want to change on a fresh install for security reasons. For some of these steps, please consult the description above on the details how an where to change things. The system is installed with an invalid password for the user "mobiliser". It is required to set a new password for this user and to also configure the password in the preferences (see below).

- 1. Change the master password for configuration file encryption in ./conf/system.properties. This step is optional and is only required if password encryption is needed in Mobiliser Platform configuration.
- 2. Update configuration property files. The Vanilla distribution comes with only database passwords preencrypted, change them according to your DB password, and use the newly configured master password. The two files holding database passwords are:
 - com.sybase365.mobiliser.framework.persistence.jdbc.
bonecp/c3p0>.pool.properties
 - com.sybase365.mobiliser.util.report.crystalreports.properties.

Note for ASE 15.7 Installations only:

t

- Uncomment the following lines in the com.sybase365.mobiliser.framework.event.scheduler.quartz.properties file
 - * #jobStore.selectWithLockSQL=SELECT * FROM {0}LOCKS WHERE LOCK_NAME = ? FOR UPDATE
 - * #jobStore.lockHandlerClass=
- Uncomment the following line in the com.sybase365.mobiliser.framework.persistence.hibernate.sessionfactory.properties file

*#hibernate.dialect=com.sybase365.mobiliser.framework.persistence.hibernate.ase.MobiliserSybase157Dialec

- 3. Change the passwords in MOB_CUSTOMER_CREDENTIALS for these preconfigured users:
 - [REQUIRED] #100: mobiliser (Internal Mobiliser user for service calls from Web UI)
 - #101: usermgr (User Manager portal login)
 - #102: cstfull (CST Agent portal login)
 - #103: selfcare Selfcare and Signup
 - #104: opsmgr (Operations Manager portal login)
 - #105: notifmgr (Notification Manager portal login)
 - #106: sysmgr (System Manager Felix Web Console login)
 - #203: Headquarter (Money Headquarter portal login)

If you choose not to update the passwords for all users, with the exception of "mobiliser", the default password is 'secret' and you will be asked to change the password upon first login to the Web UI.

- 4. Set a new preferences master password in the Web UI context.xml as well as the container property file (you may opt to store this password encrypted itself in the property file for local access). Please refer to the <u>Encryption in Mobiliser preferences</u> section and reference the JNDI entry to perform this step. This step is REQUIRED if preferences hashes are created with any key that differs from the default "paybox".
- 5. Update preferences configuration which hold 'mobiliser' user password (remember to use your new preferences master key for encryption. This step can be skipped if the database was updated with the scripts specified in the <u>Creating required Database Hash Values and required Database Updates (for preferences)</u> section. The Vanilla installation has these two configuration nodes; in order to reach these nodes you will need to log into the webUI as the opsmgr user, and select 'Preferences' on the left side of the scrren. Update the 2 preference keys 'mobiliser.password' located in the mobr5.mob_preferences table (str_name column):
 - /presentationlayer/system/com/sybase365/mobiliser/web/util/Configuration/
 - /presentationlayer/system/com/sybase365/mobiliser/web/util/DynamicServiceConfiguration/

- 6. Create a new pair of keystores, place the public keystore in the Web portal's WEB-INF/classes and the private keystore in the Mobiliser Platform container's ./conf/keys. Update the preferences configuration for the new keystore:
 - Node: /presentationlayer/system/com/sybase365/mobiliser/web/util/Configuration/
 - Property: bankAccKeyAlias the key alias for the public key to be used for bank account encryption; default: mobiliser_bank
 - Property: creditCardKeyAlias the key alias for the public key to be used for card number encryption; default: mobiliser card
 - o Property: keyStorePw the password for the public key store
 - Property: publicKeyStore the public key store's name; default: mobiliser_pub.jks
 - Node:

/businesslayer/com/sybase365/mobiliser/money/businesslogic/payment/handlers/card/impl/DummyCardPaymentHandler/

- Property: key.store the private key store's name; default: \${mobiliser.home}/conf/keys/mobiliser.iks
- Property: key.store.password the private key store's password
- Property: key.alias the alias for the private key to be used for card decryption; default: mobiliser_card
- o Property: key.password the private key password
- Node:

/businesslayer/com/sybase365/mobiliser/mbanking/businesslogic/openbank/api/OpenBankConfiguration/

- o Property: key.alias the private key to be used for bank decryption; default: mobiliser_bank
- o Property: key.password the private key password
- Property: key.store the private key store's name; default: \${mobiliser.home}/conf/keys/mobiliser.jks
- o Property: key.store.password the private key store's password
- 7. If Mobileweb and/or Smartphone access is necessary for your Mobiliser Platform installation please follow the steps provided in the <u>Mobileweb & Smartphone Client Installation/Configuration</u> section.

System Hardening

As stated above, there are certain configuration files on the file system that contain sensitive information (such as keys used for encryption for example). Access to those files cannot be monitored or controlled from the Mobiliser Platform application and are therefore subject to OS level system hardening. Access must be limited to the user who is used to run the respective server and all read and write access should be logged. The relevant files and directories are:

- {MOBILISER_HOME}/conf/
- {TOMCAT_HOME}/conf/

The user used for starting the servers (user sybase) does not require any elevated privileges (e.g. super user, sudoers list).

Web / Jettv

You can configure the HTTP Port and other settings regarding the build in Jetty HTTP server in the file

- {MOBILISER_HOME}/conf/jetty.xml

You can also configure SSL (keystore) and various other settings (DoS / QoS filters). Please refer to

- http://wiki.eclipse.org/Jetty/Reference/jetty.xml_syntax
- http://wiki.eclipse.org/Jetty/Howto/Configure_SSL

Logging

Logging is configured in

- {MOBILISER_HOME}/conf/org.ops4j.pax.logging.properties

It is a standard log4j configuration file. For details on configuration please refer to:

- <u>http://logging.apache.org/log4j/1.2/manual.html</u>

Mobiliser Platform has its own log appender. This has two changes to the default daily rolling file appender:

- The context name (last part of the URL when a service is called) is added to the name of the log file
- The "conversationId" which is part of each MobiliserRequest is included in each line of the log file that deals with handling the corresponding request

To enable request / response tracing, update the following values:

- log4j.logger.com.sybase365.mobiliser.framework.service.jsonaudit.JsonAuditManager.log=TRACE, JSON
- log4j.additivity.com.sybase365.mobiliser.framework.service.jsonaudit.JsonAuditManager.log=true

It will log all requests and responses in JSON still into the file json.log (configurable) independently of the original protocol used (SOAP, plain XML, JSON). Sensitive information (PINs, passwords, etc) is masked.

Database Configuration

The database coordinates must be configured in two separate files (one of them is only used for the reporting framework):

- {MOBILISER_HOME}/conf/cfgbackup
 - o com.sybase365.mobiliser.framework.persistence.jdbc.bonecp.pool.properties
 - o com.sybase365.mobiliser.util.report.crystalreports.properties

In both files you need to make sure that the following parameters are set correct:

- jdbcUrl=jdbc:oracle:thin:@localhost:1521:orcl (Oracle example, may vary slightly for DB2 and ASE)
- username=mobr5
- password={enc}nsoVN/2Kv4askDeZiY+DH8KYDseo0Jd5C8CJNIKpGlA=

Refer to the previous section to learn how to encrypt passwords (and other configuration data).

The other parameters can influence the performance of the system.

The parameters you might want to check are:

- maxConnectionsPerPartition=5
- partitionCount=2

The product of these two values is the maximum number of parallel connections to the database. All other parameters should only be changed if you know exactly what you are doing.

Virus Protection

SAP NetWeaver VCA

Mobiliser Platform 5.1 introduces the SAP NetWeaver Virus Scan Adapter that scans all files upload to the mobiliser platform via Web services. The Virus Scan Adaptor uses plug in to connect to various virus scan engines that are used to scan the binary data. Please find details here:

- http://help.sap.com/saphelp_nw04/helpdata/EN/ca/7cb340be761b07e10000000a155106/frameset.htm

Installation

- 1. Install/copy the NetWeaver Virus Scan adapter for your Virus Scanner. This is provided by most Virus Scan vendors.
- 2. The NW-VSI integration bundle comes with a graphical configuration and test GUI. This is part of the vsi bundle
 - \{\\$MOBILISER_HOME\}\/bundles\/07-frameworks\/com.sap.security.vsi\{\}\/version\}.jar.
- 3. Start the gui:
 - \$>java -jar \$MOBILISER_HOME/bundles/07-frameworks/com.sap.security.vsi\${version}.jar
 - > Test the connection with the EICAR test pattern and mark the provides as default provider. The mobiliser engine will always use the default provider only.
- 4. Open the mobiliser configuration file:
 - \${mobiliser_home}/conf/cfgbackup/com.sybase365.mobiliser.framework.vsi.properties and vsi.properties
 - Copy all lines from the vsi.properties file and replace the similar ones in the mobiliser configuration file.
- 5. Restart the mobiliser bundle (or the complete container) and examine the mobiliser.log file. Please make sure that there is no WARN entry like:

2012-08-28 08:22:10,768 [aims-init-10] WARN com.sybase365.mobiliser.framework.vscan.impl.VScanImpl - Cannot initialize
Virus Scan Service. The following service exception occured: Virus scan provider VSA_DEFAULT does not exist.
2012-08-28 08:22:10,890 [aims-init-10] INFO com.sybase365.mobiliser.framework.vscan.impl.VScanImpl - No virus scan will be performed

Clam AV

One widely used virus scan engine on Unix systems is ClamAV and you can use the ClamSAP library to connect the Virus Scan Adapter with the ClamAV engine. This document lists the mandatory steps to install and configure the mobiliser 5.1 virus scan adapter with ClamAV on a Linux Server.

Installation

- 1. The mobiliser 5.1 virus scan adapter with ClamAV requires 3 packages:
 - a. ClamAV virus scan engine
 - b. ClamAV development package
 - c. libclamsap
- 2. The first two packages are usually available via the Linux distributor, while libclamsap may not. But you can still download the library from http://sourceforge.net/projects/clamsap/files/
- 3. Use the libclamsap when the mobiliser can access a local clamav engine.

Configure VSI

- The configuration of the clamav adapter is straight forward. Please enable the default adapter and edit the adaptor path to point to the libclamsap shared library.:
 - com.sybase365.mobiliser.framework.vsi.properties (...) vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT=VSA_DEFAULT vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.Active=true vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.AdapterPath=/home/sybase/libclamsap.so vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.Description=DEFAULT PROVIDER $vsi.provider. Virus_Scan_Adapter. Adapters. VSA_DEFAULT. Group=DEFAULT$ vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.PoolInstanceTimeOut=3600 vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.PoolMaxInstances=50 vsi.provider.Virus_Scan_Adapter.Adapters.VSA_DEFAULT.ReInitTime=0 (...)
- 2. Restart the mobiliser instance and examine the log. The adapter is loaded successfully when you see the following log lines in the mobiliser.log:

(...)
2012-09-06 08:43:48,747 [aims-init-15] DEBUG com.sybase365.mobiliser.framework.vscan.scanner.impl.VScanlmpl - VSI Virus Scan Service initialization was successfull

Proxy Setup

As described in a previous section, it is strongly recommended to not place the Mobiliser Core in the DMZ. It is best to use a proxy in the DMZ to provide restricted access to the services provided by Mobiliser Core. This can either be done by using a standard reverse proxy or by using the Mobiliser Validating Proxy.

Reverse Proxy

The example here is provided for an Apache with proxy modules installed. The full installation and configuration of the Apache server is not covered in this document.

```
<Proxy *>
         Order deny, allow
         Allow from all
</Proxy>
```

ProxvPass /mobiliser http://localhost:8080/mobiliser ProxyPassReverse /mobiliser http://localhost:8080/mobiliser

ProxyPass /system http://localhost:8080/system ProxyPassReverse /system http://localhost:8080/system

Validating Proxy

The validating proxy is a specially assembled OSGi container that contains a subset of the Mobiliser Core bundles. It is provided as a zip file that must be extracted into an appropriate directory:

/opt/Sybase/mobiliser_proxy

The Validating Proxy contains the same Jetty specific configuration options as the Mobiliser Core container, which are documented in a previous section. In addition there is a configuration file which contains the URL for the Mobiliser Core to which the requests are forwarded (after successful validation). This file is located under:


{MOBILISER_HOME}/conf/cfqbackup/ com.sybase365.mobiliser.framework.service.proxy.properties.

UI Setup

UI Setup - Tomcat

The UI will be deployed on Tomcat (6.0.33) or later. The UI provides access to End User and Administrative Portals. As shown in the deployment diagram in a previous section, there is usually a public portal and an internal portal providing access to different functions for different types of users. The internal portal contains, for example functions to make modifications to vital system configuration and to monitor the server. This is also protected by privileges and roles, but should not be exposed to the public Internet anyway. The source code for both portals is usually identical. They only differ by a configuration file located in the WEB-INF/ folder of the jar file. In standard projects, two different WAR files should be provided that have the correct configuration file included. The public portal is to be installed on the DMZ, the internal portal on the application server tier. Otherwise, the structure of Tomcat and the WAR file is identical.





- 1. Copy the Tomcat Container from {MOBILISER_INSTALLATION}/applications/apache/apache-tomcat-6.0.33 to /opt/sybase to create the {TOMCAT_HOME} directory
 - a. Note: It is useful to create a symbolic link 'tomcat' to the {TOMCAT_HOME} directory
 - Note: All other necessary application directories are generated automatically on start up by Tomcat
- 2. Copy the UI application 'com.sybase365.mobiliser.ui.web.application-5.1.war' to the {TOMCAT_HOME}/webapps directory and rename it to ROOT.war

Initialization and System Check (Mobiliser 5.1 Core)

Start Server and UI


1. Execute the following start script {MOBILISER_HOME}/bin/startup.sh to start the Server (note: shutdown.sh and other admin scripts are also located in this directory).

```
🚅 mwalker@r5dev04:/opt/sybase/RELEASE/applications/oracle/com.sybase365.mobiliser.dist.oracle-5.0.0.RELEASE1/bin
mwalker@r5dev04 bin]$ clear
mwalker@r5dev04 bin]$ ls -1
otal 128
-rwxr-xr-x 1 sybase sybase 1373 Mar 16 14:01 create_jdbc_bundle.sh
-rwxr-xr-x 1 sybase sybase 2614 Mar 16 14:01 encrypt_pref.sh
-rw-r--r-- 1 sybase sybase 18767 Mar 16 14:01 mobiliser.bat
-rw-r--r-- 1 sybase sybase 6 Apr 7 01:31 mobiliser.pid
-rwxr-xr-x 1 sybase sybase 22338 Mar 16 14:01 mobiliser.sh
-rwxr-xr-x 1 sybase sybase 3227 Mar 16 14:01 r5 continuous.sh
-rwxr-xr-x 1 sybase sybase 2659 Mar 16 14:01 r5 continuous_tomcat.sh
rw-r--r-- 1 sybase sybase
                                                  361 Mar 16 14:01 replace.bat
                                                4096 Apr 4 21:11 reports
3506 Mar 16 14:01 setclasspath.bat
-rw-r--r-- 1 sybase sybase
rwxr-xr-x 1 sybase sybase 3635 Mar 16 14:01 setclasspath.sh
-rw-r--r- 1 sybase sybase 975 Mar 16 14:01 setenv.bat
-rwxr-xr-x 1 sybase sybase 2091 Mar 16 14:01 setenv.sh
-rwxr-xr-x 1 sybase sybase 10510 Mar 16 14:01 setup_m5_db.sh
-rw-r--r- 1 sybase sybase 2386 Mar 16 14:01 shutdown.bat
-rwxr-xr-x 1 sybase sybase 2173 Mar 16 14:01 shutdown.sh
                                                2382 Mar 16 14:01 startup.bat
2171 Mar 16 14:01 startup.sh
rw-r--r-- 1 sybase sybase
rwxr-xr-x 1 sybase sybase
rwxr-xr-x 1 sybase sybase 4626 Mar 16 14:01 upgrademobiliser.sh
rwxr-xr-x 1 sybase sybase 2807 Mar 16 14:01 upgrade_prefs.sh
 mwalker@r5dev04 bin]$
```

Monitor the Server log at {MOBILISER_HOME}/logs/felix.log until the log specifies that "AutoDeploy finished".

```
🖁 mwalker@r5dev04:/opt/sybase/RELEASE/applications/oracle/com.sybase365.mobiliser.dist.oracle-5.0.0.RELEASE1/logs
Jelcome to Apache Felix Gogo
2012-04-07 01:31:44.434:INFO:oejs.Server:jetty-7.x.y-SNAPSHOT
le.internal.servlet.OsgiManagerHttpContext@7d6ac92e}
012-04-07 01:31:46.185:INFO:oejsh.ContextHandler:stopped HttpServiceContext(httpContext=org.apache.felix.webconsc
le.internal.servlet.OsgiManagerHttpContext@7d6ac92e}
2012-04-07 01:31:46.535:INFO:oejsh.ContextHandler:started HttpServiceContext(httpContext=org.apache.felix.webconsc
le.internal.servlet.OsgiManagerHttpContext@2c4dd413}
Persistence bundle starting...
ersistence bundle started.
2012-04-07 01:31:55.470:INFO:oejsh.ContextHandler:started HttpServiceContext(httpContext=DefaultHttpContext(bundle
com.sybase365.mobiliser.framework.gateway.httpservice [308]))
2012-04-07 01:31:55.679:INFO:/:Initializing Spring FrameworkServlet 'Mobiliser'
012-04-07 01:31:56.794:INFO:oejsh.ContextHandler.started HttpServiceContext(httpContext=DefaultHttpContext(bundle
2012-04-07 01:33:03.181:INFO:oejsh.ContextHandler:started HttpServiceContext(httpContext=org.ops4j.pax.web.extende
:.war.internal.WebAppWebContainerContext83ddb7e6d)
2012-04-07 01:33:03.907:INFO:oejsh.ContextHandler:started HttpServiceContext(httpContext=DefaultHttpContext(bundle
com.sybase365.mobiliser.util.management.logic [1]}}
   Deploy finished
                                                                                                                           27% ▼
```

3. Verify that the Mobiliser Platform console has initialized successfully by viewing the customer WSDL via Web browser (http://localhost:8080/mobiliser/customer/Customer.wsdl).



4. Execute the following startup script {TOMCAT_HOME}/bin/startup.sh to start the UI (note: shutdown.sh and other admin scripts are also located in this directory).


```
₫ mwalker@r5dev04:/opt/sybase/tomcat/bin
 mwalker@r5dev04 bin]$ ls -1
 otal 612
-rw-r--r-- 1 sybase sybase 22705 Aug 16 2011 bootstrap.jar
-rw-r--r-- 1 sybase sybase 11830 Aug 16 2011 catalina.bat
 rwxr-xr-x 1 sybase sybase
                                   17708 Aug 16 2011 catalina.sh
                                    2374 Aug 16
                                                    2011 catalina-tasks.xml
 rw-r--r-- 1 sybase sybase
 rw-r--r-- 1 sybase sybase 199623 Aug 16 2011
 rw-r--r-- 1 sybase sybase
                                    2108 Aug 16 2011 digest.bat
 rw-r--r-- 1 sybase sybase
                                    1689 Aug 16 2011 digest.sh
 rwxr-xr-x 1 sybase sybase
                                    4114 Aug 16 2011 setclasspath.sh
-rwxr-xr-x 1 sybase sybase
                                     694 Mar 13 00:01 setenv.sh
                                    2108 Aug 16 2011 shutdown.bat
 rw-r--r-- 1 sybase sybase
 rwxr-xr-x 1 sybase sybase
                                    1628 Aug 16 2011 shutdown.sh
-rwxr-xr-x 1 sybase sybase 2023 Aug 16 2011
-rw-r--r- 1 sybase sybase 26828 Aug 16 2011
-rw-r--r- 1 sybase sybase 241274 Aug 16 2011
                                  2023 Aug 16 2011 startup.sh
26828 Aug 16 2011 tomcat-juli.jar
 rw-r--r-- 1 sybase sybase
                                    3479 Aug 16 2011 tool-wrapper.bat
 rwxr-xr-x 1 sybase sybase
rw-r--r-- 1 sybase sybase
                                    2113 Aug 16 2011 version.bat
1632 Aug 16 2011 version.sh
 rwxr-xr-x 1 sybase sybase
[mwalker@r5dev04 bin]$
```

5. Verify that the Tomcat Web UI application has initialized successfully by viewing it in Web browser (http://localhost:8082).




Preferences Configuration


1. Log into the UI (Operations Dashboard) as the opsmgr user (opsmgr: secret). You will be prompted to change the password for the user before you are logged in.



2. Select Preferences on the left side of the screen, expand to the following path /presentationlayer/com/sybase365/mobiliser/util/web/util and select the Configuration file.




- Navigate to the Key named publicKeyStore (Page 3) and edit the value to "{MOBILISER_HOME}/keys/mobiliser_pub.jks"
 - a. This will allow Mobiliser Platform to use the test keystore that comes with the package.




4. Click Refresh to assure that preferences changes were committed.

SMPP Configuration (Optional)

- 1. Log into the UI (Operations Dashboard) as the opsmgr user
- 2. Select Preferences on the left side of the screen, expand to the following path com/sybase365/mobiliser/util/messaging/channelmanager/engine/impl/ChannelInstantiator/ and select the smppchannel1 node file.



3. Navigate through all of the node preferences, and enter all relevant SMPP account information.




4. Click Refresh to assure that preferences changes were committed


SMTP Configuration (Optional)

Log into the UI (Operations Dashboard) as the opsmgr user


1. Select Preferences on the left side of the screen, the select "Add a Preference Node"



- 2. Select businesslayer in the Application drop down list and enter the following path in the Full Node Path field:
 - com/sybase365/mobiliser/util/messaging/channelmanager/engine/impl/ChannelInstantiator/smtpchannel1, then click Save.
- 3. Navigate to the newly created preference node in the preference tree, and double click on the smtpchannel1 node. Then select "Add a Preference"



- 4. In the Key field enter _channelType, in the Value field enter email, in the Type field enter java.lang.String. Click Save.
- 5. Repeat previous step to enter the following values
 - a. Key: channeled, Value: default, Type: java.lang.String
 - b. Key: mail.host, Value: localhost, Type: java.lang.String
 - c. Key: mail.port, Value: 25, Type: java.lang.String
 - d. Key: mail.protocol, Value: smtp, Type: java.lang.String
 - e. Key: mail.sign, Value: false, Type: java.lang.String
 - f. Key: sign.hashAlgorithm, Value: -1, Type: java.lang.String
 - g. Key: sign.keyld, Value: -1, Type: java.lang.String
- 6. Click Refresh to assure that preferences changes were committed



Default (Administrative) Web UI Accounts

The following user accounts are the administrative accounts that are created after a Mobiliser Platform Installation. Note: After the first successful attempt to log in with these accounts you will be prompted to change the password for the account before proceeding

Customer Support Accounts

Customer Support Tool – cstfull: secret Manager User Accounts – usermgr: secret Manage Notifications and Alerts – notifmgr:secret

Distribution Partner Portal Account

Create and Manage Merchants - Headquarter:secret

Operations Dashboard Admin Account

View and Manage System Configuration - opsmgr:secret

System Console

This console is used to monitor all of the functions of the Mobiliser Platform container

- 1. Default url = http://<localhost>:8080/system/console
- 2. Default Account sysmgr:secret
 - Note: This password may have been updated on first attempt to log into the Operations Dashboard.

Accessing Mobiliser Platform through JMX

Mobiliser Platform exposes various information through JMX. Local access directly connecting to the Java process is unlimited (per JMX specification), i.e., you can start jconsole (or any other JMX front-end) and connect to the



running process. In addition, Mobiliser Platform also exposes JMX through RMI. The access details are configured in the com.sybase365.mobiliser.framework.gateway.security.authentication.jmx.properties file, located in ./conf/cfgbackup. When changing the configured port, make sure to adjust both properties, jmxPort as well as serviceUrl.

Any remote access is secured with username and password, which is validated using the standard Mobiliser Platform authentication mechanisms. The property file also allows configuration of a required access role. Per default, the sysmgr user has the pre-configured JMX_ACCESS role.

Exposed Information

Mobiliser Platform exposes standard JMX statistics and operations from the embedded Jetty servlet container ehcache, which provides the underlying caching implementation for Hibernate the database connection pool implementation BoneCP. In addition there are a couple of Mobiliser Platform specific MBeans available.

- Framework components expose statistics and configuration:
 - com.sybase365.mobiliser.framework.event: provides statistics and details on the event processing framework and registered handlers
 - o com.sybase365.mobiliser.framework.service.audit.jmx: basic request auditor, exposing very high-level statistics on processed Mobiliser service calls
 - o com.sybase365.mobiliser.util.messaging.channelmanager: statistics on channels and messages
 - o com.sybase365.mobiliser.util.prefs: read and write access to preferences as well as basic preference service configuration
- Brokers expose the list of available handlers:
 - o com.sybase365.mobiliser.mbanking.businesslogic.openbank.impl
 - o com.sybase365.mobiliser.money.businesslogic.authentication.impl
 - o com.sybase365.mobiliser.money.businesslogic.billpayment.impl
 - o com.sybase365.mobiliser.money.businesslogic.bulkprocessing.impl
 - o com.sybase365.mobiliser.money.businesslogic.payment.impl
 - com.sybase365.mobiliser.money.businesslogic.transaction.flow.impl
- Hibernate DAOs allow changing the behavior on query caching and ordering:
 - o com.sybase365.mobiliser.mbanking.persistence.dao.hibernate
 - o com.sybase365.mobiliser.money
 - o com.sybase365.mobiliser.money.persistence.hibernate.dao.customer
 - o com.sybase365.mobiliser.money.persistence.hibernate.dao.job
 - o com.sybase365.mobiliser.money.persistence.hibernate.dao.pi
 - o com.sybase365.mobiliser.money.persistence.hibernate.dao.system
 - o com.sybase365.mobiliser.money.persistence.hibernate.dao.transaction
 - o com.sybase365.mobiliser.util.alerts.persistence.dao.hibernate
 - o com.sybase365.mobiliser.util.messaging.dao.impl.hibernate
 - o com.sybase365.mobiliser.util.prefs.persistence.dao.hibernate

Data Archiving, Retention, and Deletion

In the current release 5.1 (or older), Mobiliser Platform does not support data archiving out of the box, neither do we have data retention and deletion policies implemented. Hence, it is a system engineer's task to set up means using default database technology implementing any desired procedures.

Data Archiving

Transactional data can be moved out of the online transaction database safely. We do not recommend moving out customer data since this information is required in the online transaction database to ensure referential integrity. This should not be a problem since the portion of customer data should be small compared to the amount of transactional data in a system. When archiving data out of the online database, obviously this data will not be visible through the standard Mobiliser Platform user interfaces anymore.

When moving out transactional data, please be aware of foreign key constraints on transaction data; make sure to move the full information belonging to a transaction.

A Mobiliser Platform transaction stores data in these tables:

- MOB TXNS
- > MOB SUB TXNS.ID TXN->MOB TXNS.ID TXN
- ➤ MOB_TXN_ATTRIBUTES.ID_TXN->MOB_TXNS.ID_TXN
- ➤ MOB_FEES.ID_SUB_TXN->MOB_SUB_TXNS.ID_SUB_TXN

In case the transaction is an invoice payment, the invoice must be moved as well:

- ➤ MOB_INVOICES
- ➤ MOB_INV_TXNS.ID_TXN->MOB_TXNS.ID_TXN
- ➤ MOB INV TXNS.ID INVOICE->MOB INVOICES.ID INVOICE
- ➤ MOB_INV_ATTRIBUTES.ID_INVOICE->MOB_INVOICES.ID_INVOICE

Additionally there is some audit/logging data created in the following tables:

- MOB HISTORY tracks changes to individual columns in the database.
- MOB AUDIT LOGS each remote service call is tracked in this table.
- MOB_TRACEABLE_REQUESTS stores data for non-repudiation and response dehydration. Usually not more than 24 hours of data is required in this table.

Data Retention and Deletion

Mobiliser Platform does not have automated procedures to implement data retention and deletion policies. Hence, it must be part of the system setup to install jobs (or manually perform tasks) to delete data after the retention period is expired. Since the Mobiliser database holds many referential integrity constraints binding a customer record to transactions and other entities, we recommend to scramble customer data instead of physically deleting it, i.e. any personally identifiable information should be overwritten with random text (or a specific string ex. –DELETED--) in order to delete the customer record from the system.

Customer data is stored in these tables (customization project may have introduced further tables holding PII):

- ➤ MOB_CUSTOMERS
- MOB CUSTOMERS IDENTIFICATIONS.ID CUSTOMER->MOB CUSTOMER.ID CUSTOMER
- ➤ MOB_CUSTOMERS_CREDENTIALS.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- ➤ MOB_CUSTOMERS_IDENTITIES.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- ➤ MOB_CUSTOMERS_ATTRIBUTES.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- > MOB ADDRESSES.ID CUSTOMER->MOB CUSTOMER.ID CUSTOMER
- ➤ MOB_ATTACHMENTS.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- ➤ MOB_NOTES.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- ➤ MOB_PIS.ID_CUSTOMER->MOB_CUSTOMER.ID_CUSTOMER
- ➤ MOB_PIS.ID_PI<-MOB_WALLET->MOB_CUSTOMER.ID_CUSTOMER
- MOB_SVA.ID_PI->MOB_PIS.ID_PI
- ➤ MOB_CREDIT_CARDS.ID_PI->MOB_PIS.ID_PI
- MOB_BANK_ACCOUNTS.ID_PI->MOB_PIS.ID_PI
- ➤ MOB_EXTERNAL_ACCOUNTS.ID_PI->MOB_PIS.ID_PI

Deletion Script

Execute this script to obfuscate all PIs of a customer. Use with care! Also all payment instruments related information is removed. Further processing of financial transactions will not be possible.

```
- delete information about bank accounts
UPDATE MOB_BANK_ACCOUNTS SET STR_NAME = '###', STR_NAME_BANK = '###', STR_CITY_BANK = '###', STR_INSTITUTION_CODE = '###', STR_BRANCH_CODE = '###', STR_ACCOUNT_NUMBER = '###', STR_DISPLAY_NUMBER = '###' WHERE
ID_PI in (SELECT ID_PI FROM MOB_PIS WHERE ID_CUSTOMER = ?);
  -- delete information about "other" financial accounts
UPDATE MOB_EXTERNAL_ACCOUNTS SET STR_ID1 = '###', STR_ID2 = '###', STR_ID3 = '###', STR_ID4 = '###', STR_ID5 = '###', STR_ID5
ID_PI in (SELECT ID_PI FROM MOB_PIS WHERE ID_CUSTOMER = ?);
  -- delete credit card information
 UPDATE MOB_CREDIT_CARDS SET STR_CARD_NUMBER = "###", STR_CARD_HOLDER_NAME = "###", STR_DISPLAY_NUMBER = "###" WHERE
ID_PI in (SELECT ID_PI FROM MOB_PIS WHERE ID_CUSTOMER = ?);
  -- delete names of accounts
 UPDATE MOB_WALLET SET STR_ALIAS = '###' WHERE ID_CUSTOMER = ?;
-- mark all accounts as inactive

UPDATE MOB_PIS SET BOL_IS_ACTIVE = 'N' WHERE ID_CUSTOMER = ?;
 -- delete all identifications, such as mobile phone number and make them inactive
UPDATE MOB_CUSTOMERS_IDENTIFICATIONS SET STR_IDENTIFICATION = "###", BOL_IS_ACTIVE = 'N' WHERE ID_CUSTOMER = ?;
  -- delete all passwords and PINs and make them inactive
UPDATE MOB_CUSTOMERS_CREDENTIALS SET STR_CREDENTIAL = '###', BOL_IS_ACTIVE = 'N' WHERE ID_CUSTOMER = ?;
-- delete all identity (e.g. passport) information

UPDATE MOB_CUSTOMERS_IDENTITIES SET STR_IDENTITY = '###', STR_ISSUE_PLACE = '###', STR_ISSUER = '###', BOL_IS_ACTIVE = 'N' WHERE ID_CUSTOMER = ?;
     delete all general purpose attributes
UPDATE MOB_CUSTOMERS_ATTRIBUTES SET STR_VALUE = '###' WHERE ID_CUSTOMER = ?;
  -- delete all binary attachments
UPDATE MOB_ATTACHMENTS SET STR_NAME = '###', BIN_CONTENT = null WHERE ID_CUSTOMER = ?;
 -- delete all notes (system generated or manually entered)
UPDATE MOB_NOTES SET STR_SUBJECT = '###', STR_TEXT = '###' WHERE ID_CUSTOMER = ?;
  -- mark customer as inactive
 UPDATE MOB CUSTOMERS SET STR DISPLAY NAME = '###', STR SECURITY QUESTION = '###', STR SECURITY ANSWER = '###', STR REFERRAL CODE = '###', BOL IS ACTIVE = 'N',
DAT_DATE_OF_BIRTH = null WHERE ID_CUSTOMER = ?;
 -- delete all address information
 UPDATE MOB_ADDRESSES SET STR_FIRST_NAME = '###', STR_MIDDLE_NAME = '###', STR_LAST_NAME = '###', STR_TITLE = '###', STR_COMPANY1 = '###', STR_COMPANY2 = '###', STR_TITLE = '###', STR_TITLE = '###', STR_COMPANY1 = '###', STR_COMPANY2 = '###', STR_TITLE = '###',
STR_COMPANY_SHORTNAME = "###", STR_POSITION = "###", STR_STREET1 = "###", STR_STREET2 = "###", STR_HOUSE_NUMBER = "###", STR_ZIP = "###", STR_CITY = "###", STR_STREET = "###", STR_PHONE1 = "###", STR_PHONE1 = "###", STR_PHONE2 = "###", STR_FAX = "###", STR_EMAIL = "###", STR_URL = "###", STR_NAME_ADDRESS = "###" WHERE ID_CUSTOMER = ?,
  -- delete all information regarding change history
 UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT = ?;
UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT in (SELECT ID_PI FROM MOB_PIS WHERE ID_CUSTOMER = ?);
UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT in (SELECT ID_ADDRESS FROM MOB_ADDRESSES WHERE ID_CUSTOMER = ?);
 UPDATE MOB_HISTORY SET STR_OLD_VALUE = "###", STR_NEW_VALUE = "###" WHERE ID_OBJECT In (SELECT ID_IDENTITY FROM MOB_CUSTOMERS_IDENTITIES WHERE ID_CUSTOMER = ?);
 UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT IN (SELECT ID_CUSTOMER_IDENTIFICATION FROM MOB_CUSTOMERS_IDENTIFICATIONS
 WHERE ID CUSTOMER = ?):
 UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT In (SELECT ID_CUSTOMER_CREDENTIAL FROM MOB_CUSTOMERS_CREDENTIALS WHERE
 UPDATE MOB_HISTORY SET STR_OLD_VALUE = '###', STR_NEW_VALUE = '###' WHERE ID_OBJECT In (SELECT ID_NOTE FROM MOB_NOTES WHERE ID_CUSTOMER = ?);
 -- commit all data
commit:
```

Auditing Information

All tables in the Mobiliser database schema have 4 columns that track the date and user who created the record and the date and user of the last update to the record.

Table	Description
MOB_AUDIT_LOGS	Access to each service call in Mobiliser Platform is logged to the Database and to the log file. The service call is logged in this table. The name of the service, the ID of the caller, the return, and other relevant information are logged into this table. This applies to services related to customers but also to internal configurations that are accessible.
MOB_PREFERNCES_HISTORY	Changes to the configuration (Preferences) that is stored in the database is tracked additionally. This table contains previous entries along with the user who performed the update on the configuration.
MOB_HISTORY	Changes to customer and potentially other data is tracked in the table MOB_HISTORY. It contains the name of the field, the old and new value, the timestamp and the ID of the user who has done the change. This data is provided by database triggers on individual columns and is provided on an is-needed basis for each project.

Security Considerations

In case any services of the Mobiliser Core need to exposed to the public Internet (e.g. for consumption by Smartphone Mobiliser) it is essential that only a subset of the services offered by Mobiliser Platform are exposed on the Internet. The privilege and role based security concept of Mobiliser Platform only grants access to services for users on an as-needed basis but there is no need to expose all of the services on the Internet.

Services in Mobiliser Platform are always attached to a "context" that, among other things, defines the last section of the URL to address a specific service.

Exposing Web Service Endpoints Securely:

http://localhost:8080/mobiliser/customer - is the default context for generic customer related services.
http://localhost:8080/mobiliser/smartphone - is the default context for services to be consumed by Smartphone Mobiliser Platform.

Mobiliser Platform supports various transport protocols (on top of HTTP). The JSON services are exposed under a slightly different URL. The JSON variants to the two examples mentioned above are:

http://localhost:8080/mobiliser/rest/customer

http://localhost:8080/mobiliser/rest/smartphone

So in most cases it is sufficient to expose the following URLs from the Mobiliser Core

http://localhost:8080/mobiliser/smartphone


http://localhost:8080/mobiliser/rest/smartphone

(Some customized projects might use other/additional URLs).

There are two alternatives to grant access to the services.

Standard Reverse Proxy

Any reverse proxy (e.g. Apache) can be used to accept incoming requests from the Internet in the DMZ and to forward them to the Mobiliser Core running on the application server tier.



Additionally to shielding direct access to the Mobiliser Core, the Apache can also be used to provide access to the HTML5 version of Smartphone Mobiliser or any other HTML5 application. Because of the "Same origin policy" (http://en.wikipedia.org/wiki/Same_origin_policy) the HTML files and the AJAX services must be provided by the same server (hostname + port).

The Reverse Proxy can also be used for the SSL termination.

In order for the Mobiliser Platform 5.1 platform to be deployed in the Standard Reverse Proxy model, configuration changes need to be made on the Apache Web UI container (located on the DMZ layer) and one of the database preferences (located in the Persistence layer).

Updating the WebUI container:

- Open the context.xml file in the {TOMCAT_HOME}/conf/ directory of the DMZ system.
- Update the value in the context.xml file to point to the {MOBILISER_HOME} instance on the App Server.

Where "my_app_server" is your node where the mobiliser container is installed

Updating the database preferences

- Connect to the database with your choice of application that can run SQL/PL-SQL against the database
- Run the following SQL scripts against the database to update required preferences (syntax may vary slightly depending on database platform, the examples provided are for ASE 15.7 databases)

Where "my_app_server" is your node where the mobiliser container is installed


Validating Proxy

Alternatively to a Reverse Proxy the Mobiliser Validating Proxy can be used.

In addition to restricting access to certain services, the validating proxy will make sure that the incoming request corresponds to the contract (XSD) defined for the appropriate service. This check can be applied on all supported protocols (SOAP, plain XML, JSON).

The validating proxy contains a subset of the bundles from the original Mobiliser Core. It only contains the contract definitions (XSD) and the context and endpoint information.

When the request was validated successfully it is forwarded to the Mobiliser Platform in its original format.




If there is also an HTML5 client in the mix, an additional Apache with reverse proxy (or similar HTTP server) needs to be added to support the Same Origin Policy.

The validating proxy provides an additional security layer.


End-to-End Test (Mobiliser Platform 5.1 Core)

Add Customer


1. The consumer signup process begins at the Web UI login screen. Click on the link that says "Consumer Signup."




2. Click Continue to move on to the Consumer Signup form for new Mobiliser Platform customers




3. Fill in all required information fields, accept Terms and Conditions, and confirm the CAPTCHA image. Click Continue.




4. At the account summary page click Continue again



5. At the final part of the consumer signup, you will be asked for an OTP code to finalize the creation of the account.



- 6. Go to the Channel Manager console to find the OTP information:
 - a. <a href="http://<localhost>:8080/mobiliser/channelmgr/html?timeZone=Pacific/Auckland">http://<localhost>:8080/mobiliser/channelmgr/html?timeZone=Pacific/Auckland
 - b. If asked for credentials to enter page use the following; Mobiliser:secret



- 7. Enter OTP specified on the page and click Continue
- 8. You will receive a confirmation page specifying a successful consumer signup, click continue and you will be redirected to the Web UI login page again where you can log in with the newly created Mobiliser account

Operations Dashboard

Overview

This document summarizes the information available from the Mobiliser Platform 5.1 container for managing and operating the Mobiliser 5.1 environment using the Operations Dashboard Web portal application and the interfaces of the Mobiliser Platform 5.1 server.

All information presented is presented as read-only and summarizes or visualizes information accessible through the JMX provided through Mobiliser Platform and the Java virtual machine.

This covers the Operations Dashboard pages for:

- System/Environment Information
- Mobiliser Requests Information
- Data Access Information
- Messaging/Channel Information
- Event Information
- Task Information
- Trackers


It also includes information on how to develop customized trackers for the Operations Dashboard and provides information on how other interfaces outside the Money Mobiliser Operations Dashboard Web Portal can access the same set of information through:

- Mobiliser Management SOAP/REST Interfaces
- JMX RMI

JVM/System Environment Pages


Summarizes the JVM and basic system environment the Mobiliser container is running in. Key information:

- Up time
- Total/Free Physical Memory & Committed Virtual Memory
- Total Swap/Free Swap



Mobiliser Requests Information


Allows display and selection of any or all request made into the Mobiliser Platform server.



Mobiliser Requests Statistics

Allows drill down into statistics on each request made into the Mobiliser Platform server.


- Total requests
- Requests succeeded/failed
- Average response time



Data Access Information

Reports on information made available from the database access and caching layer. (Is by default off and needs to be turned on/off manually due to extra load generated).


- Counts of sessions opened/closed
- Transactions (database).
- Max/Min request duration
- Query execution rate



Messaging/Channel Information

Reports statistics generated by the Mobiliser messaging services. Also shows information (contents encrypted of last 100 messages generated).


- Messages Sent/Received
- Messages failed to send



Event Information

Shows statistics generated by the Mobiliser event system. Events are internal actions that process independently of the originating. Allows drill down into Event Handler information and statistics.


- Internal physical event queue sizes
- Internal virtual queue sizes for each different registered event type



Event Handler Details

Allows drill down into Event Handler information and statistics.


- Active/Idle Threads for this event handler
- Maximum Active/Idle Threads allocated for this event handler
- Handler run statistics; last run at date/time, last fail at date/time.
- Events processed successfully/failed/total
- Average process time



Task Information

Shows statistics generated by the Mobiliser event system for tasks. Tasks are internal date/time scheduled actions. Allows drill down into Task Handler information and statistics.

- Schedule of tasks
- Status of task handlers




Task Details

Allows drill down into Task information and statistics.

Key information:

• Task fire (start) timings; last/next



Task Handler Details

Also, allows drill down into Task Handler information and statistics.

- Active/Idle Threads for this event handler
- Maximum Active/Idle Threads allocated for this event handler
- Handler run statistics; last run at date/time, last fail at date/time.
- Events processed successfully/failed/total
- Average process time




Trackers

Trackers provide a basic visualization of any JMX statistic-type attribute accessible from the Mobiliser JMX platform. (That includes any of the statistics shown above, plus other JMX attribute information available). Chart types are:


- Line
- Bar
- Gauge
- Candlestick

Sample trackers are provided to show visualization of:


• Total generated event count as a line chart



Memory Usage as a Bar Chart



Pre-Authorization of Transaction Request as a Gauge Chart



Customized Trackers

New trackers can be added using simple configuration of the Web portal application.

- Step 1: Specify the location of the data series for the tracker.
- Step 2: Specify the tracker type linking to the data series
- Step 3: Add to list of known trackers

./webapps/portal/WEB-INF/trackers-context.xml:

```
<!--
DASHBOARD TRACKERS
  -->
<bean id="loginReqCntDataSeries"</pre>
class="com.sybase365.mobiliser.web.dashboard.pages.trackers.beans.TrackerDataSeriesBea
 cproperty name="server" value="localhost:8080" />
  property name="objectName"
value="com.sybase365.mobiliser.framework.service.audit.jmx:product=IAuditManager,insta
nce=JmxAuditManager" />
  roperty name="attribute" value="TypeAuditStatistics" />
  cproperty name="keyName" value="requestType" />
  cproperty name="keyValue"
value="com.sybase365.mobiliser.money.contract.v5_0.customer.security.LoginCustomerRequ
est" />
  roperty name="valueName" value="successCount" />
 roperty name="numberOfDataPoints" value="10" />
 roperty name="dataSeriesDao" ref="trackersDataSeriesDao" />
</bean>
<br/>
<br/>
bean id="loginReqCntTracker"
class="com.sybase365.mobiliser.web.dashboard.pages.trackers.beans.TrackerBean" init-
method="init" destroy-method="destroy">
 cproperty name="name" value="Login Count" />
  cproperty name="type" ref="LINE" />
  roperty name="sampleInterval" value="30" />
  cproperty name="sampleIntervalTimeUnit" ref="SECONDS" />
  cproperty name="pointsToDisplay" value="10" />
  property name="dataSeries">
<util:list>
 <ref local="loginReqCntDataSeries" />
</util:list>
  </property>
</bean>
DASHBOARD TRACKERS DAO
<bean id="trackersDao"</pre>
class="com.sybase365.mobiliser.web.dashboard.pages.trackers.dao.impl.TrackersSpringDao
Impl">
cproperty name="trackers">
<util:list>
 <ref local="loginReqCntTracker" />
 </util:list>
 </property>
</bean>
```

Management SOAP/REST Interface

The JMX information presented by the Web Operations Dashboard is accessed through the Mobiliser Management endpoint.

This end point translates SOAP requests in to requests for local JMX platform object and attributes information, and sends it back as a SOAP response.

This interface can also be accessed via REST returning XML or JSON data. Example (from SOAP UI):

