IOWA STATE UNIVERSITY

Department of Electrical and Computer Engineering


Lecture 23: Swapping



Agenda


- Recap
- Multi-Level Page Tables (cont')
- Swapping

- Translation Lookaside Buffer (TLB)
 - Hardware cache for speeding up paging
 - A real TLB entry (MIPS)




Flag	Content
19-bit VPN	The rest reserved for the kernel.
24-bit PFN	Systems can support with up to 64GB of main memory($2^{24}*4KB$ pages).
Global bit(G)	Used for pages that are globally-shared among processes.
ASID	OS can use to distinguish between address spaces.
Coherence bit(C)	determine how a page is cached by the hardware.
Dirty bit(D)	marking when the page has been written.
Valid bit(V)	tells the hardware if there is a valid translation present in the entry.


Address translation with TLB & page table



- TLB may improve performance greatly
 - Effective Access Time (EAT)
 - effective time for accessing memory with TLB
 - TLB Hit ratio = α
 - percentage of times that a page number is found in the TLB
 - TLB hit: one memory access
 - TLB miss: two memory accesses
 - Consider α = 80%, 100ns for each memory access
 - EAT = $0.80 \times 100 + 0.20 \times 200 = 120$ ns
 - Consider a more realistic hit ratio α = 99%; still 100ns for each memory access
 - EAT = $0.99 \times 100 + 0.01 \times 200 = 101 \text{ns}$
 - Temporal & spatial locality

- Multi-level page table
 - a linear address space is large, but many pages are not used
 - a linear page table often has many empty entries
 - split the page table into page-sized units
 - If an entire page of page-table entries is invalid, don't allocate that page of the page table at all
 - To track whether a page of the page table is valid, use a new structure, called page directory
 - It consists of a number of page directory entries (PDE)
 - one PDE per page of the page table






Agenda

- Recap
- Multi-Level Page Tables (cont')
- Swapping


- Address Translation Example
 - A 32-bit virtual address (with 1KB page size) is divided into:
 - a page number consisting of 22 bits
 - a page offset consisting of 10 bits
 - Since the page table is paged, the page number is further divided into:
 - a 12-bit page directory index (p1)
 - a 10-bit page table index (p2)

page number		page offset
p_1	ρ_2	d
12	10	10


- Address Translation Example
 - the page directory index (p1) is used to identify a page directory entry (PDE) in the page directory
 - the page table index (p2) is used to identify a page table entry (PTE) in a page of page table




- Two levels may not be sufficient
 - E.g., assume a 64-bit address space
 - If page size is 4 KB (2¹²)
 - then page table has 2⁵² entries
 - In a two-level page table
 - a page (4KB) of page table could be 2¹⁰ 4-byte entries
 - 10 bits for indexing into the page of page table
 - the page directory has 2⁴² 4-byte entries (2⁴⁴ bytes)
 - the page directory itself is huge!




- Introducing more levels
 - E.g., a three-level page table
 - page global directory (PGD)
 - page middle directory (PMD)
 - page table



Intel IA-32 Paging Architecture



- Intel x86-64
 - 64 bits is ginormous (> 16 exabytes)
 - In practice only implement 48 bit addressing
 - Page sizes of 4 KB, 2 MB, 1 GB
 - Four levels of paging hierarchy
 - Can use page address extension (PAE) to extend physical address bits



Multi-Level Page Tables


- Advantages
 - Only allocates page-table space in proportion to the amount of address space you are using.
 - The OS can grab the next free page when it needs to allocate or grow a page table.
- Disadvantages
 - may be slower for some memory accesses
 - time-space tradeoff
 - complexity

Agenda

- Recap
- Multi-Level Page Tables (cont')
- Swapping


Swapping

- Extend physical memory
 - stash away portions of address space that currently aren't in great demand
 - the unpopular pages are placed in the swap space at the next layer of memory/storage hierarchy
 - e.g., hard disk drives (HDDs)



Swapping

- Swap Space
 - Reserved space on the disk for moving pages back and forth
 - OS manages the swap space, in page-sized unit



Physical Memory and Swap Space


Swapping

- Present Bit
 - One bit in the page table entry (PTE) to support swapping
 - When the hardware checks the PTE, it may find that the page is not present in physical memory

Value	Meaning
1	page is present in physical memory
0	The page is not in memory but rather on disk.

Accessing a page not in physical memory

Page fault handler swap in a page from disk



Agenda

Recap

Questions?

- Multi-Level Page Tables (cont')
- Swapping



^{*}acknowledgement: slides include content from "Modern Operating Systems" by A. Tanenbaum, "Operating Systems Concepts" by A. Silberschatz etc., "Operating Systems: Three Easy Pieces" by R. Arpaci-Dusseau etc., and anonymous pictures from internet.