

Electricity & Magnetism

One-Shot Revision Notes (Serial Wise)

Exam Revision Version — High Yield Notes

Contains formulas, definitions, crucial derivations, TikZ diagrams, and high-weightage topics curated directly from PYQs.

Designed for Quick Revision & Exam Readiness

May 31, 2026

Contents

1	Part 1: Electrostatics	3
1.1	Electric Charge	3
1.1.1	Key Properties	3
1.2	Coulomb's Law	3
1.3	Electric Field Intensity	3
1.4	Electric Field Due to a Point Charge	4
1.5	Superposition Principle	4
1.6	Electric Flux	4
1.6.1	Special Cases	5
1.7	Gauss's Theorem	5
1.8	Applications of Gauss's Law	5
1.8.1	(A) Infinite Line Charge	5
1.8.2	(B) Infinite Plane Sheet	6
1.8.3	(C) Uniformly Charged Sphere	6
1.9	Electric Potential	6
1.10	Potential Due to a Point Charge	6
1.11	Relation Between Electric Field and Potential	6
1.12	Potential Energy	7
1.13	Electric Dipole	7
1.14	Potential Due to an Electric Dipole	7
1.15	Electric Field Due to a Dipole	8
1.16	Torque on an Electric Dipole	8
1.17	Potential Energy of a Dipole	8
1.18	Polarization	8
1.19	Relation Between Polarization and Surface Charge Density	9
1.20	Dielectric Constant	9
1.21	Electric Susceptibility	9
1.21.1	Key Relation	9
1.22	Electric Displacement Vector	9
1.23	Gauss's Law in Dielectrics	10
1.24	Capacitor with Dielectric	10
2	Part 2: Magnetostatics	12
2.1	Magnetic Field	12
2.2	Magnetic Field Lines	12
2.2.1	Crucial Properties	12
2.3	Lorentz Force	12
2.3.1	Magnetic Force Only	12
2.4	Force on a Current-Carrying Conductor	13
2.5	Motion of a Charged Particle in a Uniform Magnetic Field	13
2.6	Biot–Savart Law	13
2.7	Magnetic Field Due to an Infinite Straight Wire	14
2.8	Magnetic Field on the Axis of a Circular Coil	14
2.8.1	At the Centre of the Coil ($x = 0$):	14
2.9	Ampere's Circuital Law	14
2.10	Solenoid	14
2.11	Toroid	15
2.12	Magnetization	15
2.13	Magnetic Susceptibility	15
2.14	Magnetic Permeability	16

2.15	Relation Between Permeability and Susceptibility	16
2.16	Classification of Magnetic Materials	16
2.16.1	Diamagnetic Materials	16
2.16.2	Paramagnetic Materials	16
2.16.3	Ferromagnetic Materials	16
2.17	Comparison Table of Magnetic Materials	17
3	Part 3: Electromagnetic Induction	19
3.1	Electromagnetic Induction (EMI)	19
3.2	Magnetic Flux	19
3.2.1	Special Cases	19
3.3	Faraday's First Law	19
3.4	Faraday's Second Law	19
3.5	Motional emf	20
3.6	Lenz's Law	20
3.6.1	Implications	20
3.7	Self-Induction	20
3.8	Self-Inductance of a Solenoid	20
3.8.1	Proportionality Trends	21
3.9	Self-Inductance of a Toroid	21
3.10	Mutual Induction	21
3.11	Current Density	21
3.12	Continuity Equation	21
3.13	Displacement Current	22
3.14	Modified Ampere's Law (Ampere–Maxwell Law)	22
3.15	Maxwell's Equations	22
3.15.1	Equation 1: Gauss's Law for Electricity	22
3.15.2	Equation 2: Gauss's Law for Magnetism	22
3.15.3	Equation 3: Faraday's Law of Induction	23
3.15.4	Equation 4: Ampere–Maxwell Law	23
3.16	Maxwell's Equations Summary Table	23
4	Part 4: Network Theorems	25
4.1	Ohm's Law	25
4.2	Electrical Power	25
4.3	Kirchhoff's Current Law (KCL)	25
4.4	Kirchhoff's Voltage Law (KVL)	25
4.5	Thevenin's Theorem	26
4.5.1	Procedure to Find Thevenin Equivalent	26
4.6	Norton's Theorem	26
4.7	Thevenin–Norton Conversion	27
4.8	Maximum Power Transfer Theorem	27
4.8.1	Derivation Framework	27
4.9	Theorem Comparison Table	28
5	Entire Electricity & Magnetism Formula Sheet (Highest Priority)	30
5.1	Electrostatics	30
5.2	Magnetostatics	30
5.3	Electromagnetic Induction	30
5.4	Network Theory	31

1 Part 1: Electrostatics

Important Note: This is the condensed exam-oriented revision version. Focus heavily on memorizing the boxed formulas, definitions, and high-weightage derivations listed under the PYQ sections.

1.1 Electric Charge

Electric charge is the fundamental intrinsic property of matter that gives rise to electric forces.

1.1.1 Key Properties

1. **Quantization of Charge:** Charge exists only in discrete integral multiples of the elementary charge e .

Quantization of Charge


$$q = ne$$

Where $e = 1.6 \times 10^{-19}$ C is the charge of a proton/electron, and $n \in \mathbb{Z}$.

2. **Conservation of Charge:** The total net electric charge of an isolated system remains constant over time.
3. **Additivity of Charge:** Total charge of a system is the algebraic sum of all individual charges:
 $q_{\text{total}} = q_1 + q_2 + q_3 + \dots$

1.2 Coulomb's Law

Provides the electrostatic force of attraction or repulsion between two stationary point charges.



Coulomb's Law Formula

$$F = \frac{1}{4\pi\epsilon_0} \frac{q_1 q_2}{r^2}$$

Where ϵ_0 is the permittivity of free space ($\epsilon_0 = 8.854 \times 10^{-12}$ C²/N · m²).

Electrostatic Constant

$$\frac{1}{4\pi\epsilon_0} = 9 \times 10^9 \text{ N} \cdot \text{m}^2/\text{C}^2$$

1.3 Electric Field Intensity

The electric field intensity $\vec{E}$ at any point is defined as the electrostatic force experienced per unit positive test charge placed at that point.

Electric Field Strength

$$E = \frac{F}{q} \quad \Rightarrow \quad \vec{E} = \frac{\vec{F}}{q}$$

Unit: N/C (or V/m)

1.4 Electric Field Due to a Point Charge

Determines the electric field produced by a single source charge $+Q$ at a distance r .

**Electric Field (Point Charge)**

$$E = \frac{1}{4\pi\epsilon_0} \frac{Q}{r^2}$$

1.5 Superposition Principle

The net electric field at any point due to a system of multiple stationary charges is the vector sum of the electric fields produced by each individual charge at that point.

Superposition Principle

$$\vec{E}_{\text{net}} = \vec{E}_1 + \vec{E}_2 + \vec{E}_3 + \cdots = \sum_{i=1}^n \vec{E}_i$$

1.6 Electric Flux

Electric flux is a measure of the number of electric field lines passing through a given surface area A .

Electric Flux Formula

$$\phi_E = \vec{E} \cdot \vec{A} = EA \cos \theta$$

Where θ is the angle between the electric field vector $\vec{E}$ and the normal vector to the surface area $\vec{A}$.

Unit: $\text{N} \cdot \text{m}^2/\text{C}$

1.6.1 Special Cases

- **Maximum Flux** ($\theta = 0^\circ$): The field lines are normal to the surface.

$$\phi_E = EA$$

- **Zero Flux** ($\theta = 90^\circ$): The field lines run parallel to the surface.

$$\phi_E = 0$$

1.7 Gauss's Theorem

PYQ Priority: *****

Statement: The net electric flux ϕ_E through any closed Gaussian surface is equal to $\frac{1}{\epsilon_0}$ times the net charge enclosed within that surface.

Gauss's Law (Integral Form)

$$\oint \vec{E} \cdot d\vec{A} = \frac{Q_{\text{enclosed}}}{\epsilon_0}$$

Gauss's Law (Differential Form)

$$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$$


Where ρ is the volume charge density.

1.8 Applications of Gauss's Law

1.8.1 (A) Infinite Line Charge

PYQ Priority: *****

Calculates the electric field at a perpendicular distance r from an infinitely long wire with uniform linear charge density λ .



Electric Field of Infinite Line Charge

$$E = \frac{\lambda}{2\pi\epsilon_0 r}$$

1.8.2 (B) Infinite Plane Sheet

PYQ Priority: *****

Calculates the electric field produced by an infinite plane sheet of charge with uniform surface charge density σ .

Electric Field of Infinite Plane Sheet

$$E = \frac{\sigma}{2\epsilon_0}$$

Crucial Note: The electric field is completely **independent of the distance r** from the sheet.

1.8.3 (C) Uniformly Charged Sphere

For a solid insulating sphere of radius R and total uniform charge Q :

- **Outside the Sphere ($r \geq R$):**

Outside Sphere

$$E = \frac{1}{4\pi\epsilon_0} \frac{Q}{r^2}$$

- **Inside the Sphere ($r < R$):**

Inside Sphere

$$E = \frac{1}{4\pi\epsilon_0} \frac{Qr}{R^3}$$

1.9 Electric Potential

The electric potential V at any point in an electric field is the amount of work done per unit positive charge in bringing it from infinity to that point against electrostatic forces.

Electric Potential Formula

$$V = \frac{W}{q}$$

Unit: Volt (V) = J/C

1.10 Potential Due to a Point Charge

Potential (Point Charge)

$$V = \frac{1}{4\pi\epsilon_0} \frac{Q}{r}$$

1.11 Relation Between Electric Field and Potential

PYQ Priority: *****

Defines the relationship between the electric field intensity and the electric potential gradient.

Relation Between E and V

$$E = -\frac{dV}{dr}$$

Vector Form (Gradient):

$$\vec{E} = -\nabla V$$

1.12 Potential Energy

The electrostatic potential energy U of a charge q in an electric potential V is:

Potential Energy (Single Charge)

$$U = qV$$

For a system of two point charges q_1 and q_2 separated by a distance r :


Potential Energy (Two Charges)

$$U = \frac{1}{4\pi\epsilon_0} \frac{q_1 q_2}{r}$$

1.13 Electric Dipole

PYQ Priority: ***** (Direct 10 Marks Derivation)

A pair of equal and opposite point charges $+q$ and $-q$ separated by a very small distance $2a$.



Dipole Moment

$$p = q(2a) \implies \vec{p} = q(2\vec{a})$$

The vector direction of $\vec{p}$ is always from the **negative charge to the positive charge**.

Unit: $\text{C} \cdot \text{m}$

1.14 Potential Due to an Electric Dipole

PYQ Priority: *****

General formula for the potential V at any position (r, θ) relative to the dipole center.

Potential of a Dipole (General)

$$V = \frac{1}{4\pi\epsilon_0} \frac{p \cos \theta}{r^2}$$

- **Axial Position** ($\theta = 0^\circ$):

$$V_{\text{axial}} = \frac{1}{4\pi\epsilon_0} \frac{p}{r^2}$$

- **Equatorial Position** ($\theta = 90^\circ$):

$$V_{\text{equatorial}} = 0$$

1.15 Electric Field Due to a Dipole

- **Axial Field (End-on Position):**

Axial Electric Field

$$E_{\text{axial}} = \frac{1}{4\pi\epsilon_0} \frac{2p}{r^3}$$

- **Equatorial Field (Broadside-on Position):**

Equatorial Electric Field

$$E_{\text{equatorial}} = \frac{1}{4\pi\epsilon_0} \frac{p}{r^3}$$

- **General Position Field:**

General Electric Field

$$E = \frac{1}{4\pi\epsilon_0} \frac{p}{r^3} \sqrt{1 + 3\cos^2\theta}$$

1.16 Torque on an Electric Dipole

When placed in a uniform external electric field $\vec{E}$:

Torque on Dipole

$$\tau = pE \sin\theta$$

Vector Form:

$$\vec{\tau} = \vec{p} \times \vec{E}$$

1.17 Potential Energy of a Dipole

The potential energy stored in a dipole placed in a uniform electric field $\vec{E}$:

Potential Energy of Dipole

$$U = -pE \cos\theta = -\vec{p} \cdot \vec{E}$$

1.18 Polarization

The polarization $\vec{P}$ is defined as the induced electric dipole moment per unit volume of a dielectric material.

Polarization

$$P = \frac{\text{Electric Dipole Moment}}{\text{Volume}}$$

Unit: C/m²

1.19 Relation Between Polarization and Surface Charge Density

PYQ Priority: ****

Relates the polarization vector to the induced surface bound charge density σ_p .

Polarization and Bound Charge

$$\sigma_p = P$$

General Vector Form:

$$\sigma_p = \vec{P} \cdot \hat{n}$$

Where $\hat{n}$ is the unit normal vector pointing outward from the dielectric surface.

1.20 Dielectric Constant

The ratio of permittivity of the medium to the permittivity of free space.

Dielectric Constant

$$K = \frac{\epsilon}{\epsilon_0}$$

1.21 Electric Susceptibility

Measures how easily a dielectric polarizes when subjected to an external electric field.

Electric Susceptibility

$$\vec{P} = \epsilon_0 \chi_e \vec{E}$$

Where χ_e is the dimensionless electric susceptibility.

1.21.1 Key Relation

Relation Between K and Susceptibility

$$K = 1 + \chi_e$$

1.22 Electric Displacement Vector

The electric displacement vector $\vec{D}$ accounts for the effects of both free and bound charges in a dielectric material.

Electric Displacement Vector

$$\vec{D} = \epsilon \vec{E}$$

Alternative Form:

$$\vec{D} = \epsilon_0 \vec{E} + \vec{P}$$

1.23 Gauss's Law in Dielectrics

In a dielectric medium, the total flux of the electric displacement vector $\vec{D}$ through any closed surface is equal to the net free charge enclosed within that surface. Bound charges are implicitly accounted for by the polarization term inside $\vec{D}$.

Gauss's Law in Dielectrics

$$\oint \vec{D} \cdot d\vec{A} = Q_{\text{free}}$$

Differential Form:

$$\nabla \cdot \vec{D} = \rho_{\text{free}}$$

1.24 Capacitor with Dielectric

When a dielectric material of dielectric constant K is introduced between the plates of a parallel plate capacitor, its capacitance always increases from C_0 to $C = KC_0$. However, other electrical quantities depend on whether the battery remains connected or is isolated.

1. Case 1: Battery Remains Connected (Voltage Constant)

- **Potential Difference:** $V = V_0$ (remains constant).
- **Capacitance:** $C = KC_0$ (increases).
- **Charge:** $Q = KQ_0$ (increases as more charge is drawn from the battery).
- **Electric Field:** $E = E_0$ (remains constant since V and d are constant).
- **Energy Stored:** $U = \frac{1}{2}CV^2 = KU_0$ (increases).

2. Case 2: Capacitor is Isolated after Charging (Charge Constant)

- **Charge:** $Q = Q_0$ (remains constant since no path exists for charge flow).
- **Capacitance:** $C = KC_0$ (increases).
- **Potential Difference:** $V = \frac{V_0}{K}$ (decreases by a factor of K).
- **Electric Field:** $E = \frac{E_0}{K}$ (decreases due to induced bound charge fields).
- **Energy Stored:** $U = \frac{Q^2}{2C} = \frac{U_0}{K}$ (decreases).

Electrostatics PYQ Priority: High-Yield Topics

Make sure you can thoroughly write and derive the following high-weightage topics:

1. **Gauss's Theorem:** Derivation and physical meaning.
2. **Infinite Line Charge Field:** Gaussian cylinder application.
3. **Electric Dipole potential and field** at axial, equatorial, and general positions.
4. **Polarization relation** ($\sigma_p = \vec{P} \cdot \hat{n}$).
5. **Dielectric Constant & Electric Displacement Vector** definitions.

Electrostatics Revision Complete! ✓

2 Part 2: Magnetostatics

2.1 Magnetic Field

The vector space around a moving charge, current-carrying conductor, or magnetic material where magnetic forces can be detected.

Magnetic Field Symbol and Units

Symbol: $\vec{B}$

Unit: Tesla (T) = 1 N/(A · m) = 10⁴ Gauss

2.2 Magnetic Field Lines

Imaginary lines depicting the direction and density of the magnetic field vector.

2.2.1 Crucial Properties

- Form continuous **closed loops** (no magnetic monopoles).
- **Outside the magnet:** Point from North (*N*) to South (*S*).
- **Inside the magnet:** Point from South (*S*) to North (*N*).
- They never intersect.

2.3 Lorentz Force

PYQ Priority: ****

Total force experienced by a charged particle moving through both electric and magnetic fields.

Lorentz Force (Combined)

$$\vec{F} = q(\vec{E} + \vec{v} \times \vec{B})$$

2.3.1 Magnetic Force Only

When only a magnetic field is present:

Magnetic Lorentz Force

$$F = qvB \sin \theta$$

Where θ is the angle between the velocity vector $\vec{v}$ and the magnetic field vector $\vec{B}$.

Special Cases:

- **Parallel Motion** ($\theta = 0^\circ$ or 180°): $F = 0$. The path remains straight.
- **Perpendicular Motion** ($\theta = 90^\circ$): $F = qvB$ (Maximum force). The path becomes circular.

2.4 Force on a Current-Carrying Conductor

Magnetic Force on Wire

$$F = BIL \sin \theta$$

Vector Form:

$$\vec{F} = I(\vec{L} \times \vec{B})$$

Where I is the current, $\vec{L}$ is the length vector in the direction of the current, and $\vec{B}$ is the magnetic field.

2.5 Motion of a Charged Particle in a Uniform Magnetic Field

For a particle entering perpendicularly ($\theta = 90^\circ$):

- **Radius of the Circular Path:**

Circular Radius

$$r = \frac{mv}{qB}$$

- **Time Period of Revolution:**

Time Period

$$T = \frac{2\pi m}{qB}$$

- **Frequency of Revolution:**

Frequency

$$f = \frac{1}{T} = \frac{qB}{2\pi m}$$

2.6 Biot–Savart Law

PYQ Priority: *****

Gives the magnetic field contribution $d\vec{B}$ produced by a small current element $I d\vec{l}$ at a distance r .

Biot–Savart Law

$$dB = \frac{\mu_0}{4\pi} \frac{Idl \sin \theta}{r^2}$$

Where $\mu_0 = 4\pi \times 10^{-7} \text{ T} \cdot \text{m/A}$ is the magnetic permeability of free space.

Biot–Savart Law (Vector Form)

$$d\vec{B} = \frac{\mu_0}{4\pi} \frac{I(d\vec{l} \times \hat{r})}{r^2} = \frac{\mu_0}{4\pi} \frac{I(d\vec{l} \times \vec{r})}{r^3}$$

2.7 Magnetic Field Due to an Infinite Straight Wire

PYQ Priority: *****

Calculates the magnetic field B at a perpendicular distance r from an infinitely long straight wire carrying a steady current I .

Field of Infinite Wire

$$B = \frac{\mu_0 I}{2\pi r}$$

Crucial Proportionally: $B \propto \frac{1}{r}$

2.8 Magnetic Field on the Axis of a Circular Coil

PYQ Priority: *****

Gives the magnetic field at a distance x along the axis of a circular current loop of radius R containing N turns.

Field on Axis of Circular Coil

$$B = \frac{\mu_0 N I R^2}{2(R^2 + x^2)^{3/2}}$$

2.8.1 At the Centre of the Coil ($x = 0$):

Field at Centre of Circular Coil

$$B = \frac{\mu_0 N I}{2R}$$

2.9 Ampere's Circuital Law

PYQ Priority: *****

Statement: The line integral of the magnetic field $\vec{B}$ around any closed path (Amperian loop) is equal to μ_0 times the total net current passing through the surface enclosed by the loop.

Ampere's Law

$$\oint \vec{B} \cdot d\vec{l} = \mu_0 I_{\text{enclosed}}$$

2.10 Solenoid

PYQ Priority: *****

A long, tightly wound helical coil of wire designed to produce a uniform magnetic field.

Magnetic Field Inside Solenoid (Vacuum)

$$B = \mu_0 n I$$

Where $n = \frac{N}{l}$ is the number of turns per unit length.

Solenoid with Magnetic Core

$$B = \mu_0 \mu_r n I = \mu n I$$

Where μ_r is the relative permeability of the core material.

2.11 Toroid**PYQ Priority: ******

A solenoid bent into a closed circular ring shape.

Magnetic Field of Toroid

$$B = \frac{\mu_0 N I}{2\pi r}$$

Where r is the mean radius of the toroid and N is the total number of turns.

2.12 Magnetization

The vector quantity representing the density of induced or permanent magnetic dipole moments in a magnetic material.

Magnetization Vector

$$\vec{M} = \frac{\text{Net Magnetic Dipole Moment}}{\text{Volume}}$$

Unit: A/m

2.13 Magnetic Susceptibility

A dimensionless proportionality constant indicating the degree of magnetization of a material in response to an applied magnetic field.

Magnetic Susceptibility

$$\vec{M} = \chi \vec{H}$$

Where $\vec{H}$ is the magnetic field intensity (auxiliary field).

2.14 Magnetic Permeability

Permeability Relations

$$\mu = \frac{B}{H}$$

Relative Permeability:

$$\mu_r = \frac{\mu}{\mu_0}$$

2.15 Relation Between Permeability and Susceptibility

PYQ Priority: ****

Derive the direct relationship between magnetic permeability and magnetic susceptibility.

Relation Between μ and χ

$$\mu = \mu_0(1 + \chi)$$

$$\mu_r = 1 + \chi$$

2.16 Classification of Magnetic Materials

2.16.1 Diamagnetic Materials

- Magnetization is opposite to the external field.
- **Susceptibility:** $\chi < 0$ (weakly negative).
- **Relative Permeability:** $\mu_r < 1$.
- Strongly repelled from high-field regions.
- **Examples:** Copper (Cu), Silver (Ag), Gold (Au), Water.

2.16.2 Paramagnetic Materials

PYQ Priority: ****

Materials that magnetize weakly in the direction of the external field.

- **Susceptibility:** $\chi > 0$ (weakly positive).
- **Relative Permeability:** $\mu_r > 1$.
- Weakly attracted to magnets.
- **Examples:** Aluminium (Al), Platinum (Pt), Oxygen (O_2).

2.16.3 Ferromagnetic Materials

- Strong permanent or induced magnetization in the field direction.
- **Susceptibility:** $\chi \gg 1$ (extremely large, positive).
- **Relative Permeability:** $\mu_r \gg 1$.

- Strongly attracted to magnets.
- **Examples:** Iron (Fe), Nickel (Ni), Cobalt (Co).

2.17 Comparison Table of Magnetic Materials

Table 1: Key Magnetic Properties Comparison

Property	Diamagnetic	Paramagnetic	Ferromagnetic
Susceptibility (χ)	Negative ($\chi < 0$)	Positive ($\chi > 0$)	Very Large Positive ($\chi \gg 1$)
Relative Permeability (μ_r)	$\mu_r < 1$	$\mu_r > 1$	$\mu_r \gg 1$
External Attraction	Weakly Repelled	Weakly Attracted	Strongly Attracted
Typical Examples	Cu, Ag, H ₂ O	Al, Pt, O ₂	Fe, Ni, Co

Magnetostatics PYQ Priority: High-Yield Topics

Prioritize studying and writing out derivations for:

1. **Biot–Savart Law:** Integral and vector representation.
2. **Infinite Wire Field:** Derived via Biot–Savart and Ampere’s Law.
3. **On-Axis Circular Coil Field:** Complete derivation.
4. **Ampere’s Circuital Law:** Derivation and boundary conditions.
5. **Solenoid & Toroid:** Magnetic field formulas.
6. **Relation:** $\mu_r = 1 + \chi$.

Magnetostatics Revision Complete! ✓

3 Part 3: Electromagnetic Induction

3.1 Electromagnetic Induction (EMI)

The physical generation of an electromotive force (emf) across an electrical conductor in a changing magnetic field.

Core Concept of EMI

$$\text{Changing Magnetic Flux } (\phi_B) \implies \text{Induced emf } (e)$$

3.2 Magnetic Flux

Total magnetic field lines passing normally through a given area.

Magnetic Flux Formula

$$\phi_B = \vec{B} \cdot \vec{A} = BA \cos \theta$$

Where θ is the angle between the magnetic field $\vec{B}$ and the normal vector to the surface area $\vec{A}$.

Unit: Weber (Wb) = Tesla $\cdot$ m²

3.2.1 Special Cases

- **Maximum Flux** ($\theta = 0^\circ$): $\phi_B = BA$.
- **Zero Flux** ($\theta = 90^\circ$): $\phi_B = 0$.

3.3 Faraday's First Law

PYQ Priority: *****

Statement: Whenever the magnetic flux linked with a closed circuit changes, an electromotive force (emf) is induced in the circuit, which lasts as long as the change in flux continues.

3.4 Faraday's Second Law

PYQ Priority: *****

Statement: The magnitude of the induced emf in a circuit is directly proportional to the time rate of change of magnetic flux linked with that circuit.

Faraday's Law of Induction

$$e = -\frac{d\phi_B}{dt}$$

For a Coil with N Turns:

$$e = -N \frac{d\phi_B}{dt}$$

Negative Sign: Indicates the direction of the induced emf (dictated by Lenz's Law).

3.5 Motional emf

Induced voltage generated across a conductor moving through a stationary magnetic field.

Motional emf

$$e = Blv$$

Where B is the magnetic field, l is the length of the conductor, and v is its perpendicular velocity.

3.6 Lenz's Law

PYQ Priority: *****

Statement: The direction of the induced current is always such that it opposes the change in magnetic flux that produced it.

3.6.1 Implications

- **Flux Increasing:** Induced current creates a magnetic field opposing the increase.
- **Flux Decreasing:** Induced current creates a magnetic field supporting the flux to prevent decrease.
- Directly explains the negative sign in $e = -\frac{d\phi_B}{dt}$.
- A direct consequence of the **Law of Conservation of Energy**.

3.7 Self-Induction

The production of an opposing induced emf in a coil when the current flowing through that same coil changes over time.

Self-Inductance

$$N\phi_B = LI \quad \Rightarrow \quad L = \frac{N\phi_B}{I}$$

Where L is the self-inductance of the coil.

Unit: Henry (H) = Wb/A

Self-Induced emf

$$e = -L \frac{dI}{dt}$$

3.8 Self-Inductance of a Solenoid

PYQ Priority: *****

Derivation of self-inductance for a long solenoid of length l , area A , and total turns N .

Self-Inductance of Solenoid

$$L = \frac{\mu_0 N^2 A}{l}$$

3.8.1 Proportionality Trends

- $L \propto N^2$ (square of the number of turns).
- $L \propto A$ (cross-sectional area).
- $L \propto \frac{1}{l}$ (inversely proportional to length).

3.9 Self-Inductance of a Toroid

Self-Inductance of Toroid

$$L = \frac{\mu_0 N^2 r^2}{2R}$$

Where R is the mean radius and r is the cross-sectional radius.

3.10 Mutual Induction

The phenomenon of inducing an emf in a secondary coil when the current flowing in a primary coil changes.

Mutual Inductance

$$N_2 \phi_{21} = M I_1 \quad \Rightarrow \quad M = \frac{N_2 \phi_{21}}{I_1}$$

Where M is the mutual inductance between the two coils.

Mutual Induced emf

$$e_2 = -M \frac{dI_1}{dt}$$

Mutual Inductance of Two Coaxial Solenoids

$$M = \frac{\mu_0 N_1 N_2 A}{l}$$

3.11 Current Density

Current flowing per unit cross-sectional area of a conductor.

Current Density

$$J = \frac{I}{A} \quad \Rightarrow \quad I = \int \vec{J} \cdot d\vec{A}$$

Unit: A/m²

3.12 Continuity Equation

PYQ Priority: **** (Direct Derivation)

Expresses the global conservation of electric charge in differential form.

Continuity Equation

$$\nabla \cdot \vec{J} + \frac{\partial \rho}{\partial t} = 0$$

Where $\vec{J}$ is current density and ρ is charge density.

3.13 Displacement Current**PYQ Priority: ******

The current that arises due to a time-varying electric field, introduced by Maxwell to resolve Ampere's law inconsistency.

Displacement Current

$$I_d = \epsilon_0 \frac{d\phi_E}{dt}$$

Displacement Current Density

$$J_d = \epsilon_0 \frac{\partial E}{\partial t}$$

3.14 Modified Ampere's Law (Ampere–Maxwell Law)**Ampere–Maxwell Law**

$$\oint \vec{B} \cdot d\vec{l} = \mu_0 I_{\text{enclosed}} + \mu_0 \epsilon_0 \frac{d\phi_E}{dt}$$

3.15 Maxwell's Equations**PYQ Priority: ***** (Crucial 10 Marks Question)**

The four fundamental equations of classical electromagnetism, uniting electricity and magnetism.

3.15.1 Equation 1: Gauss's Law for Electricity**Gauss's Law (Electric)**

Differential Form: $\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$

Integral Form: $\oint \vec{E} \cdot d\vec{A} = \frac{Q_{\text{enclosed}}}{\epsilon_0}$

3.15.2 Equation 2: Gauss's Law for Magnetism**Gauss's Law (Magnetic)**

Differential Form: $\nabla \cdot \vec{B} = 0$

Integral Form: $\oint \vec{B} \cdot d\vec{A} = 0$

3.15.3 Equation 3: Faraday's Law of Induction

Faraday's Law

Differential Form: $\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$

Integral Form: $\oint \vec{E} \cdot d\vec{l} = -\frac{d\phi_B}{dt}$

3.15.4 Equation 4: Ampere–Maxwell Law

Ampere–Maxwell Law

Differential Form: $\nabla \times \vec{B} = \mu_0 \vec{J} + \mu_0 \epsilon_0 \frac{\partial \vec{E}}{\partial t}$

Integral Form: $\oint \vec{B} \cdot d\vec{l} = \mu_0 I + \mu_0 \epsilon_0 \frac{d\phi_E}{dt}$

3.16 Maxwell's Equations Summary Table

Table 2: Summary of Maxwell's Equations

Equation Name	Differential Form	Integral Form
Gauss (Electric)	$\nabla \cdot \vec{E} = \frac{\rho}{\epsilon_0}$	$\oint \vec{E} \cdot d\vec{A} = \frac{Q}{\epsilon_0}$
Gauss (Magnetic)	$\nabla \cdot \vec{B} = 0$	$\oint \vec{B} \cdot d\vec{A} = 0$
Faraday Law	$\nabla \times \vec{E} = -\frac{\partial \vec{B}}{\partial t}$	$\oint \vec{E} \cdot d\vec{l} = -\frac{d\phi_B}{dt}$
Ampere–Maxwell	$\nabla \times \vec{B} = \mu_0 \vec{J} + \mu_0 \epsilon_0 \frac{\partial \vec{E}}{\partial t}$	$\oint \vec{B} \cdot d\vec{l} = \mu_0 I + \mu_0 \epsilon_0 \frac{d\phi_E}{dt}$

Electromagnetic Induction PYQ Priority

Focus first on deriving and explaining:

1. **Maxwell's Equations:** Physical meaning of all 4 equations.
2. **Continuity Equation:** Detailed charge conservation derivation.
3. **Displacement Current:** Need for adding this term to Ampere's Law.
4. **Self-Inductance of a Solenoid:** Step-by-step derivation.
5. **Lenz's Law:** Verification of conservation of energy.

Electromagnetic Induction Revision Complete! ✓

4 Part 4: Network Theorems

4.1 Ohm's Law

Ohm's Law

$$V = IR$$

Where V is the voltage, I is the current, and R is the electrical resistance.

4.2 Electrical Power

Electrical Power Formulas

$$P = VI$$


Alternative Forms:

$$P = I^2 R \quad \text{and} \quad P = \frac{V^2}{R}$$

4.3 Kirchhoff's Current Law (KCL)

PYQ Priority: ****

Statement: The algebraic sum of currents entering and leaving any node (junction) in an electrical network is zero.



Kirchhoff's Current Law

$$\sum I = 0 \quad \Rightarrow \quad I_{\text{in}} = I_{\text{out}}$$

In the diagram above: $I_1 + I_2 = I_3$.

Conservation Law: Based on the **Law of Conservation of Charge**.

4.4 Kirchhoff's Voltage Law (KVL)

PYQ Priority: ****

Statement: The algebraic sum of all branch voltages and emf sources around any closed loop in a circuit is equal to zero.

Kirchhoff's Voltage Law


$$\sum V = 0$$

Conservation Law: Based on the **Law of Conservation of Energy**.

4.5 Thevenin's Theorem

PYQ Priority: *** (Direct PYQ Proof)**

Statement: Any linear, bilateral two-terminal network consisting of voltage/current sources and resistances can be replaced by an equivalent circuit containing a single voltage source V_{th} in series with an equivalent resistance R_{th} .



Thevenin Values

V_{th} = Open-circuit voltage measured across terminals AB

R_{th} = Equivalent resistance looking back into AB with active sources deactivated

4.5.1 Procedure to Find Thevenin Equivalent

1. Remove the load resistance R_L from terminals A and B .
2. Calculate the open-circuit voltage V_{oc} across terminals A and B . This is V_{th} .
3. Deactivate all independent sources:
 - Replace independent voltage sources with a **short circuit**.
 - Replace independent current sources with an **open circuit**.
4. Calculate the equivalent resistance looking back into terminals A and B . This is R_{th} .
5. Reconnect R_L and compute the load current:


Thevenin Load Current

$$I_L = \frac{V_{th}}{R_{th} + R_L}$$

4.6 Norton's Theorem

PYQ Priority: ** (Direct PYQ Proof)**

Statement: Any linear, bilateral active two-terminal network can be replaced by an equivalent circuit consisting of a single constant current source I_N in parallel with an equivalent resistance R_N .



Norton Values

I_N = Short-circuit current I_{sc} flowing between terminals AB

R_N = Thevenin resistance R_{th}

Norton Load Current

$$I_L = I_N \left(\frac{R_N}{R_N + R_L} \right)$$

4.7 Thevenin–Norton Conversion**Source Transformations**

Thevenin to Norton:

$$I_N = \frac{V_{th}}{R_{th}}$$

Norton to Thevenin:

$$V_{th} = I_N R_N$$


Resistances:

$$R_N = R_{th}$$

4.8 Maximum Power Transfer Theorem

PYQ Priority: *****

Statement: Maximum power is transferred from a source network to an adjustable load resistance R_L when the value of the load resistance is equal to the internal resistance R_s (or Thevenin equivalent resistance R_{th}) of the source network.

**Theorem Condition**

$$R_L = R_s \quad \text{or} \quad R_L = R_{th}$$

4.8.1 Derivation Framework

Power delivered to the load P_L :

$$P_L = I^2 R_L = \left(\frac{V_s}{R_s + R_L} \right)^2 R_L$$

To maximize power, set $\frac{dP_L}{dR_L} = 0$:

$$\frac{d}{dR_L} \left[\frac{V_s^2 R_L}{(R_s + R_L)^2} \right] = 0 \quad \implies \quad R_L = R_s$$

Substituting $R_L = R_s$ yields the maximum power:

Maximum Power Formula

$$P_{\max} = \frac{V_s^2}{4R_s}$$

Efficiency at Max Power

$$\eta = 50\%$$

4.9 Theorem Comparison Table

Table 3: Key Network Theorem Summaries

Theorem	Equivalent Form	Key Relation / Output
Thevenin	Voltage source in series with R_{th}	$I_L = \frac{V_{\text{th}}}{R_{\text{th}} + R_L}$
Norton	Current source in parallel with R_N	$I_L = I_N \frac{R_N}{R_N + R_L}$
Max Power	Load matched to source resistance	$R_L = R_{\text{th}} \implies P_{\max} = \frac{V_{\text{th}}^2}{4R_{\text{th}}}$

Network Theory PYQ Priority

Focus first on the following topics:

1. **Thevenin's Theorem:** Step-by-step proofs and analytical circuit analysis.
2. **Maximum Power Transfer Theorem:** Proof of $R_L = R_{th}$, calculation of maximum power and 50% efficiency limit.
3. **Norton's Theorem:** Parallel equivalence and Norton–Thevenin transformation steps.
4. **Kirchhoff's Laws (KCL & KVL):** Conceptual base and physical conservation principles.

Network Theory Revision Complete! ✓

5 Entire Electricity & Magnetism Formula Sheet (Highest Priority)

This is a comprehensive reference sheet listing all crucial formulas across all four parts. Memorize these!

5.1 Electrostatics

- **Electric Field:** $E = \frac{1}{4\pi\epsilon_0} \frac{Q}{r^2}$
- **Electric Potential:** $V = \frac{1}{4\pi\epsilon_0} \frac{Q}{r}$
- **Potential Gradient Relation:** $E = -\frac{dV}{dr}$ or $\vec{E} = -\nabla V$
- **Dipole Moment:** $p = q(2a)$
- **Potential Due to Dipole:** $V_{\text{dipole}} = \frac{1}{4\pi\epsilon_0} \frac{p \cos \theta}{r^2}$
- **Axial Dipole Electric Field:** $E_{\text{axial}} = \frac{1}{4\pi\epsilon_0} \frac{2p}{r^3}$
- **Equatorial Dipole Electric Field:** $E_{\text{equatorial}} = \frac{1}{4\pi\epsilon_0} \frac{p}{r^3}$

5.2 Magnetostatics

- **Lorentz Force:** $F = qvB \sin \theta$
- **Force on Wire:** $F = BIL \sin \theta$
- **Biot–Savart Law:** $dB = \frac{\mu_0}{4\pi} \frac{Idl \sin \theta}{r^2}$
- **Infinite Straight Wire Field:** $B = \frac{\mu_0 I}{2\pi r}$
- **Circular Coil Axial Field:** $B = \frac{\mu_0 N I R^2}{2(R^2 + x^2)^{3/2}}$
- **Solenoid Field:** $B = \mu_0 n I$

5.3 Electromagnetic Induction

- **Induced emf (Faraday’s Law):** $e = -N \frac{d\phi_B}{dt}$
- **Self-Induced emf:** $e = -L \frac{dI}{dt}$
- **Self-Inductance of a Solenoid:** $L = \frac{\mu_0 N^2 A}{l}$
- **Mutual Inductance of Two Solenoids:** $M = \frac{\mu_0 N_1 N_2 A}{l}$
- **Continuity Equation (Charge Conservation):** $\nabla \cdot \vec{J} + \frac{\partial \rho}{\partial t} = 0$
- **Displacement Current:** $I_d = \epsilon_0 \frac{d\phi_E}{dt}$

5.4 Network Theory

- **Ohm's Law:** $V = IR$
- **Thevenin Circuit Load Current:** $I_L = \frac{V_{th}}{R_{th} + R_L}$
- **Thevenin–Norton Conversion:** $I_N = \frac{V_{th}}{R_{th}}$ and $R_N = R_{th}$
- **Maximum Power Transfer Condition:** $R_L = R_{th}$
- **Maximum Power Output:** $P_{max} = \frac{V_s^2}{4R_s}$

All E&M One-Shot Revision Content Successfully Transformed into LaTeX! ✓