Package 'SWIM'

July 19, 2019

Title Scenario Weights for Importance Measurement

Version 0.1.0

Author Silvana M. Pesenti [aut, cre],

Alberto Bettini [aut],

Pietro Millossovich [aut],

Andreas Tsanakas [aut]

Maintainer Silvana M. Pesenti < swimpackage@gmail.com>

Description An efficient sensitivity analysis for stochastic models based on Monte Carlo samples. Provides weights on simulated scenarios from a stochastic model, such that stressed random variables fulfil given probabilistic constraints (e.g. specified values for risk measures), under the new scenario weights. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model. The 'SWIM' package is based on Pesenti S.M, Millossovich P., Tsanakas A. (2019) "Reverse Sensitivity Testing: What does it take to break the model", <doi:10.1016/j.ejor.2018.10.003>.

Depends R (>= 3.5.0)

Imports Rdpack (>= 0.7), Hmisc, nleqslv, reshape2, plyr, ggplot2, spatstat, stats

RdMacros Rdpack

License GPL-3

URL https://github.com/spesenti/SWIM

Encoding UTF-8

LazyData true

RoxygenNote 6.1.1

Suggests testthat, mytnorm, spelling, Weighted.Desc.Stat

Language en-US

NeedsCompilation no

Repository CRAN

Date/Publication 2019-07-19 10:00:04 UTC

2 cdf

R topics documented:

cdf	 2
get_data	 3
importance_rank	 4
merge.SWIM	 5
plot_cdf	 6
plot_hist	 8
plot_sensitivity	 9
quantile_stressed	 11
sensitivity	 12
stress	 15
stress_mean	 16
stress_mean_sd	 17
stress_moment	 19
stress_prob	 21
stress_user	 23
stress_VaR	 24
stress_VaR_ES	 26
summary.SWIM	 28
SWIM	 29

cdf

Empirical Distribution Function of a Stressed Model

Description

Provides the empirical distribution function of a stressed model component (random variable) under the scenario weights.

Usage

```
cdf(object, xCol = 1, wCol = 1)
```

Arguments

object	A SWIM object.
xCol	Numeric or character, (name of) the column of the underlying data of the object ($default = 1$).
wCol	Numeric, the column of the scenario weights of the object (default = 1).

Value

The empirical distribution function (a function) of the xCol component of the stressed model with weights wCol. The empirical distribution function can be evaluated at a vector.

get_data 3

Author(s)

Silvana M. Pesenti

See Also

See plot_cdf for plotting the empirical distribution function of the stressed model and quantile_stressed for sample quantiles of a stressed model.

Examples

```
## example with a stress on VaR
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = c(0.9, 0.95), q_ratio = 1.05)
grid <- seq(min(x$normal), max(x$normal), length.out = 5)
## stressed empirical distribution function
cdf(res1, xCol = 1, wCol = 1)(grid)
## baseline empirical distribution function
ecdf(x$normal)(grid)</pre>
```

get_data

Extracting from a Stressed Model

Description

Extracting the data (realisations of the stochastic model), the scenario weights, the functions generating the scenario weights, or the specifications of the stress from an object of class SWIM.

Usage

```
get_data(object, xCol = "all")
get_weights(object)
get_weightsfun(object)
get_specs(object)
```

Arguments

4 get_data

Value

get_data: A data frame containing the realisations of the stochastic model on which the object is based.

get_weights: A data.frame containing the scenario weights of the object. Columns corresponds to different stresses.

get_weightsfun: A list containing functions, which, when applied to a column of the data, generate the scenario weights of the object. The corresponding stressed columns can be obtained via get_specs.

Use get_weights if the SWIM object only contains scenario weights and not a list of functions.

get_specs: A data frame containing specifications of the stresses with each row corresponding to a different stress. Only a selection of the specifications is returned; however, all input variables are stored in the object. See also SWIM.

Functions

- get_data: extracting data.
- get_weights: extracting scenario weights.
- get_weightsfun: extracting weight functions.
- get_specs: extracting information of the stress.

Author(s)

Silvana M. Pesenti

See Also

SWIM

```
## continuing example in stress_VaR
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = 0.9, q_ratio = 1.05)

## returning the underlying data
all(get_data(res1) == x)
## the scenario weights
get_weights(res1)
get_weightsfun(res1)
get_specs(res1)</pre>
```

importance_rank 5

importance	rank

Importance Ranking for a Stressed Model

Description

Provides the importance ranks of the components (random variables) of a stressed model for different sensitivity measures.

Usage

```
importance_rank(object, xCol = "all", wCol = "all", type = c("Gamma",
    "Wasserstein", "all"), f = NULL, k = NULL)
```

Arguments

-1-44	A CHITM abject
object	A SWIM object.
xCol	Numeric or character vector, (names of) the columns of the underlying data of the object (default = "all"). If $xCol = NULL$, only the transformed data $f(x)$ is considered.
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
type	Character, one of "Gamma", "Wasserstein", "all".
f	A function, or list of functions, that, applied to x , constitute the transformation of the data for which the sensitivity is calculated.
k	A vector or list of vectors, same length as f, indicating which columns of x each function in f operates on. When f is a list, $k[[i]]$ corresponds to the input variables of $f[[i]]$.

Details

For the definition of the sensitivity measures (type), see sensitivity.

Value

A data frame containing the importance ranks of the stressed model for different sensitivity measures. Small values correspond to large sensitivities. Different rows correspond to different random variables. The first two rows specify the stress and type of the sensitivity measure on which the ranking is calculated.

See Also

See sensitivity for the values of the sensitivity measures, plot_sensitivity for plotting sensitivity measures and summary for a summary statistic of a stressed model.

6 merge.SWIM

Examples

```
## example with a stress on VaR
set.seed(0)
x <- as.data.frame(cbind(
   "log-normal" = rlnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = c(0.9, 0.95), q_ratio = 1.05)

importance_rank(res1, wCol = 1:2, type = "Gamma")
## sensitivity of log-transformed data
importance_rank(res1, wCol = 1, type = "all",
   f = list(function(x)log(x), function(x)log(x)), k = list(1,2))</pre>
```

merge.SWIM

Merging Two Stressed Models

Description

This function is a method for an object of class SWIM.

Usage

```
## S3 method for class 'SWIM'
merge(x, y, ...)
```

Arguments

x, y Objects of class SWIM.

... Additional arguments will be ignored.

Details

Merges two objects of class ${\tt SWIM},$ that are based on the same data.

Value

An object of class SWIM containing:

- x, a data.frame containing the data;
- new_weights, a list, each component corresponds to a different stress and is either a vector of scenario weights or a function, that applied to a column of x, generates the vectors of scenario weights;
- type, a list, each component corresponds to a different stress and specifies the type of the stress;

plot_cdf 7

• specs, a list, each component corresponds to a different stress and contains a list with the specifications of what has been stressed.

See SWIM for details.

Author(s)

Silvana M. Pesenti

plot_cdf

Plotting the Empirical Distribution Functions of a Stressed Model

Description

Plots the empirical distribution function of a stressed model component (random variable) under the scenario weights.

Usage

```
plot_cdf(object, xCol = 1, wCol = "all", base = FALSE, n = 500,
    x_limits, y_limits, displ = TRUE)
```

Arguments

object	A SWIM object.
xCol	Numeric or character, (name of) the column of the underlying data of the $object$ (default = 1).
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
base	Logical, if TRUE, statistics under the baseline are also returned (default = "FALSE").
n	Integer, the number of points used to plot stat_ecdf in ggplot (default = 500).
x_limits	Vector, the limits of the x-axis of the plot, the value for $x = m$ in the coord_cartesian function in ggplot.
y_limits	Vector, the limits of the y-axis of the plot, the value for ylim in the coord_cartesian function in ggplot.
displ	Logical, if TRUE the plot is displayed, otherwise the data.frame for customised plotting with ggplot is returned (default = TRUE).

8 plot_hist

Value

If displ = TRUE, a plot displaying the empirical distribution function of the stochastic model under the scenario weights.

If displ = FALSE, a data.frame for customised plotting with ggplot. The data.frame contains the columns: the column, xCol, of the data of the stressed model, stress (the stresses) and value (the values).

Denote by res the return of the function call, then ggplot can be called via:

```
ggplot(res, aes(x = res[, 1], w = value))
+stat_ecdf(aes(color = factor(stress)), n = n).
```

Note that the ggplot2 default of stat_ecdf does not take weight as an aesthetic. We use the workaround by Nicolas Woloszko, see Note below.

Note

This function is based on the ggplot stat_ecdf function. However, the stat_ecdf does not allow for specifying weights, thus the function is based on the workaround by Nicolas Woloszko, see https://github.com/NicolasWoloszko/stat_ecdf_weighted.

See Also

See cdf for the empirical distribution function of a stressed model and quantile_stressed for sample quantiles of a stressed model.

Examples

```
## example with a stress on VaR
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(10^5),
   "gamma" = rgamma(10^5, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = c(0.75, 0.95), q_ratio = 1.15)
plot_cdf(res1, xCol = 1, wCol = 1:2, base = TRUE)
plot_cdf(res1, xCol = 1, wCol = 1:2, base = TRUE,
   x_limits = c(0, 5), y_limits = c(0.5, 1))</pre>
```

plot_hist

Plotting Histograms of a Stressed Model

Description

Plots the histogram of a stressed model component (random variable) under the scenario weights.

plot_hist 9

Usage

```
plot_hist(object, xCol = 1, wCol = "all", base = FALSE, x_limits,
    displ = TRUE, binwidth, displLines = FALSE)
```

Arguments

object	A SWIM object.
xCol	Numeric or character, (name of) the column of the underlying data of the object $(default = 1)$.
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
base	Logical, if TRUE, statistics under the baseline are also returned (default = "FALSE").
x_limits	Vector, the limits of the x-axis of the plot, the value for $xlim$ in the coord_cartesian function in ggplot.
displ	Logical, if TRUE the plot is displayed, otherwise the data.frame for customised plotting with ggplot is returned (default = TRUE).
binwidth	Numeric, the width of the bins used to plot the histogram, the binwidth in the geom_freqpoly function in ggplot (default corresponds to 30 bins).
displLines	Logical, if TRUE lines are displayed instead of bins (default = FALSE).

Value

If displ = TRUE, a histogram of the stochastic model under the scenario weights.

If displ = FALSE, a data frame for customised plotting with ggplot. The data frame contains the columns: the column, xCol, of the data of the stressed model, stress (the stresses) and value (the values).

Denote by res the return of the function call, then ggplot can be called via:

```
\begin{split} & ggplot(res, aes(x=res[,1], y=..density.., weight=value))) \\ & + geom_f reqpoly(binwidth, aes(color=factor(stress))). \end{split}
```

See Also

See cdf and plot_cdf for values and plotting of the empirical distribution function of a stressed model, respectively, and quantile_stressed for sample quantiles of a stressed model.

```
## example with a stress on VaR
set.seed(0)
x <- data.frame("gamma" = rgamma(10^5, shape = 2))
res1 <- stress(type = "VaR", x = x,
    alpha = c(0.75, 0.95), q_ratio = 1.1)
plot_hist(res1, xCol = "gamma", wCol = 1:2, base = TRUE, binwidth = 0.4)
plot_hist(res1, xCol = "gamma", wCol = 1:2, base = TRUE, binwidth = 0.4, displLines = TRUE)</pre>
```

plot_sensitivity

Description

Plots the sensitivity measures for components (random variables) of a stochastic model under the scenario weights.

Usage

```
plot_sensitivity(object, xCol = "all", wCol = "all",
  type = c("Gamma", "Kolmogorov", "Wasserstein"), f = NULL, k = NULL,
  displ = TRUE)
```

Arguments

object	A SWIM object.
xCol	Numeric or character vector, (names of) the columns of the underlying data of the object (default = "all"). If $xCol = NULL$, only the transformed data $f(x)$ is considered.
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
type	Character, one of "Gamma", "Kolmogorov", "Wasserstein", "all".
f	A function, or list of functions, that, applied to x , constitute the transformation of the data for which the sensitivity is calculated.
k	A vector or list of vectors, same length as f, indicating which columns of x each function in f operates on. When f is a list, $k[[i]]$ corresponds to the input variables of $f[[i]]$.
displ	Logical, if TRUE the plot is displayed, otherwise the data.frame for customised plotting with ggplot is returned (default = TRUE).

Details

For the definition of the sensitivity measures (type), see sensitivity.

Note that the Kolmogorov distance is the same for all inputs under the same stress. Thus, it should only be used to compare different stresses not individual components.

Value

If displ = TRUE, a plot displaying the sensitivity measures of the stochastic model under the scenario weights.

If displ = FALSE, a data.frame for customised plotting with ggplot. The data.frame contains the columns: stress (the stresses), type (the types of sensitivity), X_all (the random variables), value (the values of the sensitivities).

Denote by result the return of the function call, then ggplot can be called via:

```
ggplot(result, aes(x = X_all, y = value))
```

quantile_stressed 11

```
+geom_point(aes(color = factor(stress), shape = type)).
```

See Also

See sensitivity for the values of the sensitivity measures of a stressed model and importance_rank for ranking of random variables according to their sensitivities.

Examples

```
## Consider the portfolio Y = X1 + X2 + X3 + X4 + X5,
## where (X1, X2, X3, X4, X5) are correlated normally
## distributed with equal mean and different standard deviations,
## see the README for further details.
set.seed(0)
SD \leftarrow c(70, 45, 50, 60, 75)
Corr <- matrix(rep(0.5, 5^2), nrow = 5) + diag(rep(1 - 0.5, 5))
if (!requireNamespace("mvtnorm", quietly = TRUE))
   stop("Package \"mvtnorm\" needed for this function
   to work. Please install it.")
x <- mvtnorm::rmvnorm(10^5,
   mean = rep(100, 5),
   sigma = (SD %*% t(SD)) * Corr)
data <- data.frame(rowSums(x), x)</pre>
names(data) <- c("Y", "X1", "X2", "X3", "X4", "X5")
rev.stress <- stress(type = "VaR", x = data,
   alpha = c(0.75, 0.9), q_ratio = 1.1, k = 1)
sensitivity (rev.stress, type = "all")
plot_sensitivity(rev.stress, xCol = 2:6, type = "Gamma")
plot_sensitivity(rev.stress, xCol = 6, wCol = 1, type = "all")
```

quantile_stressed Sample Quantiles of a Stressed Model

Description

Provides sample quantiles for components (random variables) of a stochastic model, corresponding to distribution functions under the scenario weights.

Usage

```
quantile_stressed(object, probs = seq(0, 1, 0.25), xCol = "all", wCol = 1, type = c("quantile", "(i-1)/(n-1)", "i/(n+1)", "i/n"))
```

12 quantile_stressed

Arguments

object	A SWIM object.
probs	Vector of probabilities with values in $[0,1]$ (default = $(0,0.25,0.5,0.75,1)$).
xCol	Numeric or character vector, (names of) the columns of the underlying data of the object (default = "all").
wCol	Numeric, the column of the scenario weights of the $object (default = 1)$.
type	Character, one of "quantile", " $(i-1)/(n-1)$ ", " $i/(n+1)$ ", " i/n ", with default = "quantile". See details below.

Details

type defines the choice of algorithm used for calculating the estimate of the sample quantiles. "quantile" corresponds to the default interpolation used in quantile. Further options are "(i-1)/(n-1)", "i/(n+1)", "i/n" the inverse of the empirical distribution function, using, respectively, (wt-1)/T, wt/(T+1), wt/T, where wt is the cumulative weight and T the total weight (usually total sample size). See wtd.quantile for further details on type, on which quantile_stressed is based.

Value

Returns a matrix with estimates of the distribution quantiles at the probabilities, probs, under the scenario weights wCol.

See Also

See wtd.quantile on which the function quantile_stressed is based. See cdf for the empirical distribution function of a stressed model.

```
## example with a stress on VaR
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = c(0.9, 0.95), q_ratio = 1.05)
## stressed sample quantiles
quantile_stressed(res1, probs = seq(0.9, 0.99, 0.01), wCol = 2)</pre>
```

sensitivity 13

sens	1	t.	1	V	1	t.v

Sensitivities of a Stressed Model

Description

Provides different sensitivity measures that compare the stressed and the baseline model.

Usage

```
sensitivity(object, xCol = "all", wCol = "all", type = c("Gamma",
    "Kolmogorov", "Wasserstein", "all"), f = NULL, k = NULL)
```

Arguments

object	A SWIM object.
xCol	Numeric or character vector, (names of) the columns of the underlying data of the object (default = "all"). If $xCol = NULL$, only the transformed data $f(x)$ is considered.
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
type	Character, one of "Gamma", "Kolmogorov", "Wasserstein", "all".
f	A function, or list of functions, that, applied to \times , constitute the transformation of the data for which the sensitivity is calculated.
k	A vector or list of vectors, same length as f, indicating which columns of x each function in f operates on. When f is a list, $k[[i]]$ corresponds to the input variables of $f[[i]]$.

Details

Provides sensitivity measures that compare the stressed and the baseline model. Implemented sensitivity measures:

1. Gamma, the *Reverse Sensitivity Measure*, defined for a random variable Y and scenario weights w by

$$Gamma = (E(Y * w) - E(Y))/c,$$

where c is a normalisation constant such that $|Gamma| \le 1$, see (Pesenti et al. 2019). Loosely speaking, the Reverse Sensitivity Measure is the normalised difference between the first moment of the stressed and the baseline distributions of Y.

2. Kolmogorov, the Kolmogorov distance, defined for distribution functions F, G by

$$Kolmogorov = sup|F(x) - G(x)|.$$

Note that the Kolmogorov distance of one stress is the same for all inputs. Should be used to compare different stresses not individual components.

14 sensitivity

3. Wasserstein, the Wasserstein distance of order 1, defined for two distribution functions F, G by

$$Wasserstein = \int |F(x) - G(x)| dx.$$

If f and k are provided, the sensitivity of the transformed data is returned.

Value

A data frame containing the sensitivity measures of the stressed model with rows corresponding to different random variables. The first two rows specify the stress and type of the sensitivity measure.

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

See Also

See importance_rank for ranking of random variables according to their sensitivities, plot_sensitivity for plotting sensitivity measures and summary for summary statistics of a stressed model.

```
## example with a stress on VaR
set.seed(0)
x <- as.data.frame(cbind(
  "log-normal" = rlnorm(1000),
  "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
  alpha = c(0.9, 0.95), q_ratio = 1.05)
sensitivity(res1, wCol = 1, type = "all")
## sensitivity of log-transformed data
sensitivity(res1, wCol = 1, type = "all",
  f = list(function(x)log(x), function(x)log(x)), k = list(1,2))
## Consider the portfolio Y = X1 + X2 + X3 + X4 + X5,
## where (X1, X2, X3, X4, X5) are correlated normally
## distributed with equal mean and different standard deviations,
## see the README for further details.
set.seed(0)
SD \leftarrow c(70, 45, 50, 60, 75)
Corr <- matrix(rep(0.5, 5^2), nrow = 5) + diag(rep(1 - 0.5, 5))
if (!requireNamespace("mvtnorm", quietly = TRUE))
   stop("Package \"mvtnorm\" needed for this function
   to work. Please install it.")
x <- mvtnorm::rmvnorm(10^5,
```

stress 15

```
mean = rep(100, 5),
    sigma = (SD %*% t(SD)) * Corr)
data <- data.frame(rowSums(x), x)
names(data) <- c("Y", "X1", "X2", "X3", "X4", "X5")
rev.stress <- stress(type = "VaR", x = data,
    alpha = c(0.75, 0.9), q_ratio = 1.1, k = 1)

sensitivity(rev.stress, type = "all")
## sensitivity to sub-portfolios X1 + X2 and X3 + X4
sensitivity(rev.stress, xCol = NULL, type = "Gamma",
    f = rep(list(function(x)x[1] + x[2]), 2), k = list(c(2,3), c(4,5)))
plot_sensitivity(rev.stress, xCol = 2:6, type = "Gamma")
importance_rank(rev.stress, xCol = 2:6, type = "Gamma")</pre>
```

stress

Stressing Random Variables

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that stressed random variables fulfil given probabilistic constraints (e.g. specified values for risk measures), under the new scenario weights. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress(type = c("VaR", "VaR ES", "mean", "mean sd", "moment", "prob",
    "user"), ...)
```

Arguments

```
Type of stress, one of "VaR", "VaR ES", "mean", "mean sd", "moment", "prob", "user".Arguments to be passed on, depending on type.
```

Value

An object of class SWIM, see SWIM for details.

Author(s)

Silvana M. Pesenti

stress_mean

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

Other stress functions: stress_VaR_ES, stress_VaR, stress_mean_sd, stress_mean, stress_moment, stress_prob, stress_user

Examples

```
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res <- stress(type = "VaR", x = x,
   alpha = 0.9, q_ratio = 1.05)
summary(res)</pre>
```

stress_mean

Stressing Means

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that stressed model components (random variables) fulfil the mean constraints. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_mean(x, k, new_means, ...)
```

Arguments

X	A vector, matrix or data frame containing realisations of random variables.
	Columns of x correspond to random variables; OR
	A SWIM object, where \times corresponds to the underlying data of the SWIM object.
k	Numeric vector, the columns of x that are stressed.
new_means	Numeric vector, same length as k, containing the stressed means.
	Additional arguments to be passed to nleqslv.

stress_mean 17

Details

The function stress_mean is a wrapper for the function stress_moment. See stress_moment for details on the additional arguments to . . . and the underlying algorithm.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list, each component corresponds to a different stress and is a vector of scenario weights;
- type = "mean";
- specs, a list, each component corresponds to a different stress and contains k and new_means.

See SWIM for details.

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

See stress_mean_sd for stressing means and standard deviations jointly, and stress_moment for moment constraints.

Other stress functions: stress_VaR_ES, stress_VaR, stress_mean_sd, stress_moment, stress_prob, stress_user, stress

```
set.seed(0)
x <- data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2),
   "beta" = rbeta(1000, shape1 = 2, shape2 = 2)))
## stressing means
res1 <- stress(type = "mean", x = x, k = 1 : 3,
   new_means = c(1, 1, 0.75))
summary(res1)
res1$specs
## calling stress_mean directly
res2 <- stress_mean(x = x, k = 1 : 3,
   new_means = c(1, 1, 0.75))
summary(res2)
## See also examples in stress_moment and stress_mean_sd.</pre>
```

18 stress_mean_sd

stress_mean_sd

Stressing Mean and Standard Deviation

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that stressed model components (random variables) fulfil the mean and standard deviation constraints. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_mean_sd(x, k, new_means, new_sd, ...)
```

Arguments

х	A vector, matrix or data frame containing realisations of random variables. Columns of \times correspond to random variables; OR A SWIM object, where \times corresponds to the underlying data of the SWIM object.
k	Numeric vector, the columns of x that are stressed.
new_means	Numeric vector, same length as k, containing the stressed means.
new_sd	Numeric vector, same length as k, containing the stressed standard deviations.
	Additional arguments to be passed to nleqslv.

Details

The function stress_mean_sd is a wrapper for the function stress_moment. See stress_moment for details on the additional arguments to . . . and the underlying algorithm.

For stressing means only, see stress_mean, for stressing higher moments and functions of moments, see stress_moment.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list, each component corresponds to a different stress and is a vector of scenario weights;
- type = "mean";
- specs, a list, each component corresponds to a different stress and contains k, new_means and new_sd.

See SWIM for details.

stress_moment 19

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

```
Other stress functions: stress_VaR_ES, stress_VaR, stress_mean, stress_moment, stress_prob, stress_user, stress
```

Examples

```
set.seed(0)
x <- data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2),
   "beta" = rbeta(1000, shape1 = 2, shape2 = 2)))
## stressing mean and sd of column 1
res1 <- stress(type = "mean sd", x = x, k = 1, new_means = 0.1,
   new_sd = 1.1, method = "Newton",
   control = list(maxit = 1000, ftol = 1E-15))
summary(res1)
## calling stress_mean_sd directly
res2 <- stress_mean_sd(x = x, k = 1, new_means = 0.1,
   new_sd = 1.1, method = "Newton",
   control = list(maxit = 1000, ftol = 1E-15))
## See also examples in stress_moment.</pre>
```

stress_moment

Stressing Moments

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that stressed model components (random variables) fulfil the moment constraints. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_moment(x, f, k, m, ...)
```

20 stress_moment

Arguments

X	A vector, matrix or data frame containing realisations of random variables.
	Columns of x correspond to random variables; OR
	A SWIM object, where \boldsymbol{x} corresponds to the underlying data of the SWIM object.
f	A function, or list of functions, that, applied to $\ensuremath{\mathtt{x}},$ constitute the moment constraints.
k	A vector or list of vectors, same length as f , indicating which columns of x each
	function in f operates on.
	When f is a list, k[[i]] corresponds to the input variables of f[[i]].
m	Numeric vector, same length as f, containing the stressed moments of $f(x)$.
	Must be in the range of $f(x)$.
	Additional arguments to be passed to nleqslv.

Details

The moment constraints are given by $E^Q(f(x)) = m$, where E^Q denotes the expectation under the stressed model. stress_moment solves the subsequent set of equations with respect to theta, using nleqslv:

$$E^{Q}(f(x)) = E(f(x) * exp(theta * f(x))) = m.$$

There is no guarantee that the set of equations will have a solution, or that the solution is unique.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list, each component corresponds to a different stress and is a vector of scenario weights;
- type = "moment";
- specs, a list, each component corresponds to a different stress and contains f, k and m.

See SWIM for details.

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

See stress_mean for stressing means and stress_mean_sd for stressing mean and standard deviation jointly.

Other stress functions: stress_VaR_ES, stress_VaR, stress_mean_sd, stress_mean, stress_prob, stress_user, stress

21 stress_prob

Examples

```
set.seed(0)
x <- data.frame(cbind(
  "normal" = rnorm(1000),
  "gamma" = rgamma(1000, shape = 2),
  "beta" = rbeta(1000, shape1 = 2, shape2 = 2)))
## stressing covariance of columns 1,2 while leaving the means unchanged
res1 <- stress_moment(x = x,
  f = list(function(x)x, function(x)x, function(x)x[1] * x[2]),
  k = list(1, 2, c(1, 2)), m = c(0, 2, 0.5),
  method = "Newton", control = list(maxit = 1000, ftol = 1E-10))
## means under the stressed model
summary (res1)
apply(x, 2, stats::weighted.mean, w = get_weights(res1))
## covariance of columns 1,2 under the stressed model
stats::weighted.mean(x[, 1] * x[, 2], w = get_weights(res1))
## stressing jointly the tail probabilities of columns 1,3
res2 <- stress_moment(x = x,
  f = list(function(x)(x > 1.5), function(x)(x > 0.9)),
  k = c(1, 3), m = c(0.9, 0.9)
summary (res2)
## probabilities under the stressed model
mean((x[, 1] > 1.5) * get_weights(res2))
mean((x[, 3] > 0.9) * get_weights(res2))
```

stress_prob

Stressing Intervals

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that a stressed model component (random variable) fulfils constraints on probability of disjoint intervals. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_prob(x, prob, lower = NULL, upper, k = 1)
```

Arguments

A vector, matrix or data frame containing realisations of random variables. Columns of x correspond to random variables; OR A SWIM object, where x corresponds to the underlying data of the SWIM object.

Numeric vector, stressed probabilities corresponding to the intervals defined prob through lower and upper.

22 stress_prob

lower	Numeric vector, left endpoints of the intervals.
upper	Numeric vector, right endpoints of the intervals.
k	Numeric, the column of x that is stressed (default = 1).

Details

The intervals are treated as half open intervals, that is the lower endpoint are not included, whereas the upper endpoint are included. If upper = NULL, the intervals are consecutive and prob cumulative.

The intervals defined through lower and upper must be disjoint.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list of functions, that applied to the kth column of x, generate the vectors of scenario weights. Each component corresponds to a different stress;
- type = "prob";
- specs, a list, each component corresponds to a different stress and contains k, lower, upper and prob.

See SWIM for details.

Author(s)

Silvana M. Pesenti

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

```
\label{lem:other stress functions: stress_VaR_ES, stress_VaR, stress\_mean\_sd, stress\_mean, stress\_moment, stress\_user, stress
```

```
set.seed(0) x <- rnorm(1000) ## consecutive intervals res1 <- stress(type = "prob", x = x, prob = 0.008, upper = -2.4) # probability under the stressed model cdf(res1, xCol = 1)(-2.4)
```

stress_user 23

```
## calling stress_prob directly
## multiple intervals
res2 <- stress_prob(x = x, prob = c(0.008, 0.06),
   lower = c(-3, -2), upper = c(-2.4, -1.6))
# probability under the stressed model
cdf(res2, xCol = 1)(c(-2.4, -1.6)) - cdf(res2, xCol = 1)(c(-3, -2))</pre>
```

stress_user

User Defined Stress

Description

Returns a SWIM object with scenario weights defined by the user.

Usage

```
stress_user(x, new_weights = NULL, new_weightsfun = NULL, k = 1)
```

Arguments

Х

A vector, matrix or data frame containing realisations of random variables.

Columns of x correspond to random variables; OR

A SWIM object, where x corresponds to the underlying data of the SWIM object.

new_weights

A vector, matrix or data frame containing scenario weights. Columns of new_weights correspond to different stresses.

new_weights are normalised to have a mean of 1.

new_weightsfun

A list of functions, that applied to the kth column of x generate the vectors of the scenario weights. Each function corresponds to a stress.

The weights generated for each stress are normalised to have a mean of 1.

k

Numeric, the column of x that is stressed (default = 1).

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list, each component corresponds to a different stress and is either a vector of scenario weights (if new_weights is provided) or (if new_weights fun is provided) a function, that applied to the kth column of x, generates the vectors of scenario weights;
- type = "user";
- specs, a list, each component corresponds to a different stress and contains k.

See SWIM for details.

24 stress_VaR

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

```
Other stress functions: stress_VaR_ES, stress_VaR, stress_mean_sd, stress_mean, stress_moment, stress_prob, stress
```

Examples

```
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "user", x = x, new_weightsfun = function(x)x^2, k = 1)
## plot user defined weights against the first column of x.
plot(x$normal,get_weights(res1), pch=".")</pre>
```

stress_VaR

Stressing Value-at-Risk

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that a stressed model component (random variable) fulfils a constraint on its quantile at a given level, also known as Value-at-Risk (VaR). Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_VaR(x, alpha, q_ratio = NULL, q = NULL, k = 1)
```

Arguments

Х	A vector, matrix or data frame containing realisations of random variables. Columns of \times correspond to random variables; OR A SWIM object, where \times corresponds to the underlying data of the SWIM object.
alpha	Numeric vector, the levels of the stressed VaR.
q_ratio	Numeric vector, the ratio of the stressed VaR to the baseline VaR. If alpha and q_ratio are vectors, they must have the same length.

stress_VaR 25

- q Numeric vector, the stressed VaR at level alpha.
 - If alpha and q are vectors, they must have the same length.
- k Numeric, the column of x that is stressed (default = 1).

Details

The stressed VaR is the quantile of the chosen model component, subject to the calculated scenario weights. The VaR at level alpha of a random variable with distribution function F is defined as its left-quantile at alpha:

$$VaR_alpha = F^{-1}(alpha).$$

If one of alpha, $q(q_ratio)$ is a vector, the stressed VaR's of the kth column of x, at levels alpha, are equal to q.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list of functions, that applied to the kth column of x, generates the vectors of scenario weights. Each component corresponds to a different stress;
- type = "VaR";
- specs, a list, each component corresponds to a different stress and contains k, alpha and q.

See SWIM for details.

Author(s)

Silvana M. Pesenti

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

Other stress functions: stress_VaR_ES, stress_mean_sd, stress_mean, stress_moment, stress_prob, stress_user, stress

26 stress_VaR_ES

Examples

```
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = 0.9, q_ratio = 1.05)

## calling stress_VaR directly
## stressing "gamma"
res2 <- stress_VaR(x = x, alpha = 0.9,
   q_ratio = c(1.03, 1.05), k = 2)
get_specs(res2)
summary(res2)</pre>
```

stress_VaR_ES

Stressing Value-at-Risk and Expected Shortfall

Description

Provides weights on simulated scenarios from a baseline stochastic model, such that a stressed model component (random variable) fulfils a constraint on its Value-at-Risk (VaR) and Expected Shortfall (ES) risk measures, both evaluated at a given level. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Usage

```
stress_VaR_ES(x, alpha, q_ratio = NULL, s_ratio = NULL, q = NULL,
    s = NULL, k = 1)
```

Arguments

X	A vector, matrix or data frame containing realisations of random variables. Columns of x correspond to random variables; OR A SWIM object, where x corresponds to the underlying data of the SWIM object.
alpha	Numeric vector, the levels of the stressed VaR.
q_ratio	Numeric vector, the ratio of the stressed VaR to the baseline VaR. If alpha and q_ratio are vectors, they must have the same length.
s_ratio	Numeric, vector, the ratio of the stressed ES to the baseline ES. If q (q_ratio) and s_ratio are vectors, they must have the same length.
d	Numeric vector, the stressed VaR at level alpha. If alpha and q are vectors, they must have the same length.
S	Numeric, vector, the stressed ES at level alpha. If q and s are vectors, they must have the same length.
k	Numeric, the column of x that is stressed (default = 1).

stress_VaR_ES 27

Details

The VaR at level alpha of a random variable with distribution function F is defined as its left-quantile at alpha:

 $VaR_alpha = F^{-1}(alpha).$

The ES at level alpha of a random variable with distribution function F is defined by:

$$ES_a lpha = 1/(1 - alpha) * int_a lpha^1 VaR_u du.$$

The stressed VaR and ES are the risk measures of the chosen model component, subject to the calculated scenario weights. If one of alpha, q, s (q_ratio, s_ratio) is a vector, the stressed VaR's and ES's of the kth column of x, at levels alpha, are equal to q and s, respectively.

Value

A SWIM object containing:

- x, a data.frame containing the data;
- new_weights, a list of functions, that applied to the kth column of x, generates the vectors of scenario weights. Each component corresponds to a different stress;
- type = "VaR ES";
- specs, a list, each component corresponds to a different stress and contains k, alpha, q and s.

See SWIM for details.

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

Other stress functions: stress_VaR, stress_mean_sd, stress_mean, stress_moment, stress_prob, stress_user, stress

```
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR ES", x = x,
   alpha = c(0.9, 0.95), q_ratio = 1.05, s_ratio = 1.08)
## calling stress_VaR_ES directly</pre>
```

28 summary.SWIM

```
## stressing "gamma"
res2 <- stress_VaR_ES(x = x, alpha = 0.9,
   q_ratio = 1.03, s_ratio = c(1.05, 1.08), k = 2)
get_specs(res2)
summary(res2)</pre>
```

summary.SWIM

Summarising Stressed Models

Description

This function is a methods for an object of class SWIM. Provides summary statistics of the stochastic model, stressed using the scenario weights.

Usage

```
## S3 method for class 'SWIM'
summary(object, ..., xCol = "all", wCol = "all",
base = FALSE)
```

Arguments

object	A SWIM object.
	Additional arguments will be ignored.
xCol	Numeric or character vector, (names of) the columns of the underlying data of the object (default = "all").
wCol	Vector, the columns of the scenario weights of the object corresponding to different stresses (default = "all").
base	Logical, if TRUE, statistics under the baseline are also returned (default = "FALSE").

Value

summary. SWIM returns a list with components corresponding to different stresses. Components contain a summary statistic of each column of the data of the SWIM object:

mean	The sample mean.
sd	The sample standard deviation.
skewness	The sample skewness.
ex kurtosis	The sample excess kurtosis
1st Qu.	The 25% quantile.
Median	The median, 50% quantile.
3rd Qu.	The 75% quantile.

SWIM 29

Author(s)

Silvana M. Pesenti

See Also

```
summary, SWIM
```

Examples

```
## continuing example in stress_VaR
set.seed(0)
x <- as.data.frame(cbind(
   "normal" = rnorm(1000),
   "gamma" = rgamma(1000, shape = 2)))
res1 <- stress(type = "VaR", x = x,
   alpha = 0.9, q_ratio = 1.05)
summary(res1, xCol = "normal", base = TRUE)</pre>
```

SWIM

SWIM: A Package for Sensitivity Analysis

Description

The SWIM package provides weights on simulated scenarios from a stochastic model, such that a stressed model components (random variables) fulfil given probabilistic constraints (e.g. specified values for risk measures), under the new scenario weights. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

Details

The SWIM (Scenario Weights for Importance Measurement) package provides weights on simulated scenarios from a stochastic model, such that stressed random variables fulfil given probabilistic constraints (e.g. specified values for risk measures), under the new scenario weights. Scenario weights are selected by constrained minimisation of the relative entropy to the baseline model.

The SWIM package is based on the *reverse sensitivity framework* developed by (Pesenti et al. 2019). Consider the random vector X = (X1, ..., Xn). Let P represent the probability measure under which all simulated scenarios have the same probability. Then, for a random variable Xi, the package solves:

```
minD(P|Q)s.t.constraints on the distribution of Xiunder Q,
```

where D(P|Q) is the Kullback-Leibler divergence (relative entropy) between P and Q. The solution is formed by the scenario weights representing the Radon-Nikodym derivative dQ / dP. The weighting generates a model for which the joint distribution of $(X1, \ldots, Xn)$ is stressed.

30 SWIM

Different elements of X can be understood as inputs or outputs of a model. For example, consider a model Y = g(Z) with input vector Z = (Z1, ..., Z(n-1)). One can then identify X1 = Y and X1 = Z1, ..., Xn = Z(n-1). Subsequently, the user of the SWIM package can stress the model output or any of the inputs, measuring the resulting impact on the distributions of other variables.

Stresses

Scenario weights for the following stresses are provided:

```
calls one of the functions below by using type
stress
                     for stressing the VaR (type = "VaR")
stress_VaR
                     for stressing the VaR and ES jointly (type = "VaR ES")
stress_VaR_ES
                     for stressing means (type = "mean")
stress_mean
stress_mean_sd
                     for stressing means and standard deviations (type = "mean sd")
                     for stressing moments (type = "moment")
stress_moment
stress_prob
                     for stressing the probabilities of intervals (type = "prob")
                     for user defined scenario weights (type = "user")
stress_user
```

A SWIM object

An object of class SWIM contains a list of:

- x, a data.frame containing realisations of a random vector;
- new_weights, a list, each component corresponds to a different stress and is either a vector of scenario weights or a function, that applied to the kth column of x, generates the vectors of scenario weights;
- type: a list, each component corresponds to a different stress and specifies the type of the stress:
- specs, a list, each component corresponds to a different stress and contains a list with the specifications of what has been stressed. Specifications depend on the type of stress:
 - type = "VaR": k, the column of x on which the stress is applied to; alpha, the level of the stressed VaR; q, the stressed VaR at level alpha.
 - type = "VaR ES": k, the column of x on which the stress is applied to; alpha, the level of the stressed VaR and ES; q, the stressed VaR at level alpha.
 - type = "mean": k, the columns of x on which the stress is applied to; new_means, the stressed means.
 - type = "mean sd": k, the columns of x on which the stress is applied to; new_means, the stressed means; new_sd, the stressed standard deviations. s, the stressed ES at level alpha.
 - type = "moment": f, the list of functions, that, applied to x, constitute the moment constraints; k, the columns of x on which each function in f operates on; m, the stressed moments of f(x).
 - type = "prob": k, the column of x on which the stress is applied to; lower, the left endpoints of the intervals; upper, the right endpoints of the intervals; prob, stressed probabilities corresponding to the intervals defined through lower and upper.
 - type = "user": k, the column of x on which the stress is applied to.

References

Pesenti SM, Millossovich P, Tsanakas A (2019). "Reverse sensitivity testing: What does it take to break the model?" *European Journal of Operational Research*, **274**(2), 654–670.

Csiszar I (1975). "I-divergence geometry of probability distributions and minimization problems." *The Annals of Probability*, 146–158.

See Also

See get_data for extracting the data, x; get_weights for extracting the scenario weights, new_weights; get_weightsfun for extracting the functions generating the scenario weights; and get_specs for extracting the specifications of the stress on an object of class SWIM.