# Lesson 2

# Validator selection and consensus

# Proof-of-Staked Authority (PoSA) consensus ("Parlia")

This is a combination of Proof of Authority and Proof of Stake

- 1. Blocks are produced by a limited set of validators;
- 2. Validators take turns to produce blocks in a PoA manner, similar to Ethereum's Clique consensus design
- 3. Validator set are elected in and out based on staking-based governance;

A fast finality mechanism similar to that used in ethereum was introduced in BEP 126.

# Finalising a block

- 1. A block is proposed by a validator and propagated to other validators.
- 2. Validators use their BLS private key to sign for the block as a vote message.
- 3. Gather the votes from validators into a pool.
- 4. Aggregate the BLS signature if its direct parent block has gotten enough votes when proposing a new block.
- 5. Set the aggregated vote attestation into the extra field of the new block's header.
- 6. Validators and full nodes who received the new block with the direct parent block's attestation can justify the direct parent block.
- 7. If there are two continuous blocks have been justified, then the previous one is finalized.

BLS stands for Boneh-Lynn-Shacham Signatures See

# **BlockExplorers**

# **Mainnet**

- BscScan https://bscscan.com/
- Bitquery <a href="https://explorer.bitquery.io/bsc">https://explorer.bitquery.io/bsc</a>
- BSCTrace <a href="https://bsctrace.com/">https://bsctrace.com/</a>

# **Testnet**

- BscScan <a href="https://testnet.bscscan.com/">https://testnet.bscscan.com/</a>
- Bitquery <a href="https://explorer.bitquery.io/bsc">https://explorer.bitquery.io/bsc</a> testnet

## **Faucets**

Test net Faucet

# **Introduction to Remix**

Remix is an IDE for Solidity development. It can run in the browser, or on the desktop.

Browser: <a href="https://remix.ethereum.org/">https://remix.ethereum.org/</a>


Desktop: npm install -g @remix-project/remixd

Remix documentation



# **Plugins**

The panel on the left allows us to add plugins




File Explorer

If we select the file icon in the plugin panel



we will see the file explorer in the middle panel

The middle panel is the file explorer, here we can navigate between the contracts we are working on.



#### **Editor Panel**

Here we edit our smart contracts

#### **Ouptut panel**

This shows the activity on our local blockchain and the results of our transactions

```
Welcome to Remix 0.27.0

Your files are stored in indexedDB, 3.66 MB / 2 GB used

You can use this terminal to:

Check transactions details and start debugging.

Execute JavaScript scripts:

Input a script directly in the command line interface

Select a JavaScript file in the file explorer and then run \`remix.execute()\` or \`remix.exeCurrent()\` in the command line interface

Right click on a JavaScript file in the file explorer and then click \`Run\`

The following libraries are accessible:

**web3 version 1.5.2*


**ethers.js*


**remix*

Type the library name to see available commands.
```

#### Compiling the contract


Choosing the compile icon in the left hand panel will display the compiler panel






#### **Deploying a contract**

Chosing the deploy and run transactions icon gives us a panel that allows us to deploy our compiled transaction to a network and run transactions.





# Choosing the network / environment




This provides a local in browser blockchain, this is the simplest environment when initially developing contracts.

We deploy the contract with the deploy button, you may need to find the correct contract in the drop down list.




If the contract deploys correctly, you will see the results in the output window.



Once it has deployed, you will see details of the contract in the deploy panel

You can interact with your contracts from here by sending transactions Note that the contract has an address on the blockchain similar to a wallet address



# **Solidity part 1**

#### Introduction

# How to define the Solidity compiler version?

```
// Any compiler version from the 0.8 release (= 0.8.x)
pragma solidity ^0.8.0;

// Greater than version 0.7.6, less than version 0.8.4
pragma solidity >0.7.6 <0.8.4;</pre>
```

#### How to define a contract?

Use the keyword contract followed by your contract name.

```
contract Score {
    // You will start writing your code here =)
}
```

How to write a variable in Solidity?

A contract would need some state. We are going to declare a new variable that will hold our score.

```
contract Score {
   uint score = 5;
}
```

#### **Important!**

Solidity is a statically typed language. So you always need to **declare the** variable type (here uint) before the variable name.

uint defines an unsigned integer of 256 bits by default.

You can also specify the number of bits, by range of 8 bits. Here are some examples below:

Туре	Number range
uint8	0 to 255
uint16	0 to 65,535
uint32	0 to 4,294,967,295
uint64	0 to 18,446,744,073,709,551,615
uint128	0 to 2^128
uint256	0 to 2^256

#### **Getters and Setters**

We need a way to write and retrieve the value of our score. We achieve this by creating a **getter** and **setter** functions.

In Solidity, you declare a function with the keyword function followed the function name (here getScore()).

```
contract Score {
    uint score = 5;

    function getScore() returns (uint) {
        return score;
    }

    function setScore(uint new_score) {
        score = new_score;
    }
}
```

#### Getter function using return

<u>Definiton</u>: In Solidity, a **getter** is a function that returns a value.

To return a value from a function (here our score), you use the following keywords:

- In the function definition: returns + variable type returned between parentheses for example (uint)
- In the function body: return followed by what you want to return for example return score; or return 137;

### Setter function: pass parameters to our function

<u>Definition</u>: In Solidity, a **setter** is a function that modifies the value of a variable (**modifies the state of the contract**). To creates a **setter**, you must specify the **parameters** when you declare your function.

After your function name, specifies between parentheses 1) the variable type (uint) and 2) the variable name (new\_score)

#### **Compiler Error:**

Try entering this code in Remix. We are still not there. The compiler should give you the following error:

```
Syntax Error: No visibility specified. Did you intend to add "public" ?
```

Therefore, we need to specify a visibility for our function. We are going to cover the notion of **visibility** in the next section.

# **Function visibility**

# Introduction

To make our functions work, we need to specify their visibility in the contract.

Add the keyword public after your function name.

```
contract Score {
    uint score = 5;
    function getScore() public returns (uint) {
        return score;
    }
    function setScore(uint new_score) public {
        score = new_score;
    }
}
```

What does the public keyword mean?

There are four types of *visibility* for functions in Solidity: public, private, external and internal. The table below explains the difference.

Visibility	Contract itself	Derived Contracts	External Contracts	External Addresses
public	<b>✓</b>	<b>✓</b>	<b>✓</b>	<b>✓</b>
private	<b>✓</b>			
internal	<b>✓</b>	<b>✓</b>		
external			✓	<b>✓</b>

#### **Learn More:**

- Those keywords are also available for state variables, except for external.
- For simplicity, you could add the public keyword to the variable. This would automatically create a **getter** for the variable. You would not need to create a **getter** function manually. (see code below)

uint score public;

Try entering that in Remix. We are still not getting there! You should receive the following Warning on Remix.

## **Compiler Warning:**

Warning: Function state mutability can be restricted to view.

#### View vs Pure ?

- view functions can **only read** from the contract storage. They can't modify the contract storage. Usually, you will use view for getters.
- pure functions can **neither read nor modify** the contract storage. They are only used for *computation* (like mathematical operations).

Because our function <code>getScore()</code> only reads from the contract state, it is a <code>view</code> function.

```
function getScore() public view returns (uint) {
   return score;
}
```

# **Adding Security with Modifiers**

Our contract has a security issue: Anyone can modify the score.

Solidity provides a global variable msg, that refers to the address that interacts with the contract's functions. The msg variables offers two associated fields:

- msg.sender: returns the address of the caller of the function.
- msg.value: returns the value in Wei of the amount of Ether sent to the function.

#### How to restrict a function to a specific caller?

We should have a feature that enables only certain addresses to change the score (your address). To achieve this, we will introduce the notion of **modifiers**.

<u>Definition</u>: A <u>modifier</u> is a special function that enables us to change the behaviour of functions in Solidity. It is mostly used to automatically check a condition before executing a function.

We will use the following modifier to restrict the function to only the *contract* owner.

```
address owner;

modifier only0wner {
    if (msg.sender == owner) {
        _;
    }
}

function setScore(uint new_score) public only0wner {
    score = new_score;
}
```

The modifier works with the following flow:

- 1. Check that the address of the caller (msg.sender) is equal to owner address.
- 2. If 1) is true, it passes the check. The \_; will be replaced by the function body where the modifier is attached.

A modifier can receive arguments like functions. Here is an example of a modifier that requires the caller to send a specific amount of Ether.

```
modifier Fee(uint fee) {
    if (msg.value == fee) {
        _;
    }
}
```

However, we still haven't defined who the owner is. We will define that in the **constructor**.

#### Constructor

<u>Definition</u>: A **constructor** is a function that is **executed only once** when the contract is deployed on the Ethereum blockchain.

In the code below, we define the contract owner:

```
contract Score {
   address owner;

   constructor() {
      owner = msg.sender;
   }
}
```

#### **Learn More:**

Constructors are optional. If there is no constructor, the contract will assume the default constructor, which is equivalent to `constructor () {}`

## Warning!

Prior to version 0.4.22, constructors were defined as function with the same name as the contract. This syntax was deprecated and is not allowed in version 0.5.0.

#### **Events**

Events are only used in Web3 to output some return values. They are a way to show the changes made into a contract.

Events act like a log statement. You declare **Events** in Solidity as follow:

```
// Outside a function
event myEvent(type1, type2, ...);

// Inside a function
emit myEvent(param1, param2, ...);
```

To illustrate, we are going to create an event to display the new score set. This event will be passed within our setScore() function. Remember that you should pass the score after you have set the new variable.

```
event Score_set(uint);

function setScore(uint new_score) public only0wner {
    score = new_score;
    emit Score_set(new_score);
}
```

You can also use the keyword indexed in front of the parameter's types in the event definition.

It will create an **index** that will enable to search for events via Web3 in your frontend.

```
event Score_set(uint indexed);
```

#### Note!

event can be used with any functions types (public, private, internal or external). However, they are **only visible outside the contract**. events are are not visible internally by Solidity. You cannot read an event. So a function cannot read the event emitted by another function for instance.

# Learn more!

When you call an event in Solidity, the arguments passed to it are stored in the transaction's log - a special data structure in the Ethereum blockchain. These logs are associated with the address of the contract, incorporated into the blockchain, and stay there as long as a block is accessible.

# **References Data Types: Mappings**

Mappings are another important complex data type used in Solidity. They are useful for association, such as associating an address with a balance or a score. You define a mapping in Solidity as follow:

```
mapping(KeyType => ValueType) mapping_name;
```

You can find below a summary of all the datatypes supported for the key and the value in a mapping.

Туре	Key	Value
int/uint	<b>✓</b>	<b>✓</b>
string	<b>✓</b>	<b>✓</b>
bytes	<b>✓</b>	<b>✓</b>
address	<b>✓</b>	<b>✓</b>
struct	Х	<b>✓</b>
mapping	Х	<b>✓</b>
enums	Х	<b>✓</b>
contract	Х	<b>✓</b>
fixed-sized array	<b>✓</b>	<b>✓</b>
dynamic-size array	X	<b>✓</b>
variable	X	Х

You can access the value associated with a key in a mapping by specifying the key name inside square brackets [] as follows: mapping\_name[key].

Our smart contract will store a mapping of all the user's addresses and their associated score. The function <code>getUserScore(address \_user)</code> enables to retrieve the score associated to a specific user's address.

```
mapping(address => uint) score_list;
```

```
function getUserScore(address user) public view returns (uint) {
   return score_list[user];
}
```

## Tips:

you can use the keyword public in front of a mapping name to create automatically a **getter** function in Solidity, as follows:

```
mapping(address => uint) public score_list;
```

#### **Learn More:**

In Solidity, mappings do not have a length, and there is no concept of a key set.

Mappings are virtually initialised in Solidity, such that every possible key exists and is mapped to a value which is the default value for that datatype.

# **Reference Data Types: Arrays**

Arrays are also an important part of Solidity. You have two types of arrays (Trepresents the data type and kithe maximum number of elements):

Fixed size array : T[k]Dynamic size array : T[]

```
uint[] all_possible_number;
uint[9] one_digit_number;
```

In Solidity, arrays are ordered numerically. Array indices are zero based. So the index of the 1st element will be **0**. You access an element in an array in the same way than you do for a mapping:

```
uint my_score = score_list[owner];
```

You can also used the following two methods to work with arrays:

```
array_name.length : returns the number of elements the array holds.
array_name.push(new_element) : adds a new element at the end of the array.
```

#### **Structs**

We can build our own datatypes by combining simpler datatypes together into more complex types using structs.

We use the keyword **struct**, followed by the structure name, then the fields that make up the structure.

For example:

```
struct Funder {
   address addr;
   uint amount;
}
```

Here we have created a datatype called Funder, that is composed of an address and a uint.

We can now declare a variable of that type

```
Funder giver;
```

and reference the elements using dot notation

```
giver.addr = address
(0xBA7283457B0A138890F21DE2ebCF1AfB9186A2EF);
giver.amount = 2500;
```

The size of the structure has to be finite, this imposes restrictions on the elements that can be included in the struct.

#### Example of a contract using reference datatypes

```
pragma solidity ^0.8.0;

contract ListExample {
   struct DataStruct {
    address userAddress;
    uint userID;
   }
```

```
DataStruct[] public records;
  function createRecord1(address _userAddress, uint _userID)
public {
   DataStruct memory newRecord;
    newRecord.userAddress = userAddress;
    newRecord.userID = _userID;
  }
  function createRecord2(address _userAddress, uint _userID)
public {
records.push(DataStruct({userAddress:_userAddress,userID:_userID})
));
 }
 function getRecordCount() public view returns(uint recordCount)
    return records.length;
 }
}
```