

Red Hat Satellite 6.6

Hammer CLI Guide

Using Hammer, the Satellite's CLI tool

Last Updated: 2020-01-28

Red Hat Satellite 6.6 Hammer CLI Guide

Using Hammer, the Satellite's CLI tool

Red Hat Satellite Documentation Team satellite-doc-list@redhat.com

Legal Notice

Copyright © 2020 Red Hat, Inc.

The text of and illustrations in this document are licensed by Red Hat under a Creative Commons Attribution–Share Alike 3.0 Unported license ("CC-BY-SA"). An explanation of CC-BY-SA is available at

http://creativecommons.org/licenses/by-sa/3.0/

. In accordance with CC-BY-SA, if you distribute this document or an adaptation of it, you must provide the URL for the original version.

Red Hat, as the licensor of this document, waives the right to enforce, and agrees not to assert, Section 4d of CC-BY-SA to the fullest extent permitted by applicable law.

Red Hat, Red Hat Enterprise Linux, the Shadowman logo, the Red Hat logo, JBoss, OpenShift, Fedora, the Infinity logo, and RHCE are trademarks of Red Hat, Inc., registered in the United States and other countries.

Linux ® is the registered trademark of Linus Torvalds in the United States and other countries.

Java [®] is a registered trademark of Oracle and/or its affiliates.

XFS [®] is a trademark of Silicon Graphics International Corp. or its subsidiaries in the United States and/or other countries.

MySQL [®] is a registered trademark of MySQL AB in the United States, the European Union and other countries.

Node.js ® is an official trademark of Joyent. Red Hat is not formally related to or endorsed by the official Joyent Node.js open source or commercial project.

The OpenStack [®] Word Mark and OpenStack logo are either registered trademarks/service marks or trademarks/service marks of the OpenStack Foundation, in the United States and other countries and are used with the OpenStack Foundation's permission. We are not affiliated with, endorsed or sponsored by the OpenStack Foundation, or the OpenStack community.

All other trademarks are the property of their respective owners.

Abstract

This document describes how to use the Hammer CLI tool to configure and manage Red Hat Satellite.

Table of Contents

CHAPTER 1. INTRODUCTION TO HAMMER	16
1.1. GETTING HELP	16
1.2. AUTHENTICATION	16
1.2.1. Hammer Authentication Session	17
1.2.2. Hammer Configuration File	17
1.2.3. Command Line	18
1.3. USING STANDALONE HAMMER	18
1.4. SETTING A DEFAULT ORGANIZATION AND LOCATION	19
1.5. CONFIGURING HAMMER	19
1.6. CONFIGURING HAMMER LOGGING	20
1.7. INVOKING THE HAMMER SHELL	21
1.8. GENERATING FORMATTED OUTPUT	21
1.9. HIDING HEADER OUTPUT FROM HAMMER COMMANDS	21
1.10. TROUBLESHOOTING WITH HAMMER	22
CHAPTER 2. REFERENCE	23
2.1. HAMMER	23
2.2. HAMMER ACTIVATION-KEY	25
2.2.1. hammer activation-key add-host-collection	25
2.2.2. hammer activation-key add-subscription	26
2.2.3. hammer activation-key content-override	26
2.2.4. hammer activation-key copy	26
2.2.5. hammer activation-key create	27
2.2.6. hammer activation-key delete	27
2.2.7. hammer activation-key host-collections	27
2.2.8. hammer activation-key info	28
2.2.9. hammer activation-key list	28
2.2.10. hammer activation-key product-content	29
2.2.11. hammer activation-key remove-host-collection	29
2.2.12. hammer activation-key remove-subscription	29
2.2.13. hammer activation-key subscriptions	30
2.2.14. hammer activation-key update	30
2.3. HAMMER ADMIN	31
2.3.1. hammer admin logging	31
2.4. HAMMER ANSIBLE	32
2.4.1. hammer ansible roles	32
2.4.1.1. hammer ansible roles delete	32
2.4.1.2. hammer ansible roles fetch	33
2.4.1.3. hammer ansible roles import	33
2.4.1.4. hammer ansible roles info	34
2.4.1.5. hammer ansible roles list	34
2.4.1.6. hammer ansible roles obsolete	34
2.4.1.7. hammer ansible roles play-hostgroups	35
2.4.1.8. hammer ansible roles play-hosts	35
2.4.2. hammer ansible variables	36
2.4.2.1. hammer ansible variables add-matcher	36
2.4.2.2. hammer ansible variables create	36
2.4.2.3. hammer ansible variables delete	37
2.4.2.4. hammer ansible variables import	38
2.4.2.5. hammer ansible variables info	38
2.4.2.6. hammer ansible variables list	38

2.4.2.7. hammer ansible variables obsolete	39
2.4.2.8. hammer ansible variables remove-matcher	39
2.4.2.9. hammer ansible variables update	39
2.5. HAMMER ARCHITECTURE	40
2.5.1. hammer architecture add-operatingsystem	41
2.5.2. hammer architecture create	41
2.5.3. hammer architecture delete	41
2.5.4. hammer architecture info	42
2.5.5. hammer architecture list	42
2.5.6. hammer architecture remove-operatingsystem	42
2.5.7. hammer architecture update	43
2.6. HAMMER ARF-REPORT	43
2.6.1. hammer arf-report delete	44
2.6.2. hammer arf-report download	44
2.6.3. hammer arf-report download-html	44
2.6.4. hammer arf-report info	45
2.6.5. hammer arf-report list	45
2.7. HAMMER AUDIT	46
2.7.1. hammer audit info	46
2.7.2. hammer audit list	46
2.8. HAMMER AUTH	47
2.8.1. hammer auth login	48
2.8.2. hammer auth logout	48
2.8.3. hammer auth status	48
2.9. HAMMER AUTH-SOURCE	48
2.9.1. hammer auth-source Idap	49
2.9.1.1. hammer auth-source Idap create	49
2.9.1.2. hammer auth-source Idap delete	50
2.9.1.3. hammer auth-source Idap info	51
2.9.1.4. hammer auth-source Idap list	51
2.9.1.5. hammer auth-source Idap update	51
2.9.2. hammer auth-source list	52
2.10. HAMMER BOOTDISK	53
2.10.1. hammer bootdisk generic	53
2.10.2. hammer bootdisk host	54
2.10.3. hammer bootdisk subnet	54
2.11. HAMMER CAPSULE	54
2.11.1. hammer capsule content	55
2.11.1.1. hammer capsule content add-lifecycle-environment	55
2.11.1.2. hammer capsule content available-lifecycle-environments	56
2.11.1.3. hammer capsule content cancel-synchronization	56
2.11.1.4. hammer capsule content info	56
2.11.1.5. hammer capsule content lifecycle-environments	56
2.11.1.6. hammer capsule content remove-lifecycle-environment	57
2.11.1.7. hammer capsule content synchronization-status	57
2.11.1.8. hammer capsule content synchronize	57
2.11.2. hammer capsule create	58
2.11.3. hammer capsule import, classes	59
2.11.4. hammer capsule import-classes	59
2.11.5. hammer capsule list	59
2.11.6. hammer capsule list	60 60
2.11.7. hammer capsule refresh-features 2.11.8. hammer capsule update	61
Z.H.O. Halliller Capsule apaate	OI.

2.12. HAMMER COMPUTE-PROFILE	61
2.12.1. hammer compute-profile create	62
2.12.2. hammer compute-profile delete	62
2.12.3. hammer compute-profile info	63
2.12.4. hammer compute-profile list	63
2.12.5. hammer compute-profile update	63
2.12.6. hammer compute-profile values	64
2.12.6.1. hammer compute-profile values add-interface	64
2.12.6.2. hammer compute-profile values add-volume	65
2.12.6.3. hammer compute-profile values create	66
2.12.6.4. hammer compute-profile values remove-interface	69
2.12.6.5. hammer compute-profile values remove-volume	69
2.12.6.6. hammer compute-profile values update	70
2.12.6.7. hammer compute-profile values update-interface	72
2.12.6.8. hammer compute-profile values update-volume	74
2.13. HAMMER COMPUTE-RESOURCE	75
2.13.1. hammer compute-resource clusters	75
2.13.2. hammer compute-resource create	76
2.13.3. hammer compute-resource delete	77
2.13.4. hammer compute-resource flavors	77
2.13.5. hammer compute-resource folders	77
2.13.6. hammer compute-resource image	78
2.13.6.1. hammer compute-resource image available	78
2.13.6.2. hammer compute-resource image create	78
2.13.6.3. hammer compute-resource image delete	79
2.13.6.4. hammer compute-resource image info	79
2.13.6.5. hammer compute-resource image list	80
2.13.6.6. hammer compute-resource image update	80
2.13.7. hammer compute-resource images	81
2.13.8. hammer compute-resource info	81
2.13.9. hammer compute-resource list	82
2.13.10. hammer compute-resource networks	82
2.13.11. hammer compute-resource resource-pools	83
2.13.12. hammer compute-resource security-groups	83
2.13.13. hammer compute-resource storage-domains	83
2.13.14. hammer compute-resource storage-pods	84
2.13.15. hammer compute-resource update	84
2.13.16. hammer compute-resource zones	85
2.14. HAMMER CONFIG-GROUP	86
2.14.1. hammer config-group create	86
2.14.2. hammer config-group delete	86
2.14.3. hammer config-group info	87
2.14.4. hammer config-group list	87
2.14.5. hammer config-group update	87
2.15. HAMMER CONFIG-REPORT	88
2.15.1. hammer config-report delete	88
2.15.2. hammer config-report info	89
2.15.3. hammer config-report list	89
2.16. HAMMER CONTENT-VIEW	90
2.16.1. hammer content-view add-repository	90
2.16.2. hammer content-view add-version	91
2.16.3. hammer content-view component	91
2.16.3.1. hammer content-view component add	91

2.16.3.2. hammer content-view component list	92
2.16.3.3. hammer content-view component remove	92
2.16.3.4. hammer content-view component update	93
2.16.4. hammer content-view copy	93
2.16.5. hammer content-view create	94
2.16.6. hammer content-view delete	94
2.16.7. hammer content-view filter	94
2.16.7.1. hammer content-view filter add-repository	95
2.16.7.2. hammer content-view filter create	95
2.16.7.3. hammer content-view filter delete	96
2.16.7.4. hammer content-view filter info	96
2.16.7.5. hammer content-view filter list	97
2.16.7.6. hammer content-view filter remove-repository	97
2.16.7.7. hammer content-view filter rule	97
2.16.7.7.1. hammer content-view filter rule create	98
2.16.7.7.2. hammer content-view filter rule delete	99
2.16.7.7.3. hammer content-view filter rule info	99
2.16.7.7.4. hammer content-view filter rule list	99
2.16.7.7.5. hammer content-view filter rule update	100
2.16.7.8. hammer content-view filter update	100
2.16.8. hammer content-view info	101
2.16.9. hammer content-view list	101
2.16.10. hammer content-view publish	102
2.16.11. hammer content-view puppet-module	102
2.16.11.1. hammer content-view puppet-module add	103
2.16.11.2. hammer content-view puppet-module list	103
2.16.11.3. hammer content-view puppet-module remove	104
2.16.12. hammer content-view purge	104
2.16.13. hammer content-view remove	104
2.16.14. hammer content-view remove-from-environment	105
2.16.15. hammer content-view remove-repository	106
2.16.16. hammer content-view remove-version	106
2.16.17. hammer content-view update	106
2.16.18. hammer content-view version	107
2.16.18.1. hammer content-view version delete	107
2.16.18.2. hammer content-view version export	108
2.16.18.3. hammer content-view version export-legacy	108
2.16.18.4. hammer content-view version import	109
2.16.18.5. hammer content-view version incremental-update	109
2.16.18.6. hammer content-view version info	110
2.16.18.7. hammer content-view version list	111
2.16.18.8. hammer content-view version promote	111
2.16.18.9. hammer content-view version republish-repositories	112
2.17. HAMMER DEFAULTS	112
2.17.1. hammer defaults add	113
2.17.2. hammer defaults delete	113
2.17.3. hammer defaults list	113
2.17.4. hammer defaults providers	113
2.18. HAMMER DISCOVERY	114
2.18.1. hammer discovery auto-provision	114
2.18.2. hammer discovery delete	114
2.18.3. hammer discovery facts	115
2.18.4. hammer discovery info	115

2.18.5. hammer discovery list	116
2.18.6. hammer discovery provision	116
2.18.7. hammer discovery reboot	117
2.18.8. hammer discovery refresh-facts	118
2.19. HAMMER DISCOVERY-RULE	118
2.19.1. hammer discovery-rule create	119
2.19.2. hammer discovery-rule delete	119
2.19.3. hammer discovery-rule info	120
2.19.4. hammer discovery-rule list	120
2.19.5. hammer discovery-rule update	120
2.20. HAMMER DOCKER	121
2.20.1. hammer docker manifest	122
2.20.1.1. hammer docker manifest info	122
2.20.1.2. hammer docker manifest list	122
2.20.2. hammer docker tag	123
2.20.2.1 hammer docker tag info	123
2.20.2.1. hammer docker tag lind	124
2.21. HAMMER DOMAIN	
2.21. hammer domain create	124
	125
2.21.2. hammer domain delete	126
2.21.3. hammer domain delete-parameter	126
2.21.4. hammer domain info	126
2.21.5. hammer domain list	127
2.21.6. hammer domain set-parameter	127
2.21.7. hammer domain update	128
2.22. HAMMER ENVIRONMENT	128
2.22.1. hammer environment create	129
2.22.2. hammer environment delete	129
2.22.3. hammer environment info	130
2.22.4. hammer environment list	130
2.22.5. hammer environment sc-params	131
2.22.6. hammer environment update	131
2.23. HAMMER ERRATUM	132
2.23.1. hammer erratum info	132
2.23.2. hammer erratum list	133
2.24. HAMMER EXPORT-TEMPLATES	133
2.25. HAMMER FACT	134
2.25.1. hammer fact list	135
2.26. HAMMER FILE	135
2.26.1. hammer file info	136
2.26.2. hammer file list	136
2.27. HAMMER FILTER	137
2.27.1. hammer filter available-permissions	137
2.27.2. hammer filter available-resources	138
2.27.3. hammer filter create	138
2.27.4. hammer filter delete	139
2.27.5. hammer filter info	139
2.27.6. hammer filter list	140
2.27.7. hammer filter update	140
2.28. HAMMER FOREIGN-INPUT-SET	141
2.28.1. hammer foreign-input-set create	141
2.28.2. hammer foreign-input-set delete	142
2.28.3. hammer foreign-input-set info	142

2.28.4. hammer foreign-input-set list	143
2.28.5. hammer foreign-input-set update	143
2.29. HAMMER FULL-HELP	144
2.30. HAMMER GLOBAL-PARAMETER	144
2.30.1. hammer global-parameter delete	144
2.30.2. hammer global-parameter list	145
2.30.3. hammer global-parameter set	145
2.31. HAMMER GPG	145
2.31.1. hammer gpg create	146
2.31.2. hammer gpg delete	146
2.31.3. hammer gpg info	146
2.31.4. hammer gpg list	147
2.31.5. hammer gpg update	147
2.32. HAMMER HOST	147
2.32.1. hammer host ansible-roles	148
2.32.1.1. hammer host ansible-roles assign	149
2.32.1.2. hammer host ansible-roles list	149
2.32.1.3. hammer host ansible-roles play	149
2.32.2. hammer host boot	150
2.32.3. hammer host config-reports	150
2.32.4. hammer host create	151
2.32.5. hammer host delete	157
2.32.6. hammer host delete-parameter	157
2.32.7. hammer host disassociate	157
2.32.8. hammer host enc-dump	158
2.32.9. hammer host errata	158
2.32.9.1. hammer host errata apply	158
2.32.9.2. hammer host errata info	159
2.32.9.3. hammer host errata list	159
2.32.9.4. hammer host errata recalculate	159
2.32.10. hammer host facts	160
2.32.11. hammer host info	160
2.32.12. hammer host interface	161
2.32.12.1. hammer host interface create	161
2.32.12.2. hammer host interface delete	162
2.32.12.3. hammer host interface info	163
2.32.12.4. hammer host interface list	163
2.32.12.5. hammer host interface update	164
2.32.13. hammer host list	165
2.32.14. hammer host package	167
2.32.14.1. hammer host package install	168
2.32.14.2. hammer host package list	168
2.32.14.3. hammer host package remove	168
2.32.14.4. hammer host package upgrade	169
2.32.14.5. hammer host package upgrade-all	169
2.32.15. hammer host package-group	169
2.32.15. hammer host package-group install	170
	170
2.32.15.2. hammer host puppet-classes	170
2.32.16. hammer host puppet-classes	170
2.32.17. hammer host puppetrun 2.32.18. hammer host reboot	171
	171
2.32.19. hammer host rebuild-config	172
2.32.20. hammer host reports	1/2

2.32.21. hammer host reset	173
2.32.22. hammer host sc-params	173
2.32.23. hammer host set-parameter	174
2.32.24. hammer host smart-variables	174
2.32.25. hammer host start	175
2.32.26. hammer host status	175
2.32.27. hammer host stop	175
2.32.28. hammer host subscription	176
2.32.28.1. hammer host subscription attach	176
2.32.28.2. hammer host subscription auto-attach	176
2.32.28.3. hammer host subscription content-override	177
2.32.28.4. hammer host subscription product-content	177
2.32.28.5. hammer host subscription register	177
2.32.28.6. hammer host subscription remove	178
2.32.28.7. hammer host subscription unregister	178
2.32.29. hammer host update	178
2.33. HAMMER HOST-COLLECTION	184
2.33.1. hammer host-collection add-host	185
2.33.2. hammer host-collection copy	185
2.33.3. hammer host-collection create	186
2.33.4. hammer host-collection delete	186
2.33.5. hammer host-collection erratum	186
2.33.5.1. hammer host-collection erratum install	187
2.33.6. hammer host-collection hosts	187
2.33.7. hammer host-collection info	190
2.33.8. hammer host-collection list	190
2.33.9. hammer host-collection package	190
2.33.9.1. hammer host-collection package install	191
2.33.9.2. hammer host-collection package remove	191
2.33.9.3. hammer host-collection package update	191
2.33.10. hammer host-collection package-group	192
2.33.10.1. hammer host-collection package-group install	192
2.33.10.2. hammer host-collection package-group remove	193
2.33.10.3. hammer host-collection package-group update	193
2.33.11. hammer host-collection remove-host	193
2.33.12. hammer host-collection update	194
2.34. HAMMER HOSTGROUP	194
2.34.1. hammer hostgroup ansible-roles	195
2.34.1.1. hammer hostgroup ansible-roles assign	195
2.34.1.2. hammer hostgroup ansible-roles list	196
2.34.1.3. hammer hostgroup ansible-roles play	196
2.34.2. hammer hostgroup create	196
2.34.3. hammer hostgroup delete	198
2.34.4. hammer hostgroup delete-parameter	199
2.34.5. hammer hostgroup info	199
2.34.6. hammer hostgroup list	199
2.34.7. hammer hostgroup puppet-classes	200
2.34.8. hammer hostgroup rebuild-config	201
2.34.9. hammer hostgroup sc-params	201
2.34.10. hammer hostgroup set-parameter	202
2.34.11. hammer hostgroup smart-variables	202
2.34.12. hammer hostgroup update	203
2.35. HAMMER IMPORT-TEMPLATES	205

2.36. HAMMER JOB-INVOCATION	206
2.36.1. hammer job-invocation cancel	207
2.36.2. hammer job-invocation create	207
2.36.3. hammer job-invocation info	208
2.36.4. hammer job-invocation list	208
2.36.5. hammer job-invocation output	208
2.36.6. hammer job-invocation rerun	209
2.37. HAMMER JOB-TEMPLATE	209
2.37.1. hammer job-template create	210
2.37.2. hammer job-template delete	211
2.37.3. hammer job-template dump	211
2.37.4. hammer job-template export	211
2.37.5. hammer job-template import	212
2.37.6. hammer job-template info	212
2.37.7. hammer job-template list	212
2.37.8. hammer job-template update	213
2.38. HAMMER LIFECYCLE-ENVIRONMENT	214
2.38.1. hammer lifecycle-environment create	214
2.38.2. hammer lifecycle-environment delete	215
2.38.3. hammer lifecycle-environment info	215
2.38.4. hammer lifecycle-environment list	215
2.38.5. hammer lifecycle-environment paths	216
2.38.6. hammer lifecycle-environment update	216
2.39. HAMMER LOCATION	216
2.39.1. hammer location add-compute-resource	217
2.39.2. hammer location add-config-template	217
2.39.3. hammer location add-domain	218
2.39.4. hammer location add-environment	218
2.39.5. hammer location add-hostgroup	218
2.39.6. hammer location add-medium	219
2.39.7. hammer location add-organization	219
2.39.8. hammer location add-smart-proxy	219
2.39.9. hammer location add-subnet	220
2.39.10. hammer location add-user	220
2.39.11. hammer location create	220
2.39.12. hammer location delete	222
2.39.13. hammer location delete-parameter	223
2.39.14. hammer location info	223
2.39.15. hammer location list	223
2.39.16. hammer location remove-compute-resource	224
2.39.17. hammer location remove-config-template	224
2.39.18. hammer location remove-domain	224
2.39.19. hammer location remove-environment	225
2.39.20. hammer location remove-hostgroup	225
2.39.21. hammer location remove-medium	225
2.39.22. hammer location remove-organization	225
2.39.23. hammer location remove-smart-proxy	226
2.39.24. hammer location remove-subnet	226
2.39.25. hammer location remove-user	226
2.39.26. hammer location set-parameter	227
2.39.27. hammer location update	227
2.40. HAMMER MEDIUM	229
2.40.1. hammer medium add-operatingsystem	230

2.40.2. hammer medium create	230
2.40.3. hammer medium delete	231
2.40.4. hammer medium info	231
2.40.5. hammer medium list	232
2.40.6. hammer medium remove-operatingsystem	232
2.40.7. hammer medium update	232
2.41. HAMMER MODEL	234
2.41.1. hammer model create	234
2.41.2. hammer model delete	234
2.41.3. hammer model info	235
2.41.4. hammer model list	235
2.41.5. hammer model update	235
2.42. HAMMER MODULE-STREAM	236
2.42.1. hammer module-stream info	236
2.42.2. hammer module-stream list	237
2.43. HAMMER ORGANIZATION	237
2.43.1. hammer organization add-compute-resource	238
2.43.2. hammer organization add-config-template	238
2.43.3. hammer organization add-domain	239
2.43.4. hammer organization add-environment	239
2.43.5. hammer organization add-hostgroup	239
2.43.6. hammer organization add-location	240
2.43.7. hammer organization add-medium	240
2.43.8. hammer organization add-smart-proxy	240
2.43.9. hammer organization add-subnet	240
2.43.10. hammer organization add-user	241
2.43.11. hammer organization create	241
2.43.12. hammer organization delete	243
2.43.13. hammer organization delete-parameter	243
2.43.14. hammer organization info	244
2.43.15. hammer organization list	244
2.43.16. hammer organization remove-compute-resource	244
2.43.17. hammer organization remove-config-template	245
2.43.18. hammer organization remove-domain	245
2.43.19. hammer organization remove-environment	245
2.43.20. hammer organization remove-hostgroup	246
2.43.21. hammer organization remove-location	246
2.43.22. hammer organization remove-medium	246
2.43.23. hammer organization remove-smart-proxy	247
2.43.24. hammer organization remove-subnet	247
2.43.25. hammer organization remove-user	247
2.43.26. hammer organization set-parameter	247
2.43.27. hammer organization update	248
2.44. HAMMER OS	250
2.44.1. hammer os add-architecture	251
2.44.2. hammer os add-config-template	251
2.44.3. hammer os add-ptable	251
2.44.4. hammer os create	252
2.44.5. hammer os delete	253
2.44.6. hammer os delete-default-template	253
2.44.7. hammer os delete-parameter	253
2.44.8. hammer os info	254
2.44.9. hammer os list	254

2.44.10. hammer os remove-architecture	255
2.44.11. hammer os remove-config-template	255
2.44.12. hammer os remove-ptable	255
2.44.13. hammer os set-default-template	256
2.44.14. hammer os set-parameter	256
2.44.15. hammer os update	256
2.45. HAMMER OSTREE-BRANCH	258
2.45.1. hammer ostree-branch info	258
2.45.2. hammer ostree-branch list	258
2.46. HAMMER PACKAGE	259
2.46.1. hammer package info	259
2.46.2. hammer package list	259
2.47. HAMMER PACKAGE-GROUP	260
2.47.1. hammer package-group info	261
2.47.2. hammer package-group list	261
2.48. HAMMER PARTITION-TABLE	262
2.48.1. hammer partition-table add-operatingsystem	262
2.48.2. hammer partition-table create	262
2.48.3. hammer partition-table delete	264
2.48.4. hammer partition-table dump	264
2.48.5. hammer partition-table info	264
2.48.6. hammer partition-table list	265
2.48.7. hammer partition-table remove-operatingsystem	265
2.48.8. hammer partition-table update	266
2.49. HAMMER PING	267
2.50. HAMMER POLICY	267
2.50.1. hammer policy create	267
2.50.2. hammer policy delete	268
2.50.3. hammer policy info	269
2.50.4. hammer policy list	269
2.50.5. hammer policy update	270
2.51. HAMMER PRODUCT	271
2.51.1. hammer product create	271
2.51.2. hammer product delete	272
2.51.3. hammer product info	272
2.51.4. hammer product list	272
2.51.5. hammer product remove-sync-plan	273
2.51.6. hammer product set-sync-plan	273
2.51.7. hammer product synchronize	274
2.51.8. hammer product update	274
2.52. HAMMER PROXY	274
2.52.1. hammer proxy content	275
2.52.1.1. hammer proxy content add-lifecycle-environment	275
2.52.1.2. hammer proxy content available-lifecycle-environments	276
2.52.1.3. hammer proxy content cancel-synchronization	276
2.52.1.4. hammer proxy content info	276
2.52.1.5. hammer proxy content lifecycle-environments	277
2.52.1.6. hammer proxy content inecycle-environment	277
2.52.1.7. hammer proxy content remove-mecycle-environment 2.52.1.7. hammer proxy content synchronization-status	277
	277
2.52.1.8. hammer proxy croate	
2.52.2. hammer proxy delete	278
2.52.3. hammer proxy delete 2.52.4. hammer proxy import-classes	279 279
4.54.7. Halliller DLOXV IIIDOLE-CIGSSES	2/9

2.52.5. hammer proxy info	280
2.52.6. hammer proxy list	280
2.52.7. hammer proxy refresh-features	281
2.52.8. hammer proxy update	281
2.53. HAMMER PUPPET-CLASS	282
2.53.1. hammer puppet-class info	282
2.53.2. hammer puppet-class list	283
2.53.3. hammer puppet-class sc-params	283
2.53.4. hammer puppet-class smart-variables	284
2.54. HAMMER PUPPET-ENVIRONMENT	285
2.54.1. hammer puppet-environment create	285
2.54.2. hammer puppet-environment delete	286
2.54.3. hammer puppet-environment info	286
2.54.4. hammer puppet-environment list	286
2.54.5. hammer puppet-environment sc-params	287
2.54.6. hammer puppet-environment update	288
2.55. HAMMER PUPPET-MODULE	289
2.55.1. hammer puppet-module info	289
2.55.2. hammer puppet-module list	289
2.56. HAMMER REALM	290
2.56.1. hammer realm create	290
2.56.2. hammer realm delete	290
2.56.3. hammer realm info	291
2.56.4. hammer realm list	291
2.56.5. hammer realm update	292
2.57. HAMMER RECURRING-LOGIC	293
2.57.1. hammer recurring-logic cancel	293
2.57.2. hammer recurring-logic info	294
2.57.3. hammer recurring-logic list	294
2.58. HAMMER REMOTE-EXECUTION-FEATURE	294
2.58.1. hammer remote-execution-feature info	295
2.58.2. hammer remote-execution-feature list	295
2.58.3. hammer remote-execution-feature update	295
2.59. HAMMER REPORT	296
2.59.1. hammer report delete	296
2.59.2. hammer report info	297
2.59.3. hammer report list	297
2.60. HAMMER REPORT-TEMPLATE	298
2.60.1. hammer report-template clone	298
2.60.2. hammer report-template create	299
2.60.3. hammer report-template delete	300
2.60.4. hammer report-template dump	300
2.60.5. hammer report-template generate	300
2.60.6. hammer report-template info	301
2.60.7. hammer report-template list	301
2.60.8. hammer report-template report-data	302
2.60.9. hammer report-template schedule	302
2.60.10. hammer report-template update	303
2.61. HAMMER REPOSITORY	304
2.61.1. hammer repository create	304
2.61.2. hammer repository delete	305
2.61.3. hammer repository export	306
2.61.4. hammer repository info	306

2.61.5. hammer repository list	306
2.61.6. hammer repository remove-content	307
2.61.7. hammer repository synchronize	308
2.61.8. hammer repository update	308
2.61.9. hammer repository upload-content	310
2.62. HAMMER REPOSITORY-SET	310
2.62.1. hammer repository-set available-repositories	311
2.62.2. hammer repository-set disable	311
2.62.3. hammer repository-set enable	311
2.62.4. hammer repository-set info	312
2.62.5. hammer repository-set list	312
2.63. HAMMER ROLE	312
2.63.1. hammer role clone	313
2.63.2. hammer role create	314
2.63.3. hammer role delete	314
2.63.4. hammer role filters	315
2.63.5. hammer role info	315
2.63.6. hammer role list	315
2.63.7. hammer role update	316
2.64. HAMMER SC-PARAM	316
2.64.1. hammer sc-param add-matcher	317
2.64.2. hammer sc-param info	317
2.64.3. hammer sc-param list	318
2.64.4. hammer sc-param remove-matcher	319
2.64.5. hammer sc-param update	319
2.65. HAMMER SCAP-CONTENT	320
2.65.1. hammer scap-content create	320
2.65.2. hammer scap-content delete	321
2.65.3. hammer scap-content download	321
2.65.4. hammer scap-content info	322
2.65.5. hammer scap-content list	322
2.65.6. hammer scap-content update	322
2.66. HAMMER SETTINGS	323
2.66.1. hammer settings list	323
2.66.2. hammer settings set	324
2.67. HAMMER SHELL	324
2.68. HAMMER SMART-VARIABLE	324
2.68.1. hammer smart-variable add-matcher	325
2.68.2. hammer smart-variable create	325
2.68.3. hammer smart-variable delete	326
2.68.4. hammer smart-variable info	326
2.68.5. hammer smart-variable list	327
2.68.6. hammer smart-variable remove-matcher	327
2.68.7. hammer smart-variable update	328
2.69. HAMMER SUBNET	328
2.69.1. hammer subnet create	329
2.69.2. hammer subnet delete	330
2.69.3. hammer subnet delete-parameter	331
2.69.4. hammer subnet info	331
2.69.5. hammer subnet list	331
2.69.6. hammer subnet set-parameter	332
2.69.7. hammer subnet update	332
2.70. HAMMER SUBSCRIPTION	334

2.70.1. hammer subscription delete-manifest	334
2.70.2. hammer subscription list	334
2.70.3. hammer subscription manifest-history	335
2.70.4. hammer subscription refresh-manifest	335
2.70.5. hammer subscription upload	335
2.71. HAMMER SYNC-PLAN	336
2.71.1. hammer sync-plan create	336
2.71.2. hammer sync-plan delete	337
2.71.3. hammer sync-plan info	337
2.71.4. hammer sync-plan list	337
2.71.5. hammer sync-plan update	338
2.72. HAMMER TAILORING-FILE	338
2.72.1. hammer tailoring-file create	338
2.72.2. hammer tailoring-file delete	339
2.72.3. hammer tailoring-file download	339
2.72.4. hammer tailoring-file info	340
2.72.5. hammer tailoring-file list	340
2.72.6. hammer tailoring-file update	340
2.73. HAMMER TASK	341
2.73.1. hammer task info	341
2.73.2. hammer task list	342
2.73.3. hammer task progress	342
2.73.4. hammer task resume	342
2.74. HAMMER TEMPLATE	343
2.74.1. hammer template add-operatingsystem	343
2.74.2. hammer template build-pxe-default	344
2.74.3. hammer template clone	344
2.74.4. hammer template combination	344
2.74.4.1. hammer template combination create	345
2.74.4.2. hammer template combination delete	345
2.74.4.3. hammer template combination info	345
2.74.4.4. hammer template combination list	346
2.74.4.5. hammer template combination update	346
2.74.5. hammer template create	347
2.74.6. hammer template delete	348
2.74.7. hammer template dump	348
2.74.8. hammer template info	348
2.74.9. hammer template kinds	349
2.74.10. hammer template list	349
2.74.11. hammer template remove–operatingsystem	350
2.74.12. hammer template update	350
2.75. HAMMER TEMPLATE-INPUT	351
2.75.1. hammer template-input create	351
2.75.2. hammer template-input delete	352
2.75.3. hammer template input delete	353
2.75.4. hammer template-input list	353
2.76. HAMMER USER	353
2.76.1 hammer user access-token	354
2.76.1.1 hammer user access-token create	354
2.76.1.2. hammer user access-token info	354
2.76.1.3. hammer user access-token linto	355
2.76.1.4. hammer user access-token revoke	355
2.76.1.4. hammer user add-role	356
Z./ O.Z. Halliller user add-fole	330

2.76.3. hammer user create	356
2.76.4. hammer user delete	357
2.76.5. hammer user info	358
2.76.6. hammer user list	358
2.76.7. hammer user remove-role	359
2.76.8. hammer user ssh-keys	359
2.76.8.1. hammer user ssh-keys add	359
2.76.8.2. hammer user ssh-keys delete	360
2.76.8.3. hammer user ssh-keys info	360
2.76.8.4. hammer user ssh-keys list	361
2.76.9. hammer user update	361
2.77. HAMMER USER-GROUP	363
2.77.1. hammer user-group add-role	363
2.77.2. hammer user-group add-user	363
2.77.3. hammer user-group add-user-group	364
2.77.4. hammer user-group create	364
2.77.5. hammer user-group delete	365
2.77.6. hammer user-group external	365
2.77.6.1. hammer user-group external create	365
2.77.6.2. hammer user-group external delete	366
2.77.6.3. hammer user-group external info	366
2.77.6.4. hammer user-group external list	367
2.77.6.5. hammer user-group external refresh	367
2.77.6.6. hammer user-group external update	367
2.77.7. hammer user-group info	368
2.77.8. hammer user-group list	368
2.77.9. hammer user-group remove-role	368
2.77.10. hammer user-group remove-user	369
2.77.11. hammer user-group remove-user-group	369
2.77.12. hammer user-group update	369
2.78. HAMMER VIRT-WHO-CONFIG	370
2.78.1. hammer virt-who-config create	370
2.78.2. hammer virt-who-config delete	372
2.78.3. hammer virt-who-config deploy	372
2.78.4. hammer virt-who-config fetch	372
2.78.5. hammer virt-who-config info	373
2.78.6. hammer virt-who-config list	373
2.78.7. hammer virt-who-config update	373

CHAPTER 1. INTRODUCTION TO HAMMER

Hammer is a powerful command-line tool provided with Red Hat Satellite 6. You can use Hammer to configure and manage a Red Hat Satellite Server either through CLI commands or automation in shell scripts. Hammer also provides an interactive shell.

Hammer compared to Satellite web UI

Compared to navigating the web UI, using Hammer can result in much faster interaction with the Satellite Server, as common shell features such as environment variables and aliases are at your disposal. You can also incorporate Hammer commands into reusable scripts for automating tasks of various complexity. Output from Hammer commands can be redirected to other tools, which allows for integration with your existing environment. You can issue Hammer commands directly on the base operating system running Red Hat Satellite.

Access to Satellite Server's base operating system is required to issue Hammer commands, which can limit the number of potential users compared to the web UI. Although the parity between Hammer and the web UI is almost complete, the web UI has development priority and can be ahead especially for newly introduced features.

Hammer compared to Satellite API

For many tasks, both Hammer and Satellite API are equally applicable. Hammer can be used as a human friendly interface to Satellite API, for example to test responses to API calls before applying them in a script (use the **-d** option to inspect API calls issued by Hammer, for example **hammer -d organization list**). Changes in the API are automatically reflected in Hammer, while scripts using the API directly have to be updated manually.

In the background, each Hammer command first establishes a binding to the API, then sends a request. This can have performance implications when executing a large number of Hammer commands in sequence. In contrast, a script communicating directly with the API establishes the binding only once. See the API Guide for more information.

1.1. GETTING HELP

View the full list of **hammer** options and subcommands by executing:

\$ hammer --help

Use **--help** to inspect any subcommand, for example:

\$ hammer organization --help

You can search the help output using **grep**, or redirect it to a text viewer, for example:

\$ hammer | less

1.2. AUTHENTICATION

A Satellite user must prove their identity to Red Hat Satellite when entering hammer commands. Hammer commands can be run manually or automatically. In either case, hammer requires Satellite credentials for authentication. There are three methods of hammer authentication:

Hammer authentication session

- Storing credentials in the hammer configuration file
- Providing credentials with each hammer command

The hammer configuration file method is recommended when running commands automatically. For example, running Satellite maintenance commands from a cron job. When running commands manually, the hammer authentication session and providing credentials with each command are recommended.

1.2.1. Hammer Authentication Session

Hammer authentication session is a cache that stores your credentials, and you have to provide them only once, at the beginning of the session. This method is suited to running several hammer commands in succession, for example a script containing hammer commands. In this scenario, you enter your Satellite credentials once, and the script runs as expected. By using the hammer authentication session, you avoid storing your credentials in the script itself and in the ~/.hammer/cli.modules.d/foreman.yml hammer configuration file.

See the instructions on how to use the sessions:

To enable sessions, add :use_sessions: true to the ~/.hammer/cli.modules.d/foreman.yml file:

:foreman: :use sessions: true

Note that if you enable sessions, credentials stored in the configuration file will be ignored.

- To start a session, enter the following command:
 - # hammer auth login

You are prompted for your Satellite credentials, and logged in. You will not be prompted for the credentials again until your session expires.

• The default length of a session is 60 minutes. You can change the time to suit your preference. For example, to change it to 30 minutes, enter the following command:

hammer settings set --name idle_timeout --value 30 Setting [idle_timeout] updated to [30]

- To see the current status of the session, enter the following command:
 - # hammer auth status
- To end the session, enter the following command:
 - # hammer auth logout

1.2.2. Hammer Configuration File

If you ran the Satellite installation with **--foreman-initial-admin-username** and **--foreman-initial-admin-password** options, credentials you entered are stored in the

~/.hammer/cli.modules.d/foreman.yml configuration file, and hammer does not prompt for your credentials.

You can also add your credentials to the ~/.hammer/cli.modules.d/foreman.yml configuration file manually:

:foreman:

:username: 'username' :password: 'password'



IMPORTANT

Use only spaces for indentation in hammer configuration files. Do not use tabs for indentation in hammer configuration files.

1.2.3. Command Line

If you do not have your Satellite credentials saved in the ~/.hammer/cli.modules.d/foreman.yml configuration file, hammer prompts you for them each time you enter a command. You can specify your credentials when executing a command as follows:

\$ hammer -u username -p password subcommands



NOTE

Examples in this guide assume having saved credentials in the configuration file, or using a hammer authentication session.

1.3. USING STANDALONE HAMMER

You can install **hammer** on a host that has no Satellite Server Server installed, and use it to connect the host to a remote Satellite.

Prerequisites

- Ensure that you register the host to Satellite Server or Capsule Server. For more information, see Registering a Host in the *Provisioning Guide*.
- Ensure that you synchronize the following repositories on Satellite Server or Capsule Server.
 For more information, see Synchronizing Red Hat Repositories in the Content Management Guide.
 - rhel-7-server-rpms
 - rhel-server-rhscl-7-rpms
 - rhel-7-server-satellite-tools-6.6-rpms

Procedure

On a host, complete the following steps to install **hammer**:

1. Enable the Red Hat Enterprise Linux, Red Hat Software Collections and Red Hat Satellite Tools repositories:

subscription-manager repos --enable=rhel-7-server-rpms \
--enable=rhel-server-rhscl-7-rpms \

--enable=rhel-7-server-satellite-tools-6.6-rpms

2. Install hammer:

yum install tfm-rubygem-hammer_cli_katello

3. Edit the :host: entry in the /etc/hammer/cli.modules.d/foreman.yml file to include the Satellite IP address or FQDN.

:host: 'https://satellite.example.com'

1.4. SETTING A DEFAULT ORGANIZATION AND LOCATION

Many **hammer** commands are organization specific. You can set a default organization and location for **hammer** commands so that you do not have to specify them every time with the **--organization** and **--location** options.

Specifying a default organization is useful when you mostly manage a single organization, as it makes your commands shorter. However, when you switch to a different organization, you must use **hammer** with the **--organization** option to specify it.

Procedure

To set a default organization and location, complete the following steps:

1. To set a default organization, enter the following command:

```
# hammer defaults add --param-name organization \ --param-value "Your_Organization"
```

You can find the name of your organization with the **hammer organization list** command.

2. Optional: To set a default location, enter the following command:

```
# hammer defaults add --param-name location \ --param-value 'Your_Location"
```

You can find the name of your location with the hammer location list command.

3. To verify the currently specified default settings, enter the following command:

hammer defaults list

1.5. CONFIGURING HAMMER

The default location for global **hammer** configuration is:

- /etc/hammer/cli_config.yml for general hammer settings
- /etc/hammer/cli.modules.d/ for CLI module configuration files

You can set user specific directives for **hammer** (in ~/.hammer/cli_config.yml) as well as for CLI modules (in respective .yml files under ~/.hammer/cli.modules.d/).

To see the order in which configuration files are loaded, as well as versions of loaded modules, issue:

\$ hammer -d --version



NOTE

Loading configuration for many CLI modules can slow down the execution of **hammer** commands. In such a case, consider disabling CLI modules that are not regularly used.

Apart from saving credentials as described in Section 1.2, "Authentication", you can set several other options in the ~/.hammer/ configuration directory. For example, you can change the default log level and set log rotation with the following directives in ~/.hammer/cli_config.yml. Note that these directives affect only the current user and are not applied globally.

:log_level: 'warning' :log_size: 5 #in MB

Similarly, you can configure user interface settings. For example, set the number of entries displayed per request in the Hammer output by changing the following line:

:per_page: 30

This setting is an equivalent of the --per-page Hammer option.

1.6. CONFIGURING HAMMER LOGGING

You can set **hammer** to log debugging information for various Satellite components.

You can set debug or normal configuration options for all Satellite components.



NOTE

After changing hammer's logging behavior, you must restart Satellite services.

satellite-maintain service restart

To set debug level for all components, use the following command:

hammer admin logging --all --level-debug # satellite-maintain service restart

• To set production level logging, use the following command:

hammer admin logging --all --level-production # satellite-maintain service restart

To list the currently recognized components, that you can set logging for:

hammer admin logging --list

To list all available logging options:

hammer admin logging --help

Usage:

hammer admin logging [OPTIONS]

1.7. INVOKING THE HAMMER SHELL

You can issue **hammer** commands through the interactive shell. To invoke the shell, issue the following command:

\$ hammer shell

In the shell, you can enter subcommands directly without typing "hammer", which can be useful for testing commands before using them in a script. To exit the shell, type **exit** or press [Ctrl + D].

1.8. GENERATING FORMATTED OUTPUT

You can modify the default formatting of the output of **hammer** commands to simplify the processing of this output by other command line tools and applications. For example, to list organizations in a CSV format with a custom separator (in this case a semicolon), issue the following command:

\$ hammer --csv --csv-separator ";" organization list

Output in CSV format is useful for example when you need to parse IDs and use them in a for loop.

Several other formatting options are available with the **--output** option:

\$ hammer --output output_format organization list

Replace output_format with one of:

- table generates output in the form of a human readable table (default).
- base generates output in the form of key-value pairs.
- **yaml** generates output in the YAML format.
- **csv** generates output in the Comma Separated Values format. To define a custom separator, use the **--csv** and **--csv-separator** options instead.
- **json** generates output in the JavaScript Object Notation format.
- **silent** suppresses the output.

1.9. HIDING HEADER OUTPUT FROM HAMMER COMMANDS

When you use any hammer command, you have the option of hiding headers from the output. If you want to pipe or use the output in custom scripts, hiding the output is useful.

• To hide the header output, add the **--no-headers** option to any hammer command.

1.10. TROUBLESHOOTING WITH HAMMER

You can use the **hammer ping** command to check the status of core Satellite services. Together with the **satellite-maintain service status** command, this can help you to diagnose and troubleshoot Satellite issues. If all services are running as expected, the output looks as follows:

\$ hammer ping candlepin: Status: ok Server Response: Duration: 22ms candlepin_auth: Status: Server Response: Duration: 17ms Status: ok Server Response: Duration: 41ms pulp auth: Status: Server Response: Duration: 23ms foreman_tasks: Status:

Server Response: Duration: 33ms

22

CHAPTER 2. REFERENCE

This chapter provides a list of Hammer usage statements. These usage statements are current to the versions of Hammer and its components released for Satellite 6.6.

2.1. HAMMER

Usage:

hammer [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

activation-key Manipulate activation keys admin Administrative server-side tasks

ansible Manage foreman ansible architecture Manipulate architectures arf-report Manipulate compliance reports

audit Search audit trails.

auth Foreman connection login/logout auth-source Manipulate auth sources bootdisk Download boot disks capsule Manipulate capsule

compute-profile Manipulate compute profiles compute-resource Manipulate compute resources

config-group Manipulate config groups config-report Browse and read reports content-view Manipulate content views defaults Defaults management

discovery
discovery-rule
docker
domain

Manipulate discovered hosts.
Manipulate discovered rules.
Manipulate docker content
Manipulate domains

environment Manipulate environments

erratum Manipulate errata

fact Search facts file Manipulate files

filter Manage permission filters foreign-input-set Manage foreign input sets

full-help Print help for all hammer commands global-parameter Manipulate global parameters

gpg Manipulate GPG Key actions on the server

host Manipulate hosts

host-collection Manipulate host collections hostgroup Manipulate hostgroups

import-templates Import templates from a git repo or a directory on the server

job-invocation Manage job invocations job-template Manage job templates

lifecycle-environment Manipulate lifecycle_environments on the server

location Manipulate locations

medium Manipulate installation media model Manipulate hardware models

module-stream View Module Streams organization Manipulate organizations os Manipulate operating system ostree-branch Manipulate ostree branches

package Manipulate packages

package-group Manipulate package groups partition-table Manipulate partition tables Get the status of the server

policy Manipulate policies
product Manipulate products
proxy Manipulate smart proxies
puppet-class Search puppet modules

puppet-environment Manipulate Puppet environments

puppet-module View Puppet Module details

realm Manipulate realms

recurring-logic Recurring logic related actions

remote-execution-feature Manage remote execution features

report Browse and read reports

report-template Manipulate report templates

repository Manipulate repositories

repository-set Manipulate repository sets on the server

role Manage user roles

sc-param Manipulate smart class parameters

scap-content Manipulate SCAP contents settings Change server settings

shell Interactive shell

smart-variable Manipulate smart variables

subnet Manipulate subnets

subscription
sync-plan
tailoring-file
task

Manipulate subscriptions
Manipulate sync plans
Manipulate Tailoring files
Tasks related actions.

template Manipulate config templates template-input Manage template inputs

user Manipulate users user-group Manage user groups

virt-who-config Manage Virt Who configurations

Options:

--[no-]use-defaults Enable/disable stored defaults. Enabled by default

--autocomplete LINE Get list of possible endings --csv Output as CSV (same as --output=csv)

--csv-separator SEPARATOR Character to separate the values

--fetch-ca-cert SERVER Fetch CA certificate from server and exit --interactive INTERACTIVE Explicitly turn interactive mode on/off

One of true/false, yes/no, 1/0.

--no-headers Hide headers from output

--output ADAPTER Set output format. One of [base, table, silent, csv, yaml, json]

--output-file OUTPUT_FILE Path to custom output file --show-ids Show ids of associated resources

--ssl-ca-file CA_FILE Configure the file containing the CA certificates

--ssl-ca-path CA_PATH Configure the directory containing the CA certificates

 $\hbox{\it --ssl-client-cert CERT_FILE} \quad \hbox{\it Configure the client's public certificate}$

--ssl-client-key KEY_FILE Configure the client's private key

--verify-ssl VERIFY SSL Configure SSL verification of remote system

One of true/false, yes/no, 1/0.

--version Show version

-c, --config CFG_FILE Path to custom config file -d, --debug Show debugging output

-h, --help Print help

-p, --password PASSWORD Password to access the remote system

-q, --quiet Completely silent

-r, --reload-cache -s, --server SERVER Force reload of Apipie cache Remote system address

-v, --[no-]verbose Be verbose (or not). True by default

2.2. HAMMER ACTIVATION-KEY

Manipulate activation keys

Usage:

hammer activation-key [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-host-collection Associate a resource add-subscription Add subscription

content-override Override product content defaults

copy Copy an activation key create Create an activation key delete Destroy an activation key

host-collections List associated host collections

info Show an activation key list List activation keys

product-content List associated products remove-host-collection remove-subscription subscriptions update List associated products

Disassociated a resource Remove subscription

List associated subscriptions

Update an activation key

Options:

-h, --help Print help

2.2.1. hammer activation-key add-host-collection

Associate a resource

Usage:

hammer activation-key add-host-collection [OPTIONS]

Options:

--host-collection HOST_COLLECTION_NAME Host collection name to search by

--host-collection-id HOST_COLLECTION_ID Id of the host collection

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.2.2. hammer activation-key add-subscription

Add subscription

Usage:

hammer activation-key add-subscription [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--quantity QUANTITY Quantity of this subscription to add

-h, --help Print help

2.2.3. hammer activation-key content-override

Override product content defaults

Usage:

hammer activation-key content-override [OPTIONS]

Options:

--content-label CONTENT LABEL Label of the content

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--override-name OVERRIDE_NAME Override parameter key or name.

To enable or disable a repo select 'enabled'.

Default value: enabled Default: "enabled"

--remove Remove a content override

--value VALUE Override value. Note for repo enablement you can use a boolean

value

-h, --help Print help

2.2.4. hammer activation-key copy

Copy an activation key

Usage:

hammer activation-key copy [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by --new-name NEW NAME Name of new activation key

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.2.5. hammer activation-key create

Create an activation key

Usage:

hammer activation-key create [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--description DESCRIPTION Description

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--max-hosts MAX_HOSTS Maximum number of registered content hosts

--name NAME Name

--organization ORGANIZATION_NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--unlimited-hosts Set hosts max to unlimited

-h, --help Print help

2.2.6. hammer activation-key delete

Destroy an activation key

Usage:

hammer activation-key delete [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.2.7. hammer activation-key host-collections

List associated host collections

Usage:

hammer activation-key host-collections [OPTIONS]

Options:

can be

Associated with specified object. The value 'host' is supported.

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host-id HOST_ID Filter products by host id

--id ID ID of activation key

--name NAME Name of activation key

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--sort-by SORT_BY Field to sort the results on

--sort-order SORT_ORDER How to order the sorted results (e.g. ASC for ascending)

-h, --help Print help

2.2.8. hammer activation-key info

Show an activation key

Usage:

hammer activation-key info [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.2.9. hammer activation-key list

List activation keys

Usage:

hammer activation-key list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Activation key name to filter by

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.2.10. hammer activation-key product-content

List associated products

Usage:

hammer activation-key product-content [OPTIONS]

Options:

--id ID

--content-access-mode-all CONTENT_ACCESS_MODE_ALL Get all content available, not just that provided by subscriptions

One of true/false, yes/no, 1/0.

--content-access-mode-env CONTENT_ACCESS_MODE_ENV Limit content to just that available in the activation key's content

View version

One of true/false, yes/no, 1/0. ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

-h, --help Print help

2.2.11. hammer activation-key remove-host-collection

Disassociate a resource

Usage:

hammer activation-key remove-host-collection [OPTIONS]

Options:

- --host-collection HOST_COLLECTION_NAME Host collection name to search by
- --host-collection-id HOST_COLLECTION_ID Id of the host collection

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help Print help

2.2.12. hammer activation-key remove-subscription

Remove subscription

Usage:

hammer activation-key remove-subscription [OPTIONS]

Options:

--id ID ID of the activation key

--name NAME Activation key name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--subscription-id SUBSCRIPTION ID ID of subscription

-h, --help Print help

2.2.13. hammer activation-key subscriptions

List associated subscriptions

Usage:

hammer activation-key subscriptions [OPTIONS]

Options:

--activation-key ACTIVATION_KEY_NAME Activation key name to search by

--available-for AVAILABLE_FOR Object to show subscriptions available for, either 'host' or

'activation key'

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST_ID

--match-host MATCH_HOST Ignore subscriptions that are unavailable to the specified host

One of true/false, yes/no, 1/0.

--match-installed MATCH_INSTALLED Return subscriptions that match installed products of the

specified host

One of true/false, yes/no, 1/0.

--name ACTIVATION KEY NAME Activation key name to search by

--no-overlap NO_OVERLAP Return subscriptions which do not overlap with a currently-

attached

Subscription

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'id DESC'

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.2.14. hammer activation-key update

Update an activation key

Usage:

hammer activation-key update [OPTIONS]

Options:

--auto-attach AUTO_ATTACH Auto attach subscriptions upon registration

One of true/false, yes/no, 1/0.

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--description DESCRIPTION Description

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--id ID ID of the activation key

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--max-hosts MAX_HOSTS Maximum number of registered content hosts

--name NAME Activation key name to search by

--new-name NEW_NAME Name

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--release-version RELEASE_VERSION Content release version

--service-level SERVICE_LEVEL Service level
--unlimited-hosts Set hosts max to unlimited

-h, --help Print help

2.3. HAMMER ADMIN

Administrative server-side tasks

Usage:

hammer admin [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

logging Logging verbosity level setup

Options:

-h, --help Print help

2.3.1. hammer admin logging

Logging verbosity level setup

Usage:

hammer admin logging [OPTIONS]

Options:

--no-backup Skip configuration backups creation.

--prefix PATH Operate on prefixed environment (e.g. chroot).

-a, --all Apply to all components.

-c, --components COMPONENTS Components to apply, use --list to get them.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-d, --level-debug Increase verbosity level to debug.

-h, --help Print help

-l, --list List available components.

-n, --dry-run Do not apply specified changes.

-p, --level-production Decrease verbosity level to standard.

2.4. HAMMER ANSIBLE

Manage foreman ansible

Usage:

hammer ansible [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

roles Manage ansible roles variables Manage ansible variables

Options:

-h, --help Print help

2.4.1. hammer ansible roles

Manage ansible roles

Usage:

hammer ansible roles [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Deletes Ansible role

fetch Fetch Ansible roles available to be imported

import Import Ansible roles

info Show role list List Ansible roles

obsolete Obsolete Ansible roles

play-hostgroups Plays Ansible roles on hostgroups

play-hosts Plays Ansible roles on hosts

Options:

-h, --help Print help

2.4.1.1. hammer ansible roles delete

Deletes Ansible role

Usage:

hammer ansible roles delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.4.1.2. hammer ansible roles fetch

Fetch Ansible roles available to be imported

Usage:

hammer ansible roles fetch [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --proxy-id PROXY_ID Capsule to fetch from
- -h, --help Print help

2.4.1.3. hammer ansible roles import

Import Ansible roles

Usage:

hammer ansible roles import [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --proxy-id PROXY_ID Capsule to import from
- --role-names ROLE_NAMES Ansible role names to import

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.4.1.4. hammer ansible roles info

Show role

Usage:

hammer ansible roles info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.4.1.5. hammer ansible roles list

List Ansible roles

Usage:

hammer ansible roles list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

host string
host_id integer
hostgroup string
hostgroup_id integer
id integer
name string
updated_at datetime

2.4.1.6. hammer ansible roles obsolete

Obsolete Ansible roles

Usage:

hammer ansible roles obsolete [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

 $\hbox{--organization-title ORGANIZATION_TITLE\ Organization\ title}$

--proxy-id PROXY_ID Capsule to import from

-h, --help Print help

2.4.1.7. hammer ansible roles play-hostgroups

Plays Ansible roles on hostgroups

Usage:

hammer ansible roles play-hostgroups [OPTIONS]

Options:

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.4.1.8. hammer ansible roles play-hosts

Plays Ansible roles on hosts

Usage:

hammer ansible roles play-hosts [OPTIONS]

Options:

--host-ids HOST_IDS IDs of hosts to play roles on

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.4.2. hammer ansible variables

Manage ansible variables

Usage:

hammer ansible variables [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-matcher Create an override value for a specific ansible variable

create Create Ansible variable delete Deletes Ansible variable

roles, it will not import any new roles
info Show variable
list List Ansible variables

obsolete Obsolete Ansible variables. This will only obsolete variables for already

existing roles, it will not delete any old roles

remove-matcher Destroy an override value update Updates Ansible variable

Options:

-h, --help Print help

2.4.2.1. hammer ansible variables add-matcher

Create an override value for a specific ansible variable

Usage:

hammer ansible variables add-matcher [OPTIONS]

Options:

--ansible-variable ANSIBLE_VARIABLE_NAME Name to search by

--ansible-variable-id ANSIBLE_VARIABLE_ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --match MATCH Override match

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--value VALUE Override value, required if omit is false

-h, --help Print help

2.4.2.2. hammer ansible variables create

Create Ansible variable

Usage:

hammer ansible variables create [OPTIONS]

Options:

--ansible-role-id ANSIBLE ROLE ID

--avoid-duplicates AVOID DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value DEFAULT_VALUE Default value of variable --description DESCRIPTION Description of variable

--hidden-value HIDDEN VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--merge-default MERGE DEFAULT Include default value when merging all matching values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash type)

One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--override OVERRIDE Whether to override variable or not

One of true/false, yes/no, 1/0.

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

--validator-type VALIDATOR TYPE Types of validation values

Possible value(s): 'regexp', 'list'

--variable VARIABLE Name of variable

--variable-type VARIABLE TYPE Types of variable values

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

-h, --help Print help

2.4.2.3. hammer ansible variables delete

Deletes Ansible variable

Usage:

hammer ansible variables delete [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.4.2.4. hammer ansible variables import

Import Ansible variables. This will only import variables for already existing roles, it will not import any new roles

Usage:

hammer ansible variables import [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization-title ORGANIZATION_TITLE Organization title

--proxy-id PROXY_ID Capsule to import from

-h, --help Print help

2.4.2.5, hammer ansible variables info

Show variable

Usage:

hammer ansible variables info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.4.2.6. hammer ansible variables list

List Ansible variables

Usage:

hammer ansible variables list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name

 $\hbox{--organization-title ORGANIZATION_TITLE Organization title}\\$

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

ansible_role string

avoid_duplicates Values: true, false imported Values: true, false

key string

merge_default Values: true, false merge_overrides Values: true, false

name string

override Values: true, false

parameter string

2.4.2.7. hammer ansible variables obsolete

Obsolete Ansible variables. This will only obsolete variables for already existing roles, it will not delete any old roles

Usage:

hammer ansible variables obsolete [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization-id ORGANIZATION_ID Organization ID

 $\hbox{--organization-title ORGANIZATION_TITLE\ Organization\ title}$

--proxy-id PROXY ID Capsule to import from

-h, --help Print help

2.4.2.8. hammer ansible variables remove-matcher

Destroy an override value

Usage:

hammer ansible variables remove-matcher [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.4.2.9. hammer ansible variables update

Updates Ansible variable

Usage:

hammer ansible variables update [OPTIONS]

Options:

--ansible-role ANSIBLE ROLE NAME Name to search by

--ansible-role-id ANSIBLE ROLE ID

--avoid-duplicates AVOID DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value DEFAULT VALUE Default value of variable --hidden-value HIDDEN_VALUE Description of variable

When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

Include default value when merging all matching values --merge-default MERGE_DEFAULT

One of true/false, yes/no, 1/0.

--merge-overrides MERGE OVERRIDES Merge all matching values (only array/hash type)

One of true/false, yes/no, 1/0.

--name NAME Name to search by

--new-name NEW NAME

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--override OVERRIDE Whether to override variable or not

One of true/false, yes/no, 1/0.

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

--validator-rule VALIDATOR RULE Used to enforce certain values for the parameter values

--validator-type VALIDATOR_TYPE Types of validation values

Possible value(s): 'regexp', 'list'

--variable VARIABLE Name of variable

--variable-type VARIABLE_TYPE Types of variable values

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'ison'

-h, --help Print help

2.5. HAMMER ARCHITECTURE

Manipulate architectures

Usage:

hammer architecture [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

Create an architecture create delete Delete an architecture info Show an architecture List all architectures

remove-operatingsystem Disassociate an operating system update Update an architecture

Options:

-h, --help Print help

2.5.1. hammer architecture add-operatingsystem

Associate an operating system

Usage:

hammer architecture add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Architecture name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help Print help

2.5.2. hammer architecture create

Create an architecture

Usage:

hammer architecture create [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME

--operatingsystem-ids OPERATINGSYSTEM IDS Operating system IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.5.3. hammer architecture delete

Delete an architecture

Usage:

hammer architecture delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Architecture name
- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.5.4. hammer architecture info

Show an architecture

Usage:

hammer architecture info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
 --name NAME Architecture name
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.5.5. hammer architecture list

List all architectures

Usage:

hammer architecture list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
- --operatingsystem-id OPERATINGSYSTEM_ID
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

name string

2.5.6. hammer architecture remove-operatingsystem

Disassociate an operating system

Usage:

hammer architecture remove-operatingsystem [OPTIONS]

Options:

- --id ID
- --name NAME Architecture name
- --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
- --operatingsystem-id OPERATINGSYSTEM_ID
- -h, --help Print help

2.5.7. hammer architecture update

Update an architecture

Usage:

hammer architecture update [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Architecture name
- --new-name NEW NAME
- --operatingsystem-ids OPERATINGSYSTEM_IDS Operating system IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.6. HAMMER ARF-REPORT

Manipulate compliance reports

Usage:

hammer arf-report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Delete an ARF Report

download Download bzipped ARF report download-html Download ARF report in HTML

info Show an ARF report

list List ARF reports

Options:

-h, --help Print help

2.6.1. hammer arf-report delete

Delete an ARF Report

Usage:

hammer arf-report delete [OPTIONS]

Options:

--id ID

--location-id LOCATION_ID

--organization ORGANIZATION_NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

-h, --help Print help

2.6.2. hammer arf-report download

Download bzipped ARF report

Usage:

hammer arf-report download [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Name to search by

--location-id LOCATION ID

--organization ORGANIZATION NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--path PATH Path to directory where downloaded file will be saved

-h, --help Print help

2.6.3. hammer arf-report download-html

Download ARF report in HTML

Usage:

hammer arf-report download-html [OPTIONS]

Options:

--id ID

--location-id LOCATION ID

--organization ORGANIZATION_NAME Name to search by

--organization-id ORGANIZATION ID Organization ID

--path PATH Path to directory where downloaded file will be saved

-h, --help Print help

2.6.4. hammer arf-report info

Show an ARF report

Usage:

hammer arf-report info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Name to search by
- --location-id LOCATION ID
- --organization ORGANIZATION_NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID
- -h, --help Print help

2.6.5. hammer arf-report list

List ARF reports

Usage:

hammer arf-report list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

- compliance_policy string
- compliance_status Values: compliant, incompliant, inconclusive
- comply_with string environment string
- eventful Values: true, false
- host string
 host_collection string
 host_id integer
 hostgroup string
 hostgroup_fullname string
 hostgroup_title string
 inconclusive with string
- last_for Values: host, policy
- last_report datetime
 lifecycle_environment string
 location string
 location_id integer
 log text
- not_comply_with string

openscap_proxy string organization string organization_id integer origin string policy string reported datetime resource text xccdf_rule_failed string xccdf_rule_name text xccdf_rule_othered string xccdf_rule_passed string

2.7. HAMMER AUDIT

Search audit trails.

Usage:

hammer audit [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show an audit list List all audits

Options:

-h, --help Print help

2.7.1. hammer audit info

Show an audit

Usage:

hammer audit info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.7.2. hammer audit list

List all audits

Usage:

hammer audit list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

action Values: create, update, delete

auditable_id integer changes text comment string host string hostgroup string hostgroup_title string id integer interface fqdn string interface ip string interface_mac string location string location_id integer organization string organization_id integer string

os os_title string parameter string partition table string provisioning template string puppetclass string remote address string setting strina time datetime

type Values: role, ptable, provisioning_template, user, filter, subnet, hostgroup, smart_proxy, katello/host/content_facet, katello/host/subscription_facet, remote_execution_feature, usergroup, katello/content_view, katello/kt_environment, realm, job_template, bookmark, lookup_value, model, domain, environment, architecture, image, ansible_role, hostgroup_class, puppetclass, medium, auth_source, compute_resource, host, interface, location, organization, os, override_value, parameter, partition_table, setting, smart_class_parameter, smart_variable

user string username string

2.8. HAMMER AUTH

Foreman connection login/logout

Usage:

hammer auth [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

login Set credentials

logout Wipe your credentials

status Information about current connections

Options:

-h, --help Print help

2.8.1. hammer auth login

Set credentials

Usage:

hammer auth login [OPTIONS]

Options:

-h, --help Print help

-p, --password PASSWORD Password to access the remote system -u, --username USERNAME Username to access the remote system

2.8.2. hammer auth logout

Wipe your credentials

Usage:

hammer auth logout [OPTIONS]

Options:

-h, --help Print help

2.8.3. hammer auth status

Information about current connections

Usage:

hammer auth status [OPTIONS]

Options:

-h, --help Print help

2.9. HAMMER AUTH-SOURCE

Manipulate auth sources

Usage:

hammer auth-source [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

Idap Manage LDAP auth sources

list List all auth sources

Options:

-h, --help Print help

2.9.1. hammer auth-source Idap

Manage LDAP auth sources

Usage:

hammer auth-source Idap [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an LDAP authentication source
delete Delete an LDAP authentication source
info Show an LDAP authentication source
list List all LDAP authentication sources
update Update an LDAP authentication source

Options:

-h, --help Print help

2.9.1.1. hammer auth-source Idap create

Create an LDAP authentication source

Usage:

hammer auth-source Idap create [OPTIONS]

Options:

--account ACCOUNT

--account-password ACCOUNT_PASSWORD Required if onthefly_register is true

--attr-firstname ATTR_FIRSTNAME
--attr-lastname ATTR_LASTNAME
--attr-login ATTR_LOGIN
--attr-mail ATTR MAIL

Required if onthefly_register is true

Required if onthefly_register is true

Required if onthefly_register is true

--attr-photo ATTR_PHOTO

--base-dn BASE_DN

--groups-base GROUPS_BASE Groups base DN

--host HOST

--Idap-filter LDAP_FILTER LDAP filter

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--onthefly-register ONTHEFLY_REGISTER One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--port PORT Defaults to 389

Possible value(s): 'free_ipa', 'active_directory', 'posix'

--tls TLS One of true/false, yes/no, 1/0.

Is posix or free_ipa

One of true/false, yes/no, 1/0.

--usergroup-sync USERGROUP SYNC Sync external user groups on login

One of true/false, yes/no, 1/0.

-h, --help Print help

2.9.1.2. hammer auth-source Idap delete

Delete an LDAP authentication source

Usage:

hammer auth-source Idap delete [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.9.1.3. hammer auth-source Idap info

Show an LDAP authentication source

Usage:

hammer auth-source Idap info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.9.1.4. hammer auth-source Idap list

List all LDAP authentication sources

Usage:

hammer auth-source Idap list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

location string
location_id integer
name string
organization string
organization id integer

2.9.1.5. hammer auth-source Idap update

Update an LDAP authentication source

Usage:

hammer auth-source Idap update [OPTIONS]

Options:

--account ACCOUNT

--account-password ACCOUNT_PASSWORD Required if onthefly_register is true

--attr-firstname ATTR_FIRSTNAME Required if onthefly_register is true --attr-lastname ATTR_LASTNAME Required if onthefly_register is true

--attr-login ATTR_LOGIN Required if onthefly_register is true
--attr-mail ATTR_MAIL Required if onthefly_register is true

--attr-photo ATTR_PHOTO

--base-dn BASE_DN

--groups-base GROUPS_BASE Groups base DN

--host HOST

--id ID

--Idap-filter LDAP_FILTER LDAP filter

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Name to search by

--new-name NEW NAME

--onthefly-register ONTHEFLY_REGISTER One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--port PORT Defaults to 389

--server-type SERVER_TYPE Type of the LDAP server

Possible value(s): 'free_ipa', 'active_directory', 'posix'

--tls TLS One of true/false, yes/no, 1/0.

Is posix or free_ipa

One of true/false, yes/no, 1/0.

--usergroup-sync USERGROUP SYNC Sync external user groups on login

One of true/false, yes/no, 1/0.

-h, --help Print help

2.9.2. hammer auth-source list

List all auth sources

-

Usage:

hammer auth-source list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

2.10. HAMMER BOOTDISK

Download boot disks

Usage:

hammer bootdisk [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

generic Download generic image host Download host image

subnet Download subnet generic image

Options:

-h, --help Print help

2.10.1. hammer bootdisk generic

Download generic image

Usage:

hammer bootdisk generic [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION TITLE Organization title

--sudo Use sudo to write to device

-h, --help Print help

2.10.2. hammer bootdisk host

Download host image

Usage:

hammer bootdisk host [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)
--full FULL True for full, false for basic reusable image

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--sudo Use sudo to write to device

-h, --help Print help

2.10.3. hammer bootdisk subnet

Download subnet generic image

Usage:

hammer bootdisk subnet [OPTIONS]

Options:

--file PATH File or device to write image to

--force Force writing to existing destination (device etc.)

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

 $\hbox{--organization-title ORGANIZATION_TITLE Organization title}\\$

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

--sudo Use sudo to write to device

-h, --help Print help

2.11. HAMMER CAPSULE

Manipulate capsule

Usage:

hammer capsule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

content Manage the capsule content

create Create a capsule delete Delete a capsule

import-classes Import puppet classes from puppet Capsule

info Show a capsule list List all capsules

refresh-features Refresh capsule features

update Update a capsule

Options:

-h, --help Print help

2.11.1. hammer capsule content

Manage the capsule content

Usage:

hammer capsule content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-lifecycle-environment
Add lifecycle environments to the capsule

available-lifecycle-environments List the lifecycle environments not attached to the capsule

cancel-synchronization Cancel running capsule synchronization info Get current capsule synchronization status

lifecycle-environments List the lifecycle environments attached to the capsule remove-lifecycle-environment Remove lifecycle environments from the capsule

synchronization-status Get current capsule synchronization status

synchronize Synchronize the content to the capsule

Options:

-h, --help Print help

2.11.1.1. hammer capsule content add-lifecycle-environment

Add lifecycle environments to the capsule

Usage:

hammer capsule content add-lifecycle-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

instead)

--id ID Id of the capsule

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

-h, --help Print help

2.11.1.2. hammer capsule content available-lifecycle-environments

List the lifecycle environments not attached to the capsule

Usage:

hammer capsule content available-lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.11.1.3. hammer capsule content cancel-synchronization

Cancel running capsule synchronization

Usage:

hammer capsule content cancel-synchronization [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

-h, --help Print help

2.11.1.4. hammer capsule content info

Get current capsule synchronization status

Usage:

hammer capsule content info [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.11.1.5. hammer capsule content lifecycle-environments

List the lifecycle environments attached to the capsule

Usage:

hammer capsule content lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.11.1.6. hammer capsule content remove-lifecycle-environment

Remove lifecycle environments from the capsule

Usage:

hammer capsule content remove-lifecycle-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--id ID Id of the capsule

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

-h, --help Print help

2.11.1.7. hammer capsule content synchronization-status

Get current capsule synchronization status

Usage:

hammer capsule content synchronization-status [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.11.1.8. hammer capsule content synchronize

Synchronize the content to the capsule

Usage:

hammer capsule content synchronize [OPTIONS]

Options:

--async Do not wait for the task

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--id ID Id of the capsule

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

--skip-metadata-check SKIP_METADATA_CHECK Skip metadata check on each repository

on the capsule

One of true/false, yes/no, 1/0.

-h, --help Print help

2.11.2. hammer capsule create

Create a capsule

Usage:

hammer capsule create [OPTIONS]

Options:

--download-policy DOWNLOAD_POLICY Download Policy of the capsule, must be one of immediate, on demand,

Background, inherit

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--url URL

-h, --help Print help

2.11.3. hammer capsule delete

Delete a capsule

Usage:

hammer capsule delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.11.4. hammer capsule import-classes

Import puppet classes from puppet Capsule

Usage:

hammer capsule import-classes [OPTIONS]

Options:

--dryrun Do not run the import

--environment ENVIRONMENT NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--except EXCEPT Optional comma-delimited string containing either 'new',

'updated', or 'obsolete' that is used to limit the imported

Puppet classes

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title --puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET ENVIRONMENT ID

-h, --help Print help

2.11.5. hammer capsule info

Show a capsule

-

Usage:

hammer capsule info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
 --name NAME Name to search by

- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.11.6. hammer capsule list

List all capsules

Usage:

hammer capsule list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

feature string
location string
location_id integer
name string
organization string
organization_id integer
url string

2.11.7. hammer capsule refresh-features

Refresh capsule features

Usage:

hammer capsule refresh-features [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.11.8. hammer capsule update

Update a capsule

Usage:

hammer capsule update [OPTIONS]

Options:

--download-policy DOWNLOAD_POLICY Download Policy of the capsule, must be one of immediate, on demand,

Background, inherit

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Name to search by

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--url URL

-h, --help Print help

2.12. HAMMER COMPUTE-PROFILE

Manipulate compute profiles

Usage:

hammer compute-profile [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a compute profile
delete Delete a compute profile
info Show a compute profile
list List of compute profiles
update Update a compute profile

values Create update and delete Compute profile values

Options:

-h, --help Print help

2.12.1. hammer compute-profile create

Create a compute profile

Usage:

hammer compute-profile create [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.12.2. hammer compute-profile delete

Delete a compute profile

Usage:

hammer compute-profile delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--name NAME Compute profile name

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.12.3. hammer compute-profile info

Show a compute profile

Usage:

hammer compute-profile info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Compute profile name

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.12.4. hammer compute-profile list

List of compute profiles

Usage:

hammer compute-profile list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

name string

2.12.5. hammer compute-profile update

Update a compute profile

Usage:

hammer compute-profile update [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Compute profile name

- --new-name NEW_NAME

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.12.6. hammer compute-profile values

Create update and delete Compute profile values

Usage:

hammer compute-profile values [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-interface Add interface for Compute Profile add-volume Add volume for Compute Profile Create compute profile set of values create Remove compute profile interface remove-interface Remove compute profile volume remove-volume Update compute profile values update update-interface Update compute profile interface update-volume Update compute profile volume

Options:

-h, --help Print help

2.12.6.1. hammer compute-profile values add-interface

Add interface for Compute Profile

Usage:

hammer compute-profile values add-interface [OPTIONS]

Options:

- --compute-profile-id COMPUTE_PROFILE_ID
- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --interface SET_VALUES Interface parameters, should be comma separated list of

values

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

-ii, --neip

Provider specific options: ec2: --interface: gce: --interface: libvirt: --interface: compute type Possible values: bridge, network compute bridge Name of interface according to type Possible values: virtio, rtl8139, ne2k pci, pcnet, e1000 compute_model openstack: --interface: ovirt: --interface: compute name Compute name, e.g. eth0 compute network Select one of available networks for a cluster, must be an ID compute interface Interface type rackspace: --interface: vmware: --interface: Type of the network adapter, for example one of: compute_type VirtualVmxnet3. VirtualE1000 See documentation center for your version of vSphere to find more details about available adapter types: https://www.vmware.com/support/pubs/ compute network Network ID from VMware

2.12.6.2. hammer compute-profile values add-volume

Add volume for Compute Profile

Usage:

hammer compute-profile values add-volume [OPTIONS]

Options:

- --compute-profile-id COMPUTE_PROFILE_ID
- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --volume VOLUME Volume parameters, should be comma separated list of values

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters -h, --help Print help Provider specific options: ec2: --volume: gce: --volume: libvirt: --volume: pool_name One of available storage pools String value, eg. 10G capacity Possible values: raw, qcow2 format_type openstack: --volume: ovirt: --volume: Volume size in GB, integer value size gb storage_domain ID of storage domain bootable Boolean, only one volume can be bootable rackspace: --volume: vmware: --volume: name storage_pod Storage Pod ID from VMware Datastore ID from VMware datastore Integer number, volume size in GB size gb true/false thin true/false eager_zero persistent/independent persistent/independent nonpersistent mode

2.12.6.3. hammer compute-profile values create

Create compute profile set of values

- --compute-resource-id COMPUTE_RESOURCE_ID
- --interface INTERFACE Interface parameters, should be comma separated list of values Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters Can be specified multiple times. --location LOCATION NAME Location name --location-id LOCATION ID --location-title LOCATION TITLE Location title --organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION_TITLE Organization title --volume VOLUME Volume parameters, should be comma separated list of values Comma-separated list of key=value. JSON is acceptable and preferred way for complex parameters Can be specified multiple times. -h, --help Print help Provider specific options: ec2: --volume: --interface: --compute-attributes: flavor id image_id availability_zone security_group_ids managed_ip gce: --volume: --interface: --compute-attributes: machine_type image id network external_ip libvirt: --volume: One of available storage pools pool_name String value, eg. 10G capacity Possible values: raw, qcow2 format type --interface: compute type Possible values: bridge, network Name of interface according to type compute_bridge Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000 compute_model --compute-attributes: cpus Number of CPUs memory String, amount of memory, value in bytes

Boolean (expressed as 0 or 1), whether to start the machine or not start openstack: --volume: --interface: --compute-attributes: flavor ref image_ref tenant_id security_groups network ovirt: --volume: size_gb Volume size in GB, integer value ID of storage domain storage domain bootable Boolean, only one volume can be bootable --interface: compute name Compute name, e.g. eth0 compute_network Select one of available networks for a cluster, must be an ID compute_interface Interface type --compute-attributes: cluster ID of cluster to use Hardware profile to use template cores Integer value, number of cores Amount of memory, integer value in bytes memory rackspace: --volume: --interface: --compute-attributes: flavor id image_id vmware: --volume: name storage_pod Storage Pod ID from VMware Datastore ID from VMware datastore size gb Integer number, volume size in GB true/false thin true/false eager_zero persistent/independent_persistent/independent_nonpersistent mode --interface: compute_type Type of the network adapter, for example one of:

VirtualVmxnet3, VirtualE1000

See documentation center for your version of vSphere to find more details about available adapter types:

https://www.vmware.com/support/pubs/

--compute-attributes:

cpus CPU count

corespersocket Number of cores per socket (applicable to hardware versions < 10 only)

memory_mb Integer number, amount of memory in MB

firmware automatic/bios/efi cluster Cluster ID from VMware

resource_pool Resource Pool ID from VMware

path Path to folder

guest_id Guest OS ID form VMware

scsi_controller_type ID of the controller from VMware hardware version Hardware version ID from VMware

add_cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine

cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on

annotation Annotation Notes

2.12.6.4. hammer compute-profile values remove-interface

Remove compute profile interface

Usage:

hammer compute-profile values remove-interface [OPTIONS]

Options:

- --compute-profile-id COMPUTE_PROFILE_ID
- --compute-resource COMPUTE_RESOURCE_NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --interface-id INTERFACE ID Interface id
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.12.6.5. hammer compute-profile values remove-volume

Remove compute profile volume

Usage:

hammer compute-profile values remove-volume [OPTIONS]

Options

- --compute-profile COMPUTE PROFILE NAME Compute profile name
- --compute-profile-id COMPUTE PROFILE ID

- --compute-resource COMPUTE_RESOURCE_NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION_TITLE Organization title
- --volume-id VOLUME ID Volume id
- -h, --help Print help

2.12.6.6. hammer compute-profile values update

Update compute profile values

Usage:

hammer compute-profile values update [OPTIONS]

Options:

--compute-attributes COMPUTE ATTRS Compute resource attributes, should be comma separated list of values

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

- --compute-profile COMPUTE PROFILE NAME Compute profile name
- --compute-profile-id COMPUTE_PROFILE_ID
- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --interface INTERFACE Interface parameters, should be comma separated list of values

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

Can be specified multiple times.

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --volume VOLUME Volume parameters, should be comma separated list of values

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

Can be specified multiple times.

Print help -h, --help

Provider specific options:

ec2:

- --volume:
- --interface:
- --compute-attributes:

flavor id

image id

availability zone

```
security_group_ids
  managed_ip
gce:
 --volume:
 --interface:
 --compute-attributes:
  machine_type
  image_id
  network
  external_ip
libvirt:
 --volume:
  pool_name
                  One of available storage pools
                String value, eg. 10G
  capacity
  format_type
                 Possible values: raw, qcow2
 --interface:
  compute type
                   Possible values: bridge, network
  compute_model
                    Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000
 --compute-attributes:
               Number of CPUs
  cpus
                 String, amount of memory, value in bytes
  memory
  start
              Boolean (expressed as 0 or 1), whether to start the machine or not
openstack:
 --volume:
 --interface:
 --compute-attributes:
  flavor_ref
  image_ref
  tenant_id
  security_groups
  network
ovirt:
 --volume:
                Volume size in GB, integer value
  size_gb
  storage domain
                    ID of storage domain
                Boolean, only one volume can be bootable
  bootable
 --interface:
  compute_name
                    Compute name, e.g. eth0
  compute_network Select one of available networks for a cluster, must be an ID
  compute_interface Interface type
```

--compute-attributes:

cluster ID of cluster to use template Hardware profile to use cores Integer value, number of cores

memory Amount of memory, integer value in bytes

rackspace: --volume:

--interface:

--compute-attributes:

flavor_id image_id

vmware:

--volume:

name

storage_pod Storage Pod ID from VMware datastore Datastore ID from VMware

size_gb Integer number, volume size in GB

thin true/false eager_zero true/false

mode persistent/independent_persistent/independent_nonpersistent

--interface:

compute_type Type of the network adapter, for example one of:

VirtualVmxnet3, VirtualE1000

See documentation center for your version of vSphere to find more details about available adapter types:

https://www.vmware.com/support/pubs/

compute network Network ID from VMware

--compute-attributes:

cpus CPU count

corespersocket Number of cores per socket (applicable to hardware versions < 10 only)

memory_mb Integer number, amount of memory in MB

firmware automatic/bios/efi cluster Cluster ID from VMware

resource_pool Resource Pool ID from VMware

path Path to folder

guest id Guest OS ID form VMware

scsi_controller_type ID of the controller from VMware hardware_version Hardware version ID from VMware

add cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine

cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on

annotation Annotation Notes

2.12.6.7. hammer compute-profile values update-interface

Update compute profile interface

```
Usage:
  hammer compute-profile values update-interface [OPTIONS]
Options:
--compute-profile COMPUTE PROFILE NAME Compute profile name
--compute-profile-id COMPUTE_PROFILE_ID
--compute-resource COMPUTE_RESOURCE_NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--interface SET VALUES
                                   Interface parameters, should be comma separated list of
values
                         Comma-separated list of key=value.
                        JSON is acceptable and preferred way for complex parameters
--interface-id INTERFACE ID
                                    Interface id
--location LOCATION NAME
                                     Location name
--location-id LOCATION ID
--location-title LOCATION TITLE Location title
--organization ORGANIZATION_NAME
                                          Organization name
--organization-id ORGANIZATION ID
                                        Organization ID
--organization-title ORGANIZATION_TITLE Organization title
                           Print help
-h, --help
Provider specific options:
 ec2:
  --interface:
 gce:
  --interface:
 libvirt:
  --interface:
   compute type
                     Possible values: bridge, network
   compute bridge Name of interface according to type
                      Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000
   compute_model
 openstack:
  --interface:
 ovirt:
  --interface:
                      Compute name, e.g. eth0
   compute name
   compute_network
                      Select one of available networks for a cluster, must be an ID
   compute interface Interface type
 rackspace:
  --interface:
 vmware:
  --interface:
                     Type of the network adapter, for example one of:
   compute_type
```

See documentation center for your version of vSphere to find more details about

VirtualVmxnet3, VirtualE1000

compute network Network ID from VMware

https://www.vmware.com/support/pubs/

available adapter types:

2.12.6.8. hammer compute-profile values update-volume

Update compute profile volume

```
Usage:
  hammer compute-profile values update-volume [OPTIONS]
Options:
--compute-profile-id COMPUTE PROFILE ID
--compute-resource COMPUTE RESOURCE NAME Compute resource name
--compute-resource-id COMPUTE_RESOURCE_ID
--location LOCATION_NAME
                                   Location name
--location-id LOCATION_ID
--location-title LOCATION TITLE Location title
--organization ORGANIZATION NAME
                                        Organization name
--organization-id ORGANIZATION_ID
                                      Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--volume VOLUME
                               Volume parameters, should be comma separated list of values
                       Comma-separated list of key=value.
                       JSON is acceptable and preferred way for complex parameters
                                 Volume id
--volume-id VOLUME ID
-h, --help
                         Print help
Provider specific options:
 ec2:
  --volume:
 gce:
  --volume:
 libvirt:
  --volume:
   pool name
                  One of available storage pools
                 String value, eg. 10G
   capacity
                  Possible values: raw, qcow2
   format_type
 openstack:
  --volume:
 ovirt:
  --volume:
   size gb
                 Volume size in GB, integer value
                    ID of storage domain
   storage_domain
   bootable
                 Boolean, only one volume can be bootable
 rackspace:
  --volume:
 vmware:
  --volume:
   name
                   Storage Pod ID from VMware
   storage_pod
                 Datastore ID from VMware
   datastore
   size_gb
                 Integer number, volume size in GB
```

thin true/false eager_zero true/false

mode persistent/independent persistent/independent nonpersistent

2.13. HAMMER COMPUTE-RESOURCE

Manipulate compute resources

Usage:

hammer compute-resource [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

clusters List available clusters for a compute resource

create Create a compute resource delete Delete a compute resource

flavors List available flavors for a compute resource folders List available folders for a compute resource image View and manage compute resource's images images List available images for a compute resource

info Show a compute resource list List all compute resources

networks
resource-pools
security-groups
List available networks for a compute resource
List resource pools for a compute resource cluster
List available security groups for a compute resource

storage-domains List storage domains for a compute resource storage-pods List storage pods for a compute resource

update Update a compute resource

zones List available zone for a compute resource

Options:

-h, --help Print help

2.13.1. hammer compute-resource clusters

List available clusters for a compute resource

Usage:

hammer compute-resource clusters [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Compute resource name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.2. hammer compute-resource create

Create a compute resource

Usage:

hammer compute-resource create [OPTIONS]

Options:

--caching-enabled CACHING_ENABLED Enable caching, for VMware only

One of true/false, yes/no, 1/0.

--datacenter DATACENTER For RHEV, VMware Datacenter

--description DESCRIPTION

--display-type DISPLAY_TYPE For Libvirt only Possible value(s): 'VNC', 'SPICE'

--domain DOMAIN For RHEL OpenStack Platform (v3) only

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ovirt-quota OVIRT_QUOTA For RHEV only, ID of quota to use

--password PASSWORD Password for RHEV, EC2, VMware, RHEL OpenStack

Platform. Secret key for EC2

--project-domain-id PROJECT_DOMAIN_ID For RHEL OpenStack Platform (v3) only

--project-domain-name PROJECT_DOMAIN_NAME For RHEL OpenStack Platform (v3) only --provider PROVIDER Providers include Libvirt, Ovirt, EC2, Vmware, Openstack,

Rackspace, GCE

--public-key PUBLIC_KEY For RHEV only

--public-key-path PUBLIC_KEY_PATH Path to a file that contains oVirt public key (For oVirt only)

--region REGION For EC2 only, use 'us-gov-west-1' for GovCloud region

--server SERVER For VMware

--set-console-password SET_CONSOLE_PASSWORD For Libvirt and VMware only

One of true/false, yes/no, 1/0.

--tenant TENANT For RHEL OpenStack Platform only

--url URL URL for Libvirt, RHEV, RHEL OpenStack Platform and Rackspace

For RHEV only

One of true/false, yes/no, 1/0.

Username for RHEV, EC2, VMware, RHEL OpenStack Platform.

--user USER Access Key for

--use-v4 USE_V4

EC2.

--uuid UUID Deprecated, please use datacenter

-h, --help Print help

2.13.3. hammer compute-resource delete

Delete a compute resource

Usage:

hammer compute-resource delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Compute resource name

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.4. hammer compute-resource flavors

List available flavors for a compute resource

Usage:

hammer compute-resource flavors [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Compute resource name

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.13.5. hammer compute-resource folders

List available folders for a compute resource

Usage:

hammer compute-resource folders [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Compute resource name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.6. hammer compute-resource image

View and manage compute resource's images

Usage:

hammer compute-resource image [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

available Show images available for addition

create Create an image delete Delete an image info Show an image

list List all images for a compute resource

update Update an image

Options:

-h, --help Print help

2.13.6.1. hammer compute-resource image available

Show images available for addition

Usage:

hammer compute-resource image available [OPTIONS]

Options:

--compute-resource NAME Compute resource name

--compute-resource-id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.13.6.2. hammer compute-resource image create

Create an image

Usage:

hammer compute-resource image create [OPTIONS]

Options:

- --architecture-id ARCHITECTURE_ID
- --compute-resource COMPUTE_RESOURCE_NAME Compute resource name
- $\hbox{--compute-resource-id COMPUTE_RESOURCE_ID}$
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME
- --operatingsystem-id OPERATINGSYSTEM ID
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --password PASSWORD
- --user-data USER_DATA Whether or not the image supports user data

One of true/false, yes/no, 1/0.

- --username USERNAME
- --uuid UUID Template ID in the compute resource

-h, --help Print help

2.13.6.3. hammer compute-resource image delete

Delete an image

Usage:

hammer compute-resource image delete [OPTIONS]

Options:

- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE RESOURCE ID
- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.13.6.4. hammer compute-resource image info

Show an image

Usage:

hammer compute-resource image info [OPTIONS]

Options:

- --architecture-id ARCHITECTURE_ID

- --compute-resource COMPUTE_RESOURCE_NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --operatingsystem-id OPERATINGSYSTEM ID

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.13.6.5. hammer compute-resource image list

List all images for a compute resource

Usage:

hammer compute-resource image list [OPTIONS]

Options:

- --architecture-id ARCHITECTURE_ID
- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --operatingsystem-id OPERATINGSYSTEM ID
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

architecture integer compute_resource string name string

operatingsystem integer

user data Values: true, false

username string

2.13.6.6. hammer compute-resource image update

Update an image

Usage:

hammer compute-resource image update [OPTIONS]

Options:

--architecture-id ARCHITECTURE ID

- --compute-resource COMPUTE RESOURCE NAME Compute resource name
- --compute-resource-id COMPUTE_RESOURCE_ID
- --id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--new-name NEW_NAME

--operatingsystem-id OPERATINGSYSTEM_ID

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--password PASSWORD

--user-data USER_DATA Whether or not the image supports user data

One of true/false, yes/no, 1/0.

--username USERNAME

--uuid UUID Template ID in the compute resource

-h, --help Print help

2.13.7. hammer compute-resource images

List available images for a compute resource

Usage:

hammer compute-resource images [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME Compute resource name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.8. hammer compute-resource info

Show a compute resource

Usage:

hammer compute-resource info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME Compute resource name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.9. hammer compute-resource list

List all compute resources

Usage:

hammer compute-resource list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

id integer
location string
location_id integer
name string
organization string
organization_id integer
type string

2.13.10. hammer compute-resource networks

List available networks for a compute resource

Usage:

hammer compute-resource networks [OPTIONS]

Options:

--cluster-id CLUSTER_ID

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Compute resource name

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.13.11. hammer compute-resource resource-pools

List resource pools for a compute resource cluster

Usage:

hammer compute-resource resource-pools [OPTIONS]

Options:

- --cluster-id CLUSTER_ID
- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Compute resource name
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.13.12. hammer compute-resource security-groups

List available security groups for a compute resource

Usage:

hammer compute-resource security-groups [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --name NAME Compute resource name
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.13.13. hammer compute-resource storage-domains

List storage domains for a compute resource

Usage:

hammer compute-resource storage-domains [OPTIONS]

Options:

- --cluster-id CLUSTER_ID
- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Compute resource name
- --organization ORGANIZATION NAME Organization name

- --organization-title ORGANIZATION_TITLE Organization title
- --storage-domain STORAGE_DOMAIN
- -h, --help Print help

2.13.14. hammer compute-resource storage-pods

List storage pods for a compute resource

Usage:

hammer compute-resource storage-pods [OPTIONS]

Options:

- --cluster-id CLUSTER_ID
- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Compute resource name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --storage-pod STORAGE POD
- -h, --help Print help

2.13.15. hammer compute-resource update

Update a compute resource

Usage:

hammer compute-resource update [OPTIONS]

Options:

--caching-enabled CACHING ENABLED Enable caching, for VMware only

One of true/false, yes/no, 1/0.

--datacenter DATACENTER For RHEV, VMware Datacenter

--description DESCRIPTION

--display-type DISPLAY_TYPE For Libvirt only

Possible value(s): 'VNC', 'SPICE'

--domain DOMAIN For RHEL OpenStack Platform (v3) only

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Compute resource name

--new-name NEW_NAME

--organization ORGANIZATION_NAME Organization name

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ovirt-quota OVIRT_QUOTA For RHEV only, ID of quota to use

--password PASSWORD Password for RHEV, EC2, VMware, RHEL OpenStack

Platform. Secret key for EC2

--project-domain-id PROJECT_DOMAIN_ID For RHEL OpenStack Platform (v3) only

--project-domain-name PROJECT_DOMAIN_NAME For RHEL OpenStack Platform (v3) only --provider PROVIDER Providers include Libvirt, Ovirt, EC2, Vmware, Openstack,

Rackspace, GCE

--public-key PUBLIC_KEY For RHEV only

--public-key-path PUBLIC_KEY_PATH Path to a file that contains oVirt public key (For oVirt

only)

--region REGION For EC2 only, use 'us-gov-west-1' for GovCloud region

--server SERVER For VMware

--set-console-password SET_CONSOLE_PASSWORD For Libvirt and VMware only

One of true/false, yes/no, 1/0.

--tenant TENANT For RHEL OpenStack Platform only

--url URL URL for Libvirt, RHEV, RHEL OpenStack Platform and Rackspace

--use-v4 USE_V4 For RHEV only

One of true/false, yes/no, 1/0.

--user USER Username for RHEV, EC2, VMware, RHEL OpenStack Platform.

Access Key for

EC2.

--uuid UUID Deprecated, please use datacenter

-h, --help Print help

2.13.16. hammer compute-resource zones

List available zone for a compute resource

Usage:

hammer compute-resource zones [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Compute resource name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.14. HAMMER CONFIG-GROUP

Manipulate config groups

Usage:

hammer config-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a config group
delete Delete a config group
info Show a config group
list List of config groups
update Update a config group

Options:

-h, --help Print help

2.14.1. hammer config-group create

Create a config group

Usage:

hammer config-group create [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME

--organization-title ORGANIZATION_TITLE Organization title

--puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.14.2. hammer config-group delete

Delete a config group

Usage:

hammer config-group delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID
- $\hbox{--organization-title ORGANIZATION_TITLE Organization title} \\$
- -h, --help Print help

2.14.3. hammer config-group info

Show a config group

Usage:

hammer config-group info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.14.4. hammer config-group list

List of config groups

Usage:

hammer config-group list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'

- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

class string name string

2.14.5. hammer config-group update

Update a config group

_

Usage:

hammer config-group update [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --new-name NEW NAME
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --puppet-class-ids PUPPET_CLASS_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.15. HAMMER CONFIG-REPORT

Browse and read reports

Usage:

hammer config-report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Delete a report info Show a report list List all reports

Options:

-h, --help Print help

2.15.1. hammer config-report delete

Delete a report

Usage:

hammer config-report delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title

- --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title -h, --help Print help
- 2.15.2. hammer config-report info

Show a report

Usage:

hammer config-report info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.15.3. hammer config-report list

List all reports

Usage:

hammer config-report list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

applied integer environment string

eventful Values: true, false

failed integer failed_restarts integer host string host id integer hostgroup string hostgroup_fullname string hostgroup_title string last report datetime location string

log text organization string origin string pending integer datetime reported resource text restarted integer skipped integer

2.16. HAMMER CONTENT-VIEW

Manipulate content views

Usage:

hammer content-view [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-repository Associate a resource

add-version Add a content view version to a composite view

component View and manage components

copy
create
Create a content view
delete
Delete a content view
filter
View and manage filters
info
Show a content view
list
List content views

publish Publish a content view

puppet-module View and manage puppet modules purge Delete old versions of a content view

remove Remove versions and/or environments from a content view and reassign

systems and keys

remove-from-environment Remove a content view from an environment

remove-repository Disassociate a resource

remove-version Remove a content view version from a composite view

update Update a content view

version View and manage content view versions

Options:

-h, --help Print help

2.16.1. hammer content-view add-repository

Associate a resource

Usage:

hammer content-view add-repository [OPTIONS]

Options:

--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.16.2. hammer content-view add-version

Add a content view version to a composite view

Usage:

hammer content-view add-version [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.3. hammer content-view component

View and manage components

Usage:

hammer content-view component [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add Add components to the content view

list List components attached to this content view remove Remove components from the content view

update Update a component associated with the content view

Options:

-h, --help Print help

2.16.3.1. hammer content-view component add

Add components to the content view

Usage:

hammer content-view component add [OPTIONS]

Options:

--component-content-view COMPONENT_CONTENT_VIEW_NAME Content View

name of the component who's latest version is desired

--component-content-view-id COMPONENT_CONTENT_VIEW_ID Content View

identifier of the component who's latest version is desired

--component-content-view-version COMPONENT_CONTENT_VIEW_VERSION_VERSION Content View Version number of the component. Either use this or --component-content-view-version-id option

--component-content-view-version-id COMPONENT_CONTENT_VIEW_VERSION_ID Content View Version identifier of the component

--composite-content-view COMPOSITE_CONTENT_VIEW_NAME Name of the

composite content view

--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID Composite content

view identifier

--latest Select the latest version of the components content

view is desired

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.3.2. hammer content-view component list

List components attached to this content view

Usage:

hammer content-view component list [OPTIONS]

Options:

--composite-content-view COMPOSITE_CONTENT_VIEW_NAME Name of the composite content view

--composite-content-view-id COMPOSITE_CONTENT_VIEW_ID Composite content view identifier

--organization ORGANIZATION NAME

Organization name to search by

--organization-id ORGANIZATION_ID

Organization ID to search by

--organization-label ORGANIZATION LABEL

Organization label to search by

-h, --help Print help

2.16.3.3. hammer content-view component remove

Remove components from the content view

Usage:

hammer content-view component remove [OPTIONS]

Options:

--component-content-view-ids COMPONENT_CONTENT_VIEW_IDs Array of component content view identifiers to remove. Comma separated list of values

--component-content-views COMPONENT_CONTENT_VIEW_NAMES Array of component content view names to remove. Comma separated list of values

--component-ids COMPONENT_IDS

Array of content view component IDs to

remove. Identifier of the component

Association

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --composite-content-view COMPOSITE CONTENT VIEW NAME Name of the composite content view
- --composite-content-view-id COMPOSITE_CONTENT_VIEW_ID Composite content view identifier
- --organization ORGANIZATION NAME

Organization name to search by

--organization-id ORGANIZATION ID

Organization ID to search by

--organization-label ORGANIZATION LABEL

Organization label to search by

-h, --help

Print help

2.16.3.4. hammer content-view component update

Update a component associated with the content view

Usage:

hammer content-view component update [OPTIONS]

Options:

--component-content-view COMPONENT CONTENT VIEW NAME Content View

name of the component who's latest version is desired

--component-content-view-id COMPONENT_CONTENT_VIEW_ID Content View

identifier of the component who's latest version is desired

--component-content-view-version COMPONENT_CONTENT_VIEW_VERSION_VERSION Content View Version number of the component. Either use this or --component-content-view-version-id

--component-content-view-version-id COMPONENT_CONTENT_VIEW_VERSION_ID Content

View Version identifier of the component

--composite-content-view COMPOSITE CONTENT VIEW NAME Name of the

composite content view

--composite-content-view-id COMPOSITE CONTENT VIEW ID Composite content

view identifier

--id ID Content view component ID. Identifier of the

component association

--latest Select the latest version of the components content

view is desired

Organization name to search by --organization ORGANIZATION NAME --organization-id ORGANIZATION_ID Organization ID to search by Organization label to search by

--organization-label ORGANIZATION_LABEL

-h, --help Print help

2.16.4. hammer content-view copy

Copy a content view

Usage:

hammer content-view copy [OPTIONS]

Options:

--id ID Content view numeric identifier

--name NAME Content view name to search by --new-name NEW NAME New content view name

--organization ORGANIZATION NAME Organization name to search by

- --organization-id ORGANIZATION_ID
 Organization ID to search by
- --organization-label ORGANIZATION_LABEL Organization label to search by
- -h, --help Print help

2.16.5. hammer content-view create

Create a content view

Usage:

hammer content-view create [OPTIONS]

Options:

--auto-publish AUTO_PUBLISH Enable/Disable auto publish of composite view

One of true/false, yes/no, 1/0.

--component-ids COMPONENT_IDS List of component content view version ids for composite

views

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--composite Create a composite content view

--description DESCRIPTION Description for the content view

--label LABEL Content view label

--name NAME Name of the content view

--organization-label ORGANIZATION_LABEL Organization label to search by

--repository-ids REPOSITORY_IDS List of repository ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--solve-dependencies SOLVE_DEPENDENCIES Solve RPM dependencies by default on Content View publish, defaults to

False

One of true/false, yes/no, 1/0.

-h, --help Print help

2.16.6. hammer content-view delete

Delete a content view

Usage:

hammer content-view delete [OPTIONS]

Options:

--async Do not wait for the task
--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID to search by --organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.7. hammer content-view filter

View and manage filters

Usage:

hammer content-view filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-repository Associate a resource

create Create a filter for a content view

delete Delete a filter info Show filter info list List filters

remove-repository Disassociate a resource View and manage filter rules

update Update a filter

Options:

-h, --help Print help

2.16.7.1. hammer content-view filter add-repository

Associate a resource

Usage:

hammer content-view filter add-repository [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Filter identifier

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID to search by

--organization-id OnGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by Product-id PRODUCT_ID Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.16.7.2. hammer content-view filter create

create a filter for a content view

Usage:

hammer content-view filter create [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME
Content view name to search by

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--description DESCRIPTION Description of the filter

--inclusion INCLUSION Specifies if content should be included or excluded, default:

Inclusion=false

One of true/false, yes/no, 1/0.

--name NAME Name of the filter

--organization-id ORGANIZATION_ID
Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--original-packages ORIGINAL_PACKAGES Add all packages without errata to the included/excluded list. (package

Filtor only

One of true/false, yes/no, 1/0.

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier

--repositories REPOSITORY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--repository-ids REPOSITORY_IDS List of repository ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--type TYPE Type of filter (e.g. rpm, package_group, erratum, docker)

-h, --help Print help

2.16.7.3. hammer content-view filter delete

delete a filter

Usage:

hammer content-view filter delete [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Filter identifier

--name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.7.4. hammer content-view filter info

show filter info

Usage:

hammer content-view filter info [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Filter identifier

--name NAME Name to search by

- --organization-label ORGANIZATION_LABEL Organization label to search by
- -h, --help Print help

2.16.7.5. hammer content-view filter list

list filters

Usage:

hammer content-view filter list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier --full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME Filter content view filters by name --order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by --organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string
--types TYPES Types of filters

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.16.7.6. hammer content-view filter remove-repository

Disassociate a resource

Usage:

hammer content-view filter remove-repository [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Filter identifier

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by --organization-label ORGANIZATION LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID Repository ID

-h, --help Print help

2.16.7.7. hammer content-view filter rule

View and manage filter rules

Usage:

hammer content-view filter rule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a filter rule. The parameters included should be based upon the filter

type.

delete Delete a filter rule info Show filter rule info list List filter rules

update Update a filter rule. The parameters included should be based upon the filter

type.

Options:

-h, --help Print help

2.16.7.7.1. hammer content-view filter rule create

Create a filter rule. The parameters included should be based upon the filter type.

Usage:

hammer content-view filter rule create [OPTIONS]

Options:

--architecture ARCHITECTURE Package: architecture

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT VIEW ID Content view numeric identifier

--date-type DATE TYPE Erratum: search using the 'Issued On' or 'Updated On'

Column of the errata. Values are 'issued'/'updated'

--end-date END_DATE Erratum: end date (YYYY-MM-DD)

--errata-id ERRATA ID Erratum: id

--errata-ids ERRATA IDS Erratum: IDs or a select all object

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--max-version MAX_VERSION Package: maximum version
--min-version MIN_VERSION Package: minimum version

--name NAME Package, package group, or docker tag names

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--names NAMES Package and package group names

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by --start-date START_DATE Erratum: start date (YYYY-MM-DD)

--types TYPES Erratum: types (enhancement, bugfix, security)

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--uuid UUID --version VERSION Package group: uuid Package: version

-h, --help Print help

2.16.7.7.2. hammer content-view filter rule delete

Delete a filter rule

Usage:

hammer content-view filter rule delete [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by

--content-view-filter-id CONTENT VIEW FILTER ID Filter identifier

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Rule identifier

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.7.7.3. hammer content-view filter rule info

Show filter rule info

Usage:

hammer content-view filter rule info [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT VIEW FILTER NAME Name to search by

--content-view-filter-id CONTENT VIEW FILTER ID Filter identifier

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Rule identifier

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by

-h, --help Print help

2.16.7.7.4. hammer content-view filter rule list

List filter rules

Usage:

hammer content-view filter rule list [OPTIONS]

Options:

--content-view CONTENT VIEW NAME Content view name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT VIEW ID Content view numeric identifier

--errata-id ERRATA_ID Errata_id of the content view filter rule
--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME Name of the content view filter rule --order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by --organization-label ORGANIZATION_LABEL

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.16.7.7.5. hammer content-view filter rule update

Update a filter rule. The parameters included should be based upon the filter type.

Usage:

hammer content-view filter rule update [OPTIONS]

Options:

--architecture ARCHITECTURE Package: architecture

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter CONTENT VIEW FILTER NAME Name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT_VIEW_ID Content view numeric identifier --end-date END_DATE Erratum: end date (YYYY-MM-DD)

--errata-id ERRATA_ID Erratum: id --id ID Rule identifier

--max-version MAX_VERSION Package: maximum version
--min-version MIN_VERSION Package: minimum version

--name NAME Name to search by

--new-name NEW_NAME Package, package group, or docker tag: name

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by
--start-date START DATE Erratum: start date (YYYY-MM-DD)

--types TYPES Erratum: types (enhancement, bugfix, security)

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--version VERSION Package: version

-h, --help Print help

2.16.7.8. hammer content-view filter update

update a filter

Usage:

hammer content-view filter update [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Filter identifier

--inclusion INCLUSION Specifies if content should be included or excluded, default:

Inclusion=false

One of true/false, yes/no, 1/0.

--name NAME Name to search by

--new-name NEW NAME New name for the filter

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--original-packages ORIGINAL_PACKAGES Add all packages without errata to the

included/excluded list. (package

Filter only)

One of true/false, yes/no, 1/0.

--repositories REPOSITORY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--repository-ids REPOSITORY_IDS List of repository ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.16.8. hammer content-view info

Show a content view

Usage:

hammer content-view info [OPTIONS]

Options:

--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.16.9. hammer content-view list

List content views

Usage:

hammer content-view list [OPTIONS]

Options:

--composite COMPOSITE Filter only composite content views

One of true/false, yes/no, 1/0.

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search

bν

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--name NAME Name of the content view

--noncomposite NONCOMPOSITE Filter out composite content views

One of true/false, yes/no, 1/0.

--nondefault NONDEFAULT Filter out default content views

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--without WITHOUT Do not include this array of content views

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.16.10. hammer content-view publish

Publish a content view

Usage:

hammer content-view publish [OPTIONS]

Options:

--async Do not wait for the task

--description DESCRIPTION Description for the new published content view version

--id ID Content view identifier

--major MAJOR Override the major version number
--minor MINOR Override the minor version number
--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by --repos-units REPOS_UNITS Specify the list of units in each repo

Comma separated list of values defined by a schema. See Option details

section below.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--repos-units "label=string\,rpm_filenames=array, ... "

2.16.11. hammer content-view puppet-module

View and manage puppet modules

Usage:

hammer content-view puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add Add a puppet module to the content view

list List content view puppet modules

remove Remove a puppet module from the content view

Options:

-h, --help Print help

2.16.11.1. hammer content-view puppet-module add

Add a puppet module to the content view

Usage:

hammer content-view puppet-module add [OPTIONS]

Options:

--author AUTHOR Puppet module's author to search by

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID The id of the puppet module to associate
--name NAME Puppet module name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--uuid UUID Puppet module's UUID to search by

-h, --help Print help

2.16.11.2. hammer content-view puppet-module list

List content view puppet modules

Usage:

hammer content-view puppet-module list [OPTIONS]

Options:

--author AUTHOR Author of the puppet module

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME Name of the puppet module --order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--uuid UUID Uuid of the puppet module

-h, --help Print help

2.16.11.3. hammer content-view puppet-module remove

Remove a puppet module from the content view

Usage:

hammer content-view puppet-module remove [OPTIONS]

Options:

--author AUTHOR Puppet module's author to search by

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Puppet module ID

--name NAME Puppet module name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--uuid UUID Puppet module's UUID to search by

-h, --help Print help

2.16.12. hammer content-view purge

Delete old versions of a content view

Usage:

hammer content-view purge [OPTIONS]

Options:

--async Do not wait for the task

--count COUNT Count of unused versions to keep

Default: 3

--id ID Content View numeric identifier

--name NAME Content View name

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

Unfortunately the server does not support such operation.

2.16.13. hammer content-view remove

Remove versions and/or environments from a content view and reassign systems and keys

Usage:

hammer content-view remove [OPTIONS]

Options:

--async Do not wait for the task

--content-view-version-ids VERSION_IDS Version ids to remove

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--content-view-versions CONTENT VIEW VERSION VERSIONS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environment-ids ENVIRONMENT IDS

(--environment-ids is deprecated: Use --

lifecycle-environment-ids instead)

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environments ENVIRONMENT NAMES

(--environments is deprecated: Use --

lifecycle-environments instead)

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID Content view numeric identifier

--key-content-view-id KEY_CONTENT_VIEW_ID Content view to reassign orphaned

activation keys to

--key-environment-id KEY ENVIRONMENT ID Environment to reassign orphaned activation keys to

--lifecycle-environment-ids LIFECYCLE ENVIRONMENT IDS Environment ids to remove

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lifecycle-environments LIFECYCLE_ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

Content view name to search by

--organization ORGANIZATION NAME

Organization name to search by

--organization-id ORGANIZATION ID

Organization ID to search by

--organization-label ORGANIZATION_LABEL

Organization label to search by

--system-content-view-id SYSTEM CONTENT VIEW ID Content view to reassign orphaned systems to

systems to

-h, --help Print help

2.16.14. hammer content-view remove-from-environment

Remove a content view from an environment

hammer content-view remove-from-environment [OPTIONS]

Options:

--async Do not wait for the task

--environment ENVIRONMENT NAME Lifecycle environment name to search by (-environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID

(--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--id ID Content view numeric identifier

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE ENVIRONMENT ID

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID

--organization-label ORGANIZATION_LABEL

-h, --help Print help

Organization ID to search by
Organization label to search by

2.16.15. hammer content-view remove-repository

Disassociate a resource

Usage:

hammer content-view remove-repository [OPTIONS]

Options:

--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID Repository ID

-h, --help Print help

2.16.16. hammer content-view remove-version

Remove a content view version from a composite view

Usage:

hammer content-view remove-version [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

 $\hbox{--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number} \\$

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--id ID Content view numeric identifier

--name NAME Content view name to search by

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by

b leads

-h, --help Print help

2.16.17. hammer content-view update

Update a content view

Usage:

hammer content-view update [OPTIONS]

Options:

--auto-publish AUTO_PUBLISH Enable/Disable auto publish of composite view

One of true/false, yes/no, 1/0.

--component-ids COMPONENT_IDS List of component content view version ids for composite

views

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION Description for the content view

--id ID Content view identifier

--name NAME Content view name to search by
--new-name NEW_NAME New name for the content view
--organization ORGANIZATION_NAME Organization name to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--repository-ids REPOSITORY IDS List of repository ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--solve-dependencies SOLVE_DEPENDENCIES Solve RPM dependencies by default on Content View publish, defaults to

False

One of true/false, yes/no, 1/0.

-h, --help Print help

2.16.18. hammer content-view version

View and manage content view versions

Usage:

hammer content-view version [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Remove content view version export Export a content view version

export-legacy Export a content view (legacy method)

import Import a content view version

incremental-update Perform an Incremental Update on one or more Content View Versions

info Show content view version list List content view versions

promote Promote a content view version

republish-repositories Forces a republish of the version's repositories' metadata

Options:

-h, --help Print help

2.16.18.1. hammer content-view version delete

Remove content view version

Usage:

hammer content-view version delete [OPTIONS]

Options:

--async Do not wait for the task

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT VIEW ID Content view numeric identifier

--environment ENVIRONMENT NAME Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--id ID Content view version identifier

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

Content view version number --version VERSION

-h, --help Print help

2.16.18.2. hammer content-view version export

Export a content view version

Usage:

hammer content-view version export [OPTIONS]

Options:

--export-dir EXPORT DIR Directory to put content view version export into.

--id ID Content View Version numeric identifier

Print help -h, --help

2.16.18.3. hammer content-view version export-legacy

Export a content view (legacy method)

Usage:

hammer content-view version export-legacy [OPTIONS]

Options:

Do not wait for the task --async

--content-view CONTENT VIEW NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier --environment ENVIRONMENT_NAME Lifecycle environment name t

Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--export-to-iso EXPORT_TO_ISO Export to ISO format

One of true/false, yes/no, 1/0.

Content view version identifier --id ID

Maximum size of each ISO in MB --iso-mb-size ISO MB SIZE

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID

Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--since SINCE Optional date of last export (ex: 2010-01-01T12:00:00Z)

--version VERSION Content view version number

-h, --help Print help

2.16.18.4. hammer content-view version import

Import a content view version

Usage:

hammer content-view version import [OPTIONS]

Options:

--async Do not wait for the task

--export-tar EXPORT TAR Location of export tar on disk

--organization-id ORGANIZATION_ID Organization numeric identifier

-h, --help Print help

2.16.18.5. hammer content-view version incremental-update

Perform an Incremental Update on one or more Content View Versions

Usage:

hammer content-view version incremental-update [OPTIONS]

Options:

--async Do not wait for the task

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--deb-ids DEB_IDS Deb Package ids to copy into the new versions

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--debs DEB_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION The description for the new generated Content View

Versions

--errata-ids ERRATA_IDS Errata ids to copy into the new versions

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--host-ids HOST_IDS IDs of hosts to update

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lifecycle-environment-ids ENVIRONMENT_IDS List of lifecycle environment IDs to update the content view version in

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lifecycle-environments ENVIRONMENTS List of lifecycle environment names to update the content view version in

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name for resolving lifecycle

environment names

--organization-id ORGANIZATION_ID Organization id for resolving lifecycle environment names

--package-ids PACKAGE_IDS Package ids to copy into the new versions

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--packages PACKAGE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--propagate-all-composites PROPAGATE_ALL_COMPOSITES If true, will publish a new composite version using any specified

Content_view_version_id that has been promoted to a lifecycle

environment

One of true/false, yes/no, 1/0.

--puppet-module-ids PUPPET_MODULE_IDS Puppet Module ids to copy into the new versions

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-modules PUPPET_MODULE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--resolve-dependencies RESOLVE_DEPENDENCIES If true, when adding the specified errata or packages, any needed

Dependencies will be copied as well. Defaults to true

One of true/false, yes/no, 1/0.

--update-all-hosts UPDATE Update all editable and applicable hosts within the specified Content View and \

Lifecycle Environments One of true/false, yes/no, 1/0.

-h, --help Print help

2.16.18.6. hammer content-view version info

Show content view version

Usage:

hammer content-view version info [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--id ID Content view version identifier

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--version VERSION Content view version number

-h, --help Print help

2.16.18.7. hammer content-view version list

List content view versions

Usage:

hammer content-view version list [OPTIONS]

Options:

--composite-version-id COMPOSITE_VERSION_ID Filter versions that are components in the

specified composite version

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return
--puppet-module PUPPET_MODULE_NAME Name to search by
--puppet-module-id PUPPET_MODULE_ID A puppet module identifier

--search SEARCH Search string

--triggered-by-id TRIGGERED BY ID Filter composite versions whose publish was

triggered by the specified

Component version

--version VERSION Filter versions by version number

-h, --help Print help

2.16.18.8. hammer content-view version promote

Promote a content view version

Usage:

hammer content-view version promote [OPTIONS]

Options:

--async Do not wait for the task

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--description DESCRIPTION The description for the content view version promotion

--environment-ids ENVIRONMENT_IDS Identifiers for Lifecycle Environment (--environment-ids is deprecated: Use --lifecycle-environment-ids instead)

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--force Force content view promotion and bypass lifecycle environment restriction

--from-lifecycle-environment FROM_ENVIRONMENT_ID Environment name from where to promote its version from (if version is unknown)

--from-lifecycle-environment-id FROM_ENVIRONMENT_ID Id of the environment from where to promote its version from (if version is unknown)

--id ID Content view version identifier

--lifecycle-environment-ids LIFECYCLE_ENVIRONMENT_IDS Identifiers for Lifecycle Environment Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by --to-lifecycle-environment TO_ENVIRONMENT ID Id of the target environment

--version VERSION Content view version number

-h, --help Print help

2.16.18.9. hammer content-view version republish-repositories

Forces a republish of the version's repositories' metadata

Usage:

hammer content-view version republish-repositories [OPTIONS]

Options:

--async Do not wait for the task

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--id ID Content view version identifier

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--version VERSION Content view version number

-h, --help Print help

2.17. HAMMER DEFAULTS

Defaults management

Usage:

hammer defaults [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add Add a default parameter to config

delete Delete a default param
list List all the default parameters
providers List all the providers

Options:

-h, --help Print help

2.17.1, hammer defaults add

Add a default parameter to config

Usage:

hammer defaults add [OPTIONS]

Options:

--param-name OPTION_NAME The name of the default option (e.g. organization_id)

--provider OPTION_PROVIDER The name of the provider providing the value. For list available

providers see 'hammer defaults providers'

-h, --help Print help

2.17.2. hammer defaults delete

Delete a default param

Usage:

hammer defaults delete [OPTIONS]

Options:

-h, --help Print help

2.17.3. hammer defaults list

List all the default parameters

Usage:

hammer defaults list [OPTIONS]

Options:

-h, --help Print help

2.17.4. hammer defaults providers

List all the providers

Usage:

hammer defaults providers [OPTIONS]

Options:

-h, --help Print help

2.18. HAMMER DISCOVERY

Manipulate discovered hosts.

Usage:

hammer discovery [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

auto-provision Auto provision a host delete Delete a discovered host

facts List all fact values info Show a discovered host list List all discovered hosts

provision Provision a discovered host

reboot Reboot a host

refresh-facts Refresh the facts of a host

Options:

-h, --help Print help

2.18.1. hammer discovery auto-provision

Auto provision a host

Usage:

hammer discovery auto-provision [OPTIONS]

Options:

--all Auto provision all discovered hosts

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.18.2. hammer discovery delete

Delete a discovered host

Usage:

hammer discovery delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

```
--location-title LOCATION_TITLE Location title
--name NAME Name to search by
```

- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.18.3. hammer discovery facts

List all fact values

Usage:

hammer discovery facts [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

string fact short name string facts string string host host.hostgroup string host id integer location string location_id integer name string organization string organization_id integer origin string

reported_at datetime short_name string type string value string

2.18.4. hammer discovery info

Show a discovered host

Usage:

hammer discovery info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.18.5. hammer discovery list

List all discovered hosts

Usage:

hammer discovery list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort results

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

2.18.6. hammer discovery provision

Provision a discovered host

Usage:

hammer discovery provision [OPTIONS]

Options:

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE ID

--ask-root-password ASK_ROOT_PW One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

--capabilities CAPABILITIES

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID
--enabled ENABLED

Numerical ID or domain name
One of true/false, yes/no, 1/0.

--host-parameters-attributes HOST_PARAMETERS_ATTRIBUTES Comma separated list of values.

Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--id ID

--image IMAGE_NAME

--image-id IMAGE ID

Name to search by

--interface INTERFACE

Interface parameters Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

Can be specified multiple times.

--ip IP

Not required if using a subnet with DHCP Capsule

Not required if it's a virtual machine

Medium name

Model name

One of true/false, yes/no, 1/0.

Location name

Location title

--location LOCATION NAME

--location-id LOCATION ID

--location-title LOCATION TITLE

--mac MAC

--managed MANAGED

--medium MEDIUM NAME

--medium-id MEDIUM ID

--model MODEL_NAME

--model-id MODEL ID

--name NAME

Name to search by

--new-name NEW NAME

--operatingsystem OPERATINGSYSTEM TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM ID

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title One of true/false, yes/no, 1/0. --overwrite OVERWRITE

--owner-id OWNER ID

--parameters PARAMS Host parameters

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--partition-table PARTITION_TABLE NAME

Partition table name

--partition-table-id PARTITION TABLE ID

--progress-report-id PROGRESS REPORT ID

UUID to track orchestration tasks status,

/api/orchestration/:UUID/tasks

--provision-method METHOD

Possible value(s): 'build', 'image'

--puppet-ca-proxy-id PUPPET CA PROXY ID

--puppet-environment PUPPET_ENVIRONMENT_NAME

Puppet environment name

--puppet-environment-id PUPPET ENVIRONMENT ID

--puppet-proxy-id PUPPET PROXY ID

--puppetclass-ids PUPPETCLASS IDS

Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--pxe-loader PXE LOADER

DHCP filename option (Grub2 or PXELinux by

default)

Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',

'Grub UEFI', 'Grub2 BIOS', 'Grub2 ELF', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE Chain UEFI'

--root-password ROOT PW

--sp-subnet-id SP SUBNET ID

--subnet SUBNET NAME Subnet name

--subnet-id SUBNET_ID

-h, --help Print help

2.18.7. hammer discovery reboot

Reboot a host

Usage:

hammer discovery reboot [OPTIONS]

Options:

--all Reboot all discovered hosts

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.18.8. hammer discovery refresh-facts

Refresh the facts of a host

Usage:

hammer discovery refresh-facts [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.19. HAMMER DISCOVERY-RULE

Manipulate discovered rules.

Usage:

hammer discovery-rule [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a discovery rule

delete Delete a rule

info Show a discovery rule list List all discovery rules update Update a rule

Options:

-h, --help Print help

2.19.1. hammer discovery-rule create

Create a discovery rule

Usage:

hammer discovery-rule create [OPTIONS]

Options:

--enabled ENABLED Flag is used for temporary shutdown of rules

One of true/false, yes/no, 1/0.

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--hostname HOSTNAME Defines a pattern to assign human-readable hostnames to the

matching hosts

--hosts-limit HOSTS_LIMIT

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS Location ID for provisioned hosts

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--max-count MAX_COUNT

Enables to limit maximum amount of provisioned hosts per

rule

--name NAME Represents rule name shown to the users

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS Organization ID for provisioned hosts

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--priority PRIORITY Puts the rules in order, low numbers go first. Must be greater then

zero

--search SEARCH Query to match discovered hosts for the particular rule

-h, --help Print help

2.19.2. hammer discovery-rule delete

Delete a rule

Usage:

hammer discovery-rule delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.19.3. hammer discovery-rule info

Show a discovery rule

Usage:

hammer discovery-rule info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.19.4. hammer discovery-rule list

List all discovery rules

Usage:

hammer discovery-rule list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort results
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

2.19.5. hammer discovery-rule update

Update a rule

Usage:

hammer discovery-rule update [OPTIONS]

Options:

--enabled ENABLED Flag is used for temporary shutdown of rules

One of true/false, yes/no, 1/0.

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--hostname HOSTNAME Defines a pattern to assign human-readable hostnames to the

matching hosts

--hosts-limit HOSTS_LIMIT

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION IDS Location ID for provisioned hosts

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--max-count MAX_COUNT Enables to limit maximum amount of provisioned hosts per rule

--name NAME Name to search by

--new-name NEW NAME Represents rule name shown to the users

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS
Organization ID for provisioned hosts

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--priority PRIORITY Puts the rules in order, low numbers go first. Must be greater then

zero

--search SEARCH Query to match discovered hosts for the particular rule

-h, --help Print help

2.20. HAMMER DOCKER

Manipulate docker content

Usage:

hammer docker [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

manifest Manage docker manifests

tag Manage docker tags

Options:

-h, --help Print help

2.20.1. hammer docker manifest

Manage docker manifests

Usage:

hammer docker manifest [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a docker manifest list List docker_manifests

Options:

-h, --help Print help

2.20.1.1. hammer docker manifest info

Show a docker manifest

Usage:

hammer docker manifest info [OPTIONS]

Options:

--id ID A docker manifest identifier --name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.20.1.2. hammer docker manifest list

List docker_manifests

Usage:

hammer docker manifest list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by --content-view-filter-id CONTENT VIEW FILTER ID Filter identifier --content-view-id CONTENT_VIEW_ID Content view numeric identifier --content-view-version CONTENT VIEW VERSION VERSION Content view version number --content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier --environment ENVIRONMENT NAME Lifecycle environment name to search by (-environment is deprecated: Use --lifecycle-environment instead) --environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --lifecycleenvironment-id instead) --full-result FULL_RESULT Whether or not to show all results One of true/false, yes/no, 1/0. --ids IDS lds to filter content by Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --lifecycle-environment LIFECYCLE ENVIRONMENT NAME Lifecycle environment name to search by --lifecycle-environment-id LIFECYCLE ENVIRONMENT ID Sort field and order, eg. 'id DESC' --order ORDER --organization ORGANIZATION NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID --organization-label ORGANIZATION LABEL Organization label to search by --page PAGE Page number, starting at 1 --per-page PER_PAGE Number of results per page to return --product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID Product numeric identifier --repository REPOSITORY_NAME Repository name to search by

Repository ID

Search string

Print help

2.20.2. hammer docker tag

--search SEARCH

--repository-id REPOSITORY ID

Manage docker tags

-h, --help

Usage:

hammer docker tag [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a docker tag list List docker_tags

Options:

-h, --help Print help

2.20.2.1. hammer docker tag info

Show a docker tag

Usage:

hammer docker tag info [OPTIONS]

Options:

--id ID A docker tag identifier --name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.20.2.2. hammer docker tag list

List docker_tags

Usage:

hammer docker tag list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter-id CONTENT VIEW FILTER ID Filter identifier

--content-view-id CONTENT VIEW ID Content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID (--environ

(--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS Ids to filter content by

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

--search SEARCH Search string

-h, --help Print help

2.21. HAMMER DOMAIN

Manipulate domains

Usage:

hammer domain [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a domain delete Delete a domain

delete-parameter Delete parameter for a domain

info Show a domain list List of domains

set-parameter Create or update parameter for a domain

update Update a domain

Options:

-h, --help Print help

2.21.1. hammer domain create

Create a domain

Usage:

hammer domain create [OPTIONS]

Options:

--description DESC Full name describing the domain

--dns DNS_NAME Name of DNS proxy to use within this domain
--dns-id DNS_ID ID of DNS proxy to use within this domain

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME The full DNS domain name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION NAMES Comma separated list of values. Values containing

comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.21.2. hammer domain delete

Delete a domain

Usage:

hammer domain delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Domain name

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.21.3. hammer domain delete-parameter

Delete parameter for a domain

Usage:

hammer domain delete-parameter [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--name NAME Parameter name

-h, --help Print help

2.21.4. hammer domain info

Show a domain

Usage:

hammer domain info [OPTIONS]

Options:

--id ID Numerical ID or domain name

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Domain name

--organization ORGANIZATION_NAME Organization name

 --show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values One of true/false, yes/no, 1/0.

-h, --help Print help

2.21.5. hammer domain list

List of domains

Usage:

hammer domain list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results
--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

-h, --help Print help

Search / Order fields:

fullname string
location string
location_id integer
name string
organization string
organization_id integer
params text

2.21.6. hammer domain set-parameter

Create or update parameter for a domain

Usage:

hammer domain set-parameter [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID Numerical ID or domain name --hidden-value HIDDEN VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--name NAME Parameter name

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.21.7. hammer domain update

Update a domain

Usage:

hammer domain update [OPTIONS]

Options:

--description DESC Full name describing the domain

--dns DNS_NAME Name of DNS proxy to use within this domain
--dns-id DNS_ID ID of DNS proxy to use within this domain

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Domain name

--new-name NEW_NAME The full DNS domain name
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.22. HAMMER ENVIRONMENT

Manipulate environments

Usage:

hammer environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an environment

delete Delete an environment info Show an environment list List all environments

sc-params List all smart class parameters

update Update an environment

Options:

-h, --help Print help

2.22.1. hammer environment create

Create an environment

Usage:

hammer environment create [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.22.2. hammer environment delete

Delete an environment

Usage:

hammer environment delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Puppet environment name

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.22.3. hammer environment info

Show an environment

Usage:

hammer environment info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Puppet environment name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.22.4. hammer environment list

List all environments

Usage:

hammer environment list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

content_view string
lifecycle_environment string
location string

location_id integer
name string
organization string
organization_id integer

2.22.5. hammer environment sc-params

List all smart class parameters

Usage:

hammer environment sc-params [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

 $\hbox{--puppet-environment-id PUPPET_ENVIRONMENT_ID}\\$

--search SEARCH Filter results

--show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge_default Values: true, false values: true, false

override Values: true, false

parameter string puppetclass string puppetclass_name string

2.22.6. hammer environment update

Update an environment

Usage:

hammer environment update [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Puppet environment name

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.23. HAMMER ERRATUM

Manipulate errata

Usage:

hammer erratum [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show an erratum

list List errata

Options:

-h, --help Print help

2.23.1. hammer erratum info

Show an erratum

Usage:

hammer erratum info [OPTIONS]

Options:

--id ID An erratum identifier
--name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY ID Repository ID

-h, --help Print help

2.23.2. hammer erratum list

List errata

Usage:

hammer erratum list [OPTIONS]

Options:

--available-for AVAILABLE_FOR

Return errata that can be added to the specified

object. The values

'content_view_version' and 'content_view_filter are supported.

--content-view CONTENT_VIEW_NAME

Content view name to search by Name to search by

--content-view-filter CONTENT_VIEW_FILTER_NAME --content-view-filter-id CONTENT_VIEW_FILTER_ID

Filter identifier

--content-view-id CONTENT VIEW ID

Content view numeric identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID

--cve CVE CVE identifier

Lifecycle environment name to search by

Content view version identifier

--environment ENVIRONMENT_NAME
--environment-id ENVIRONMENT_ID

--errata-restrict-applicable ERRATA_RESTRICT_APPLICABLE Return errata that are applicable to

one or more hosts (defaults to true if

Host_id is specified)

One of true/false, yes/no, 1/0.

--errata-restrict-installable ERRATA_RESTRICT_INSTALLABLE Return errata that are upgradable

on one or more hosts

One of true/false, yes/no, 1/0.

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST NAME Host name

--host-id HOST ID

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID
--repository REPOSITORY NAME

Number of results per page to return
Product name to search by
Product numeric identifier
Repository name to search by

--repository-id REPOSITORY ID Repository ID

--search SEARCH Search string

-h, --help Print help

2.24. HAMMER EXPORT-TEMPLATES

Export templates to a git repo or a directory on the server

Usage:

hammer export-templates [OPTIONS]

Options:

--branch BRANCH Branch in Git repo.

--dirname DIRNAME The directory within Git repo containing the templates

--filter FILTER Export templates with names matching this regex (case-insensitive;

snippets

Are not filtered).

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--metadata-export-mode METADATA_EXPORT_MODE Specify how to handle metadata

Possible value(s): 'refresh', 'keep', 'remove'

--negate NEGATE Negate the prefix (for purging).

One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--repo REPO Override the default repo from settings.

--verbose BE_VERBOSE Be verbose

One of true/false, yes/no, 1/0.

-h, --help Print help

2.25. HAMMER FACT

Search facts

Usage:

hammer fact [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

list List all fact values

Options:

-h, --help Print help

2.25.1. hammer fact list

List all fact values

Usage:

hammer fact list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

fact string string fact_short_name facts string host string host.hostgroup string host id integer location string location_id integer name string organization string organization_id integer

reported_at datetime short_name string type string value string

string

2.26. HAMMER FILE

Manipulate files

origin

Usage:

hammer file [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a file list List files

Options:

-h, --help Print help

2.26.1. hammer file info

Show a file

Usage:

hammer file info [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT VIEW ID Content view numeric identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number

--id ID A file identifier

File name to search by --name NAME

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

Product name to search by --product PRODUCT_NAME --product-id PRODUCT ID Product numeric identifier

--repository REPOSITORY NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.26.2. hammer file list

List files

Usage:

hammer file list [OPTIONS]

Options:

--content-view CONTENT VIEW NAME Content view name to search by

--content-view-filter CONTENT VIEW FILTER NAME Name to search by

--content-view-filter-id CONTENT VIEW FILTER ID Filter identifier

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number

--content-view-version-id CONTENT VIEW VERSION ID Content view version identifier

--environment ENVIRONMENT NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT ID

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

lds to filter content by --ids IDS

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Sort field and order, eg. 'id DESC' --order ORDER

--organization ORGANIZATION_NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID
--search SEARCH Search string

-h, --help Print help

2.27. HAMMER FILTER

Manage permission filters

Usage:

hammer filter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

available-permissions List all permissions

available-resources List available resource types

create Create a filter
delete Delete a filter
info Show a filter
list List all filters
update Update a filter

Options:

-h, --help Print help

2.27.1. hammer filter available-permissions

List all permissions

Usage:

hammer filter available-permissions [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--resource-type RESOURCE_TYPE

--search SEARCH Filter results

-h, --help Print help

Search / Order fields: name string resource_type string

2.27.2. hammer filter available-resources

List available resource types

Usage:

hammer filter available-resources [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.27.3. hammer filter create

Create a filter

Usage:

hammer filter create [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION NAME Organization name

--organization-ids ORGANIZATION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--override OVERRIDE One of true/false, yes/no, 1/0.

--permission-ids PERMISSION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--permissions PERMISSION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--role ROLE_NAME User role name

--role-id ROLE_ID --search SEARCH

-h, --help Print help

Filters inherit organizations and locations from its role by default. This behavior can be changed by setting --override=true.

Therefore options --organization[s|-ids] and --location[s|-ids] are applicable only when the override flag is set.

Overriding organizations and locations:

2.27.4. hammer filter delete

Delete a filter

Usage:

hammer filter delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.27.5. hammer filter info

Show a filter

Usage:

hammer filter info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.27.6. hammer filter list

List all filters

Usage:

hammer filter list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

limited Values: true, false

location string location_id integer organization string organization_id integer

override Values: true, false

permission string resource string role string role_id integer search text

unlimited Values: true, false

2.27.7. hammer filter update

Update a filter

Usage:

hammer filter update [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--override OVERRIDE One of true/false, yes/no, 1/0.

--permission-ids PERMISSION_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--permissions PERMISSION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--role ROLE_NAME User role name

--role-id ROLE_ID --search SEARCH

-h, --help Print help

Filters inherit organizations and locations from its role by default. This behavior can be changed by setting --override=true.

Therefore options --organization[s|-ids] and --location[s|-ids] are applicable only when the override flag is set.

Overriding organizations and locations:

2.28. HAMMER FOREIGN-INPUT-SET

Manage foreign input sets

Usage:

hammer foreign-input-set [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a foreign input set
delete Delete a foreign input set
info Show foreign input set details

list List foreign input sets

update Update a foreign input set

Options:

-h, --help Print help

2.28.1. hammer foreign-input-set create

Create a foreign input set

Usage:

hammer foreign-input-set create [OPTIONS]

Options:

--description DESCRIPTION Input set description

--exclude EXCLUDE A comma separated list of input names to be included from the

foreign

Template.

--include INCLUDE A comma separated list of input names to be included from the

foreign

Template.

--include-all INCLUDE_ALL Include all inputs from the foreign template

One of true/false, yes/no, 1/0.

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization-title ORGANIZATION_TITLE Organization title

--target-template-id TARGET_TEMPLATE_ID Target template ID

--template-id TEMPLATE_ID

-h, --help Print help

2.28.2. hammer foreign-input-set delete

Delete a foreign input set

Usage:

hammer foreign-input-set delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--template-id TEMPLATE_ID

-h, --help Print help

2.28.3. hammer foreign-input-set info

Show foreign input set details

Usage:

hammer foreign-input-set info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --template-id TEMPLATE_ID
- -h, --help Print help

2.28.4. hammer foreign-input-set list

List foreign input sets

Usage:

hammer foreign-input-set list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--template-id TEMPLATE ID

-h, --help Print help

2.28.5. hammer foreign-input-set update

Update a foreign input set

Usage:

hammer foreign-input-set update [OPTIONS]

Options:

--description DESCRIPTION Input set description

--exclude EXCLUDE A comma separated list of input names to be included from the

foreign

Template.

--id ID

--include INCLUDE A comma separated list of input names to be included from the

foreign

Template.

--include-all INCLUDE_ALL Include all inputs from the foreign template

One of true/false, yes/no, 1/0.

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--new-name NEW_NAME

- --organization-title ORGANIZATION_TITLE Organization title
- --target-template-id TARGET_TEMPLATE_ID Target template ID
- --template-id TEMPLATE_ID
- -h, --help Print help

2.29. HAMMER FULL-HELP

Print help for all hammer commands

Usage:

hammer full-help [OPTIONS]

Options:

--md Format output in markdown

-h, --help Print help

2.30. HAMMER GLOBAL-PARAMETER

Manipulate global parameters

Usage:

hammer global-parameter [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Delete a global parameter list List all global parameters set Set a global parameter

Options:

-h, --help Print help

2.30.1. hammer global-parameter delete

Delete a global parameter

Usage:

hammer global-parameter delete [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Common parameter name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.30.2. hammer global-parameter list

List all global parameters

Usage:

hammer global-parameter list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

Paginate results --page PAGE

--page PER_PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

Print help -h, --help

Search / Order fields:

domain_name string host_group_name string host_name string key_type string location_name string name string organization_name string os_name string parameter_type string subnet_name text type string value text

2.30.3. hammer global-parameter set

Set a global parameter

Usage:

hammer global-parameter set [OPTIONS]

Options:

--hidden-value HIDDEN_VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--name NAME Parameter name

--parameter-type PARAMETER TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.31. HAMMER GPG

Manipulate GPG Key actions on the server

Usage:

hammer gpg [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a gpg key
delete Destroy a gpg key
info Show a gpg key
list List gpg keys

update Update a repository

Options:

-h, --help Print help

2.31.1. hammer gpg create

Create a gpg key

Usage:

hammer gpg create [OPTIONS]

Options:

--key GPG_KEY_FILE GPG Key file
--name NAME Identifier of the gpg key

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.31.2. hammer gpg delete

Destroy a gpg key

Usage:

hammer gpg delete [OPTIONS]

Options:

--id ID Gpg key numeric identifier --name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.31.3. hammer gpg info

Show a gpg key

Usage:

hammer gpg info [OPTIONS]

Options:

--id ID Gpg key numeric identifier --name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.31.4. hammer gpg list

List gpg keys

Usage:

hammer gpg list [OPTIONS]

Options:

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME Name of the GPG key

--order ORDER Sort field and order, eg. 'id DESC'

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.31.5. hammer gpg update

Update a repository

Usage:

hammer gpg update [OPTIONS]

Options:

--id ID Gpg key numeric identifier
--key GPG_KEY_FILE GPG Key file
--name NAME Name to search by

--new-name NEW_NAME Identifier of the gpg key

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.32. HAMMER HOST

Manipulate hosts

Usage:

hammer host [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

ansible-roles Manage Ansible roles on a host boot Boot host from specified device

config-reports List all reports create Create a host delete Delete a host

delete-parameter Delete parameter for a host

disassociate Disassociate a host enc-dump Dump host's ENC YAML errata Manage errata on your hosts

facts List all fact values info Show a host

interface View and manage host's network interfaces

list List all hosts

package Manage packages on your hosts

package-group Manage package-groups on your hosts

puppet-classes List all Puppet classes

puppetrun Force a Puppet agent run on the host

reboot Reboot a host

rebuild-config Rebuild orchestration related configurations for host

reports List all reports reset Reset a host

sc-params List all smart class parameters

set-parameter Create or append a parameter for a host

smart-variables List all smart variables

start Power a host on

status Get configuration status of host

stop Power a host off

subscription Manage subscription information on your hosts

update Update a host

Options:

-h, --help Print help

2.32.1. hammer host ansible-roles

Manage Ansible roles on a host

Usage:

hammer host ansible-roles [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

assign Assigns Ansible roles to a host list List all Ansible roles for a host play Plays Ansible roles on a host

Options:

-h, --help Print help

2.32.1.1. hammer host ansible-roles assign

Assigns Ansible roles to a host

Usage:

hammer host ansible-roles assign [OPTIONS]

Options:

--ansible-role-ids ANSIBLE ROLE IDS Ansible roles to assign to a host

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.1.2. hammer host ansible-roles list

List all Ansible roles for a host

Usage:

hammer host ansible-roles list [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.1.3. hammer host ansible-roles play

Plays Ansible roles on a host

Usage:

hammer host ansible-roles play [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Host name

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.2. hammer host boot

Boot host from specified device

Usage:

hammer host boot [OPTIONS]

Options:

--device DEVICE Boot device, valid devices are disk, cdrom, pxe, bios

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.3. hammer host config-reports

List all reports

Usage:

hammer host config-reports [OPTIONS]

Options:

--id ID Host id

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-id OrtoAntizATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

applied integer environment string

eventful Values: true, false

failed integer failed_restarts integer host string host id integer hostgroup string hostgroup_fullname string hostgroup title string last report datetime location strina log text organization string origin string integer pending datetime reported resource text restarted integer integer skipped

2.32.4. hammer host create

Create a host

Usage:

hammer host create [OPTIONS]

Options:

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-password ASK_ROOT_PW One of true/false, yes/no, 1/0.

--autoheal AUTOHEAL Sets whether the Host will autoheal subscriptions

upon checkin

One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

--comment COMMENT Additional information about this host

--compute-attributes COMPUTE ATTRS Compute resource attributes

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

--compute-profile COMPUTE PROFILE NAME Compute profile name

--compute-profile-id COMPUTE_PROFILE_ID

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE_RESOURCE_ID

--config-group-ids CONFIG_GROUP_IDS IDs of associated config groups

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--config-groups CONFIG GROUP NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--content-source CONTENT SOURCE NAME Content Source name

--content-source-id CONTENT SOURCE ID

--content-view CONTENT VIEW NAME Name to search by

--content-view-id CONTENT VIEW ID Content view numeric identifier

--domain DOMAIN NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--enabled ENABLED Include this host within Satellite reporting

One of true/false, yes/no, 1/0.

--environment ENVIRONMENT NAME Environment name (--environment is

deprecated: Use --puppet-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --

puppet-environment-id instead)

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--hypervisor-guest-uuids HYPERVISOR GUEST UUIDS List of hypervisor guest uuids

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--image IMAGE NAME Name to search by

--image-id IMAGE ID

--installed-products-attributes INSTALLED PRODUCTS ATTRIBUTES List of products installed on the host

Comma separated list of values defined by a schema. See

Option details section below.

JSON is acceptable and preferred way for complex

parameters

--interface INTERFACE Interface parameters

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

Can be specified multiple times.

Not required if using a subnet with DHCP Capsule --ip IP

--kickstart-repository REPOSITORY NAME Kickstart repository name

--kickstart-repository-id KICKSTART_REPOSITORY_ID Repository Id associated with the

kickstart repo used for provisioning

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by --lifecycle-environment-id LIFECYCLE ENVIRONMENT ID ID of the environment

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--mac MAC Required for managed host that is bare metal, not

required if it's a

Virtual machine

--managed MANAGED True/False flag whether a host is managed or

unmanaged. Note: this value

Also determines whether several parameters are required or

not

One of true/false, yes/no, 1/0.

Medium name

Model name

--medium MEDIUM NAME

--medium-id MEDIUM ID

--model MODEL NAME

--model-id MODEL ID

--name NAME

--openscap-proxy-id OPENSCAP PROXY ID ID of OpenSCAP Capsule --operatingsystem OPERATINGSYSTEM TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM ID

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title --overwrite OVERWRITE One of true/false, yes/no, 1/0.

Default: "true"

--owner OWNER LOGIN --owner-id OWNER ID --owner-type OWNER TYPE

Login of the owner ID of the owner Host's owner type

Possible value(s): 'User', 'Usergroup'

--parameters PARAMS

Replaces with new host parameters

Partition table name

Comma-separated list of key=value. JSON is acceptable and preferred way for complex

parameters

--partition-table PARTITION TABLE NAME

--partition-table-id PARTITION_TABLE_ID

--product PRODUCT_NAME --product-id PRODUCT ID

Name to search by Product numeric identifier

--progress-report-id PROGRESS_REPORT_ID status, GET

UUID to track orchestration tasks

/api/orchestration/:UUID/tasks

--provision-method PROVISION METHOD

The method used to provision the host.

Possible value(s): 'build', 'image', 'bootdisk'

--puppet-ca-proxy PUPPET CA PROXY NAME

--puppet-ca-proxy-id PUPPET CA PROXY ID

Puppet CA Capsule ID

--puppet-class-ids PUPPET CLASS IDS

Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--puppet-classes PUPPET CLASS NAMES

Comma separated list of values.

Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--puppet-environment PUPPET ENVIRONMENT NAME

Puppet environment name

--puppet-environment-id PUPPET ENVIRONMENT ID

--puppet-proxy PUPPET_PROXY_NAME

--puppet-proxy-id PUPPET PROXY ID

Puppet Capsule ID

Sets the system add-ons

--purpose-addons PURPOSE ADDONS

Sets the system purpose usage

Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--purpose-role PURPOSE ROLE --purpose-usage PURPOSE_USAGE

Sets the system purpose usage DHCP filename option (Grub2/PXELinux by

--pxe-loader PXE_LOADER

default)

'Grub UEFI', 'Grub2 BIOS', 'Grub2 ELF', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE Chain UEFI' Name to search by --realm REALM NAME --realm-id REALM ID Numerical ID or realm name --release-version RELEASE VERSION Release version for this Host to use (7Server, 7.1, etc) --root-password ROOT_PW Required if host is managed and value is not inherited from host group or default password in settings --service-level SERVICE LEVEL Service level to be used for autoheal --subnet SUBNET NAME Subnet name --subnet-id SUBNET ID --volume VOLUME Volume parameters Comma-separated list of key=value. JSON is acceptable and preferred way for complex parameters Can be specified multiple times. Print help -h, --help Option details: Following parameters accept format defined by its schema (bold are required): --installed-products-attributes "product id=string\,product name=string\,arch=string\,version=string, Available keys for --interface: mac ip type Possible values: interface, bmc, bond, bridge name subnet id domain id identifier true/false managed true/false, each managed hosts needs to have one primary interface. primary provision true/false virtual true/false For virtual=true: VLAN tag, this attribute has precedence over the subnet VLAN ID. Only for virtual tag interfaces. attached_to Identifier of the interface to which this interface belongs, e.g. eth1. For type=bond: mode Possible values: balance-rr, active-backup, balance-xor, broadcast, 802.3ad, balance-tlb, balance-alb attached devices Identifiers of slave interfaces, e.g. [eth1,eth2] bond options For type=bmc: provider always IPMI username password Provider specific options: ec2: --volume:

```
--interface:
 --compute-attributes:
  flavor id
  image_id
  availability_zone
  security_group_ids
  managed_ip
gce:
 --volume:
 --interface:
 --compute-attributes:
  machine_type
  image_id
  network
  external ip
libvirt:
 --volume:
                  One of available storage pools
  pool_name
                String value, eg. 10G
  capacity
                Possible values: raw, qcow2
  format_type
 --interface:
  compute_type
                   Possible values: bridge, network
  Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000
  compute_model
  start
              Boolean (expressed as 0 or 1), whether to start the machine or not
 --compute-attributes:
               Number of CPUs
  cpus
                 String, amount of memory, value in bytes
  memory
  start
              Boolean (expressed as 0 or 1), whether to start the machine or not
openstack:
 --volume:
 --interface:
 --compute-attributes:
  flavor_ref
  image_ref
  tenant_id
  security_groups
  network
```

ovirt: --volume: Volume size in GB, integer value size_gb storage_domain ID of storage domain Boolean, only one volume can be bootable bootable --interface: Compute name, e.g. eth0 compute name Select one of available networks for a cluster, must be an ID compute_network compute interface Interface type Boolean (expressed as 0 or 1), whether to start the machine or not start --compute-attributes: ID of cluster to use cluster Hardware profile to use template Integer value, number of cores cores Amount of memory, integer value in bytes memory rackspace: --volume: --interface: --compute-attributes: flavor_id image_id vmware: --volume: name Storage Pod ID from VMware storage pod

Datastore ID from VMware datastore

size gb Integer number, volume size in GB

true/false thin true/false eager zero

mode persistent/independent persistent/independent nonpersistent

--interface:

Type of the network adapter, for example one of: compute_type

> VirtualVmxnet3. VirtualE1000

See documentation center for your version of vSphere to find more details about available adapter types:

https://www.vmware.com/support/pubs/

compute network Network ID from VMware

start Must be a 1 or 0, whether to start the machine or not

--compute-attributes:

CPU count cpus

Number of cores per socket (applicable to hardware versions < 10 only) corespersocket

Integer number, amount of memory in MB memory_mb

firmware automatic/bios/efi cluster Cluster ID from VMware

resource_pool Resource Pool ID from VMware path Path to folder

guest_id Guest OS ID form VMware

scsi_controller_type ID of the controller from VMware hardware_version Hardware version ID from VMware

add cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine

cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on

annotation Annotation Notes

2.32.5. hammer host delete

Delete a host

Usage:

hammer host delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.6. hammer host delete-parameter

Delete parameter for a host

Usage:

hammer host delete-parameter [OPTIONS]

Options:

--host HOST NAME Host name

--host-id HOST ID

--name NAME Parameter name

-h, --help Print help

2.32.7. hammer host disassociate

Disassociate a host

Usage:

hammer host disassociate [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.8. hammer host enc-dump

Dump host's ENC YAML

Usage:

hammer host enc-dump [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.9. hammer host errata

Manage errata on your hosts

Usage:

hammer host errata [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

apply Schedule errata for installation
info Retrieve a single errata for a host
list List errata available for the content host
recalculate Force regenerate applicability.

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.32.9.1. hammer host errata apply

Schedule errata for installation

Usage:

hammer host errata apply [OPTIONS]

Options:

--async Do not wait for the task

--errata-ids ERRATA_IDS List of Errata ids to install

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--host HOST_NAME Host name

--host-id HOST ID

--ids IDS List of errata ids to perform an action on, (ex: RHSA-2019:1168)

Comma separated list of values. Values containing comma should be quoted or

escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--search SEARCH Search string for erratum to perform an action on

-h, --help Print help

2.32.9.2. hammer host errata info

Retrieve a single errata for a host

Usage:

hammer host errata info [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--id ID Errata id of the erratum (RHSA-2012:108)

--name NAME Name to search by

-h, --help Print help

2.32.9.3. hammer host errata list

List errata available for the content host

Usage:

hammer host errata list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-id CONTENT VIEW ID Content view numeric identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT ID

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST_ID

--order ORDER Sort field and order, eg. 'id DESC'

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.32.9.4. hammer host errata recalculate

Force regenerate applicability.

Usage:

hammer host errata recalculate [OPTIONS]

Options:

--async Do not wait for the task --host HOST_NAME Host name

--host-id HOST ID

-h, --help Print help

2.32.10. hammer host facts

List all fact values

Usage:

hammer host facts [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

string fact_short_name string facts string host string host.hostgroup string host id integer location string location id integer name string organization string organization_id integer origin string

reported_at datetime short_name string type string value string

2.32.11. hammer host info

Show a host

Usage:

hammer host info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION TITLE Organization title

--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values

One of true/false, yes/no, 1/0.

-h, --help Print help

2.32.12. hammer host interface

View and manage host's network interfaces

Usage:

hammer host interface [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an interface on a host delete Delete a host's interface info Show an interface for host list List all interfaces for host update Update a host's interface

Options:

-h, --help Print help

2.32.12.1. hammer host interface create

Create an interface on a host

Usage:

hammer host interface create [OPTIONS]

Options:

--attached-devices ATTACHED DEVICES Identifiers of attached interfaces, e.g. \['eth1',

'eth2']`. For bond interfaces those are the slaves. Only for bond

And bridges interfaces.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--attached-to ATTACHED_TO Identifier of the interface to which this interface belongs, e.g. eth1.

Only for virtual interfaces.

--bond-options BOND_OPTIONS Space separated options, e.g. miimon=100. Only for bond

interfaces.

--compute-attributes COMPUTE_ATTRS
Compute resource specific attributes

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--domain DOMAIN_NAME Domain name

--host HOST_NAME Host name

--host-id HOST_ID

--identifier IDENTIFIER Device identifier, e.g. eth0 or eth1.1

--ip IP IPv4 address of interface --ip6 IP6 IPv6 address of interface --location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--mac MAC MAC address of interface. Required for managed interfaces on bare

metal.

--managed MANAGED Should this interface be managed via DHCP and DNS capsule

and should it be

Configured during provisioning? One of true/false, yes/no, 1/0.

--mode MODE Bond mode of the interface, e.g. balance-rr. Only for bond

interfaces.

Possible value(s): 'balance-rr', 'active-backup', 'balance-xor', 'broadcast',

'802.3ad', 'balance-tlb', 'balance-alb'

--mtu MTU MTU, this attribute has precedence over the subnet MTU.

--name NAME Interface's DNS name

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

--password PASSWORD Only for BMC interfaces.

--primary Should this interface be used for constructing the FQDN of the host?

Each managed hosts needs to have one primary interface

--provider PROVIDER Interface provider, e.g. IPMI. Only for BMC interfaces.

Possible value(s): 'IPMI', 'SSH'

--provision Should this interface be used for TFTP of PXELinux (or SSH for image-

based hosts)? Each managed hosts needs to have one provision interface

--subnet SUBNET NAME Subnet name

--subnet-id SUBNET ID

--subnet6-id SUBNET6 ID Satellite subnet ID of IPv6 interface

--tag TAG VLAN tag, this attribute has precedence over the subnet VLAN ID. Only

for

Virtual interfaces.

--type TYPE Interface type, e.g. bmc. Default is interface

Possible value(s): 'interface', 'bmc', 'bond', 'bridge'

--username USERNAME Only for BMC interfaces.

--virtual VIRTUAL Alias or VLAN device

One of true/false, yes/no, 1/0.

-h, --help Print help

2.32.12.2. hammer host interface delete

Delete a host's interface

Usage:

hammer host interface delete [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST ID

--id ID ID of interface

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.32.12.3. hammer host interface info

Show an interface for host

Usage:

hammer host interface info [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--id ID ID or name of interface

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.12.4. hammer host interface list

List all interfaces for host

Usage:

hammer host interface list [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--host HOST_NAME Host name

--host-id HOST_ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

-h, --help Print help

2.32.12.5. hammer host interface update

Update a host's interface

Usage:

hammer host interface update [OPTIONS]

Options:

--attached-devices ATTACHED_DEVICES Identifiers of attached interfaces, e.g. `['eth1',

'eth2']`. For bond interfaces those are the slaves. Only for bond

And bridges interfaces.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--attached-to ATTACHED_TO Identifier of the interface to which this interface belongs, e.g.

Only for virtual interfaces.

--bond-options BOND_OPTIONS Space separated options, e.g. miimon=100. Only for bond interfaces.

--compute-attributes COMPUTE_ATTRS
Compute resource specific attributes

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--domain DOMAIN NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--host HOST_NAME Host name

--host-id HOST_ID

--id ID ID of interface

--identifier IDENTIFIER Device identifier, e.g. eth0 or eth1.1

--ip IP IPv4 address of interface --ip6 IP6 IPv6 address of interface --location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--mac MAC MAC address of interface. Required for managed interfaces on bare

metal.

--managed MANAGED Should this interface be managed via DHCP and DNS capsule

and should it be

Configured during provisioning? One of true/false, yes/no, 1/0.

--mode MODE Bond mode of the interface, e.g. balance-rr. Only for bond

interfaces.

Possible value(s): 'balance-rr', 'active-backup', 'balance-xor', 'broadcast',

'802.3ad', 'balance-tlb', 'balance-alb'

--mtu MTU MTU, this attribute has precedence over the subnet MTU.

--name NAME Interface's DNS name

--organization-title ORGANIZATION_TITLE Organization title --password PASSWORD Only for BMC interfaces.

--primary Should this interface be used for constructing the FQDN of the host?

Each managed hosts needs to have one primary interface

--provider PROVIDER Interface provider, e.g. IPMI. Only for BMC interfaces.

Possible value(s): 'IPMI', 'SSH'

--provision Should this interface be used for TFTP of PXELinux (or SSH for image-

based hosts)? Each managed hosts needs to have one provision interface

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET ID

--subnet6-id SUBNET6 ID Satellite subnet ID of IPv6 interface

--tag TAG VLAN tag, this attribute has precedence over the subnet VLAN ID. Only

for

Virtual interfaces.

--type TYPE Interface type, e.g. bmc. Default is interface

Possible value(s): 'interface', 'bmc', 'bond', 'bridge'

--username USERNAME Only for BMC interfaces.

--virtual VIRTUAL Alias or VLAN device

One of true/false, yes/no, 1/0.

-h, --help Print help

2.32.13. hammer host list

List all hosts

Usage:

hammer host list [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title --location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--puppet-environment PUPPET ENVIRONMENT NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID
--search SEARCH Filter results

--thin THIN Only list ID and name of hosts

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

activation_key string activation_key_id string addon text

addons_status Values: mismatched, matched, not_specified

ansible_role string applicable_errata string

```
applicable_rpms
                       string
architecture
                    string
autoheal
                   boolean
                 Values: true, false
build
class
                  string
                    text
comment
compute resource
                        string
compute_resource_id
                         integer
config_group
                     string
content source
                      string
content_view
                     string
content_view_id
                      integer
domain
                   string
domain id
                    integer
environment
                     string
                     Values: security needed, errata needed, updated, unknown
errata status
                       Values: ok, error
execution_status
facts
                 string
global status
                     Values: ok, warning, error
has_ip
                   string
                    string
has mac
                    string
hostgroup
hostgroup_fullname
                        string
hostgroup id
                     integer
hostgroup_name
                        string
hostgroup_title
                     string
hypervisor
                    Values: true, false
hypervisor_host
                      string
image
                   string
installable_errata
                      string
installed_at
                   datetime
                string
ip
job invocation.id
                      string
job invocation.result
                       Values: cancelled, failed, pending, success
last_checkin
                    datetime
last_report
                   datetime
lifecycle environment
                        string
lifecycle_environment_id integer
location
                  string
location_id
                   integer
mac
                  string
                     Values: true, false
managed
model
                   string
name
                   string
organization
                    string
organization id
                     integer
origin
                 string
os
                 string
os_description
                     string
os id
                  integer
os_major
                    string
os minor
                    string
os_title
                  string
owner
                   string
owner_id
                    integer
                     string
owner_type
```

```
string
params
params_name
                       string
parent_hostgroup
                       string
puppet_ca
                    string
puppet_proxy_id
                       integer
puppetmaster
                      string
purpose_status
                      Values: mismatched, matched, not specified
realm
                  string
realm id
                   integer
registered at
                    datetime
registered_through
                       string
release_version
                      string
role
                text
                   Values: mismatched, matched, not_specified
role status
service_level
                   Values: mismatched, matched, not specified
sla status
smart_proxy
                     string
status.applied
                    integer
status.enabled
                     Values: true, false
status.failed
                   integer
status.failed restarts integer
                     Values: true, false
status.interesting
status.pending
                     integer
status.restarted
                     integer
status.skipped
                     integer
subnet
                  string
subnet.name
                     text
subnet6
                   string
subnet6.name
                      text
subscription id
                     string
subscription_name
                       string
subscription_status
                       Values: valid, partial, invalid, unknown, unsubscribed_hypervisor
subscription uuid
                    Values: reboot needed, process restart needed, updated
trace status
upgradable_rpms
                       string
usage
                  text
                     Values: mismatched, matched, not specified
usage status
                     string
user.firstname
                     string
user.lastname
user.login
                   string
user.mail
                   string
usergroup
                    string
                       string
usergroup.name
uuid
                 string
```

2.32.14. hammer host package

Manage packages on your hosts

Usage:

hammer host package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

install Install packages remotely

List packages installed on the host list Uninstall packages remotely remove Update packages remotely upgrade upgrade-all Update packages remotely

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.32.14.1. hammer host package install

Install packages remotely

Usage:

hammer host package install [OPTIONS]

Options:

Do not wait for the task --async --host HOST_NAME Host name

--host-id HOST ID

--packages PACKAGES List of package names

Comma separated list of values. Values containing comma should be quoted or

escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.32.14.2. hammer host package list

List packages installed on the host

Usage:

hammer host package list [OPTIONS]

Options:

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST NAME Host name

--host-id HOST ID

--order ORDER Sort field and order, eg. 'id DESC'

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.32.14.3. hammer host package remove

Uninstall packages remotely

Usage:

hammer host package remove [OPTIONS]

Options:

--async Do not wait for the task --host HOST_NAME Host name

--host-id HOST_ID

--packages PACKAGES List of package names

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.32.14.4. hammer host package upgrade

Update packages remotely

Usage:

hammer host package upgrade [OPTIONS]

Options:

--async Do not wait for the task --host HOST_NAME Host name

--host-id HOST_ID

--packages PACKAGES List of packages names

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.32.14.5. hammer host package upgrade-all

Update packages remotely

Usage:

hammer host package upgrade-all [OPTIONS]

Options:

--async Do not wait for the task --host HOST_NAME Host name

--host-id HOST_ID

-h, --help Print help

2.32.15. hammer host package-group

Manage package-groups on your hosts

Usage:

hammer host package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

install Install packages remotely remove Uninstall packages remotely

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.32.15.1. hammer host package-group install

Install packages remotely

Usage:

hammer host package-group install [OPTIONS]

Options:

--async Do not wait for the task

--groups GROUPS List of package group names

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--host HOST_NAME Host name

--host-id HOST_ID

-h, --help Print help

2.32.15.2. hammer host package-group remove

Uninstall packages remotely

Usage:

hammer host package-group remove [OPTIONS]

Options:

--async Do not wait for the task

--groups GROUPS List of package group names

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--host HOST_NAME Host name

--host-id HOST ID

-h, --help Print help

2.32.16. hammer host puppet-classes

List all Puppet classes

Usage:

hammer host puppet-classes [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST ID

--location-id LOCATION_ID Scope by locations

--order ORDER Sort field and order, eg. 'id DESC'

--organization-id ORGANIZATION_ID Scope by organizations

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

config_group string
environment string
host string
hostgroup string
key string
location string
name string
organization string

2.32.17. hammer host puppetrun

Force a Puppet agent run on the host

Usage:

hammer host puppetrun [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.18. hammer host reboot

Reboot a host

Usage:

hammer host reboot [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.19. hammer host rebuild-config

Rebuild orchestration related configurations for host

Usage:

hammer host rebuild-config [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Host name

--only ONLY Limit rebuild steps, valid steps are DHCP, DNS, TFTP

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.20. hammer host reports

List all reports

Usage:

hammer host reports [OPTIONS]

Options:

--id ID Host id

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Host name

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

applied integer environment string

eventful Values: true, false

failed integer
failed_restarts integer
host string
host_id integer
hostgroup string
hostgroup_fullname string
hostgroup_title string

datetime last_report location string log text organization string origin string pending integer reported datetime resource text restarted integer skipped integer

2.32.21, hammer host reset

Reset a host

Usage:

hammer host reset [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Host name
- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.32.22. hammer host sc-params

List all smart class parameters

Usage:

hammer host sc-params [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

 $\hbox{\it --organization-title ORGANIZATION_TITLE\ Organization\ title}$

--page PAGE Paginate results
--per-page PER PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge_default Values: true, false values: true, false

override Values: true, false

parameter string puppetclass string puppetclass_name string

2.32.23. hammer host set-parameter

Create or append a parameter for a host

Usage:

hammer host set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--host HOST NAME Host name

--host-id HOST ID

--name NAME Parameter name

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.32.24. hammer host smart-variables

List all smart variables

Usage:

hammer host smart-variables [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

key string

merge_default Values: true, false merge_overrides Values: true, false override Values: true, false

parameter string puppetclass string

2.32.25. hammer host start

Power a host on

Usage:

hammer host start [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.26. hammer host status

Get configuration status of host

Usage:

hammer host status [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.27. hammer host stop

Power a host off

Usage:

hammer host stop [OPTIONS]

Options:

--force Force turning off a host

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Host name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.32.28. hammer host subscription

Manage subscription information on your hosts

Usage:

hammer host subscription [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

attach Add a subscription to a host

auto-attach Trigger an auto-attach of subscriptions content-override Override product content defaults

product-content List associated products

register Register a host with subscription and information

remove

unregister Unregister the host as a subscription consumer

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.32.28.1. hammer host subscription attach

Add a subscription to a host

Usage:

hammer host subscription attach [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST ID

--quantity Quantity Quantity Quantity of this subscriptions to add. Defaults to 1

--subscription-id SUBSCRIPTION_ID ID of subscription

-h, --help Print help

2.32.28.2. hammer host subscription auto-attach

Trigger an auto-attach of subscriptions

Usage:

hammer host subscription auto-attach [OPTIONS]

Options:

--host HOST NAME Host name

--host-id HOST_ID

-h, --help Print help

2.32.28.3. hammer host subscription content-override

Override product content defaults

Usage:

hammer host subscription content-override [OPTIONS]

Options:

--content-label CONTENT_LABEL Label of the content

--host HOST_NAME Host name

--host-id HOST_ID

--override-name OVERRIDE_NAME Override parameter key or name.

To enable or disable a repo select 'enabled'.

Default value: enabled Default: "enabled"

--remove Remove a content override

--value VALUE Override value. Note for repo enablement you can use a boolean value

-h, --help Print help

2.32.28.4. hammer host subscription product-content

List associated products

Usage:

hammer host subscription product-content [OPTIONS]

Options:

--content-access-mode-all CONTENT_ACCESS_MODE_ALL Get all content available, not just that provided by subscriptions

One of true/false, yes/no, 1/0.

--content-access-mode-env CONTENT_ACCESS_MODE_ENV Limit content to just that available in the host's content view version

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST ID

-h, --help Print help

2.32.28.5. hammer host subscription register

Register a host with subscription and information

Usage:

hammer host subscription register [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by --content-view-id CONTENT_VIEW_ID Content view numeric identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS UUIDs of the virtual guests from the host's hypervisor

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE ENVIRONMENT ID ID of the environment

--name NAME Name of the host

--organization ORGANIZATION_NAME
--organization-id ORGANIZATION_ID
--organization-label ORGANIZATION_LABEL
--release-version RELEASE VERSION

Organization name to search by
Organization ID to search by
Release version of the content host

--service-level SERVICE_LEVEL A service level for auto-healing process, e.g. SELF-

SUPPORT

--uuid UUID UUID to use for registered host, random uuid is generated if

not provided

-h, --help Print help

2.32.28.6. hammer host subscription remove

Usage:

hammer host subscription remove [OPTIONS]

Options:

--host HOST NAME Host name

--host-id HOST ID

--quantity Quantity Remove the first instance of a subscription with matching id and quantity

--subscription-id SUBSCRIPTION_ID ID of subscription

-h, --help Print help

2.32.28.7. hammer host subscription unregister

Unregister the host as a subscription consumer

Usage:

hammer host subscription unregister [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST_ID

-h, --help Print help

2.32.29. hammer host update

Update a host

Usage:

hammer host update [OPTIONS]

Options:

--ansible-role-ids ANSIBLE ROLE IDS IDs of associated ansible roles

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--architecture ARCHITECTURE NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-password ASK_ROOT_PW One of true/false, yes/no, 1/0.

--autoheal AUTOHEAL Sets whether the Host will autoheal subscriptions

upon checkin

One of true/false, yes/no, 1/0.

--build BUILD One of true/false, yes/no, 1/0.

--comment COMMENT Additional information about this host

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

--compute-profile COMPUTE PROFILE NAME Compute profile name

--compute-profile-id COMPUTE_PROFILE_ID

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE RESOURCE ID

--config-group-ids CONFIG_GROUP_IDS IDs of associated config groups

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--config-groups CONFIG_GROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--content-source CONTENT_SOURCE_NAME Content Source name

--content-source-id CONTENT SOURCE ID

--content-view CONTENT VIEW NAME Name to search by

--content-view-id CONTENT VIEW ID Content view numeric identifier

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--enabled ENABLED Include this host within Satellite reporting

One of true/false, yes/no, 1/0.

--environment ENVIRONMENT_NAME Environment name (--environment is

deprecated: Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --

puppet-environment-id instead)

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--hypervisor-guest-uuids HYPERVISOR_GUEST_UUIDS List of hypervisor guest uuids

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--id ID

--image IMAGE NAME Name to search by

--image-id IMAGE ID

--installed-products-attributes INSTALLED_PRODUCTS_ATTRIBUTES List of products installed on

the host

Comma separated list of values defined by a schema. See

Option details section below.

JSON is acceptable and preferred way for complex

parameters

--interface INTERFACE Interface parameters

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

Can be specified multiple times.

Not required if using a subnet with DHCP Capsule --ip IP

--kickstart-repository REPOSITORY NAME Kickstart repository name

--kickstart-repository-id KICKSTART REPOSITORY ID Repository Id associated with the

kickstart repo used for provisioning

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by --lifecycle-environment-id LIFECYCLE ENVIRONMENT ID ID of the environment

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--mac MAC Required for managed host that is bare metal, not

required if it's a

Virtual machine

True/False flag whether a host is managed or --managed MANAGED

unmanaged. Note: this value

Also determines whether several parameters are required or

Operating system title

not

One of true/false, yes/no, 1/0.

Medium name

--medium MEDIUM NAME --medium-id MEDIUM ID

--model MODEL NAME Model name

--model-id MODEL ID

--name NAME Host name

--new-location NEW LOCATION NAME Location name

--new-location-id NEW_LOCATION_ID

--new-location-title NEW_LOCATION_TITLE Location title

--new-name NEW NAME

--new-organization NEW ORGANIZATION NAME Organization name --new-organization-id NEW ORGANIZATION ID Organization ID --new-organization-title NEW_ORGANIZATION_TITLE Organization title --openscap-proxy-id OPENSCAP_PROXY_ID ID of OpenSCAP Capsule

--operatingsystem OPERATINGSYSTEM TITLE

--operatingsystem-id OPERATINGSYSTEM ID

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title One of true/false, yes/no, 1/0.

--overwrite OVERWRITE

--owner OWNER LOGIN Login of the owner --owner-id OWNER_ID ID of the owner

--owner-type OWNER TYPE Host's owner type

Possible value(s): 'User', 'Usergroup'

--parameters PARAMS

Replaces with new host parameters

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

--partition-table PARTITION_TABLE_NAME

Partition table name

--partition-table-id PARTITION_TABLE_ID

--product PRODUCT_NAME
--product-id PRODUCT_ID

Name to search by Product numeric identifier

--progress-report-id PROGRESS_REPORT_ID

UUID to track orchestration tasks

status, GET

/api/orchestration/:UUID/tasks

--provision-method PROVISION METHOD

The method used to provision the host.

Possible value(s): 'build', 'image', 'bootdisk'

--puppet-ca-proxy PUPPET_CA_PROXY_NAME

--puppet-ca-proxy-id PUPPET_CA_PROXY_ID

Puppet CA Capsule ID

--puppet-class-ids PUPPET_CLASS_IDS

Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--puppet-classes PUPPET_CLASS_NAMES

Comma separated list of values.

Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--puppet-environment PUPPET_ENVIRONMENT_NAME

Puppet environment name

 $\hbox{--puppet-environment-id PUPPET_ENVIRONMENT_ID}\\$

--puppet-proxy PUPPET_PROXY_NAME

--puppet-proxy-id PUPPET_PROXY_ID

Puppet Capsule ID

--purpose-addons PURPOSE_ADDONS

Sets the system add-ons

Comma separated list of values. Values containing comma

slash.

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex

parameters

--purpose-role PURPOSE_ROLE
--purpose-usage PURPOSE USAGE

Sets the system purpose usage
Sets the system purpose usage

--pxe-loader PXE LOADER

DHCP filename option (Grub2/PXELinux by

default)

Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',

'Grub UEFI', 'Grub2 BIOS', 'Grub2 ELF', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded',

'iPXE Chain BIOS', 'iPXE Chain UEFI'

--realm REALM_NAME Name to search by

--realm-id REALM_ID Numerical ID or realm name

--release-version RELEASE_VERSION

Release version for this Host to use

(7Server, 7.1, etc)

--root-password ROOT_PW

Required if host is managed and value is not

inherited from host group or default password in settings

--service-level SERVICE LEVEL

Service level to be used for autoheal

--subnet SUBNET_NAME

Subnet name

--subnet-id SUBNET_ID

--volume VOLUME

Volume parameters

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex

parameters

Can be specified multiple times.

-h, --help Print help

Option details:

```
Following parameters accept format defined by its schema (bold are required):
 --installed-products-attributes "product_id=string\,product_name=string\,arch=string\,version=string,
Available keys for --interface:
 mac
 ip
 type
              Possible values: interface, bmc, bond, bridge
 name
 subnet_id
 domain_id
 identifier
 managed
               true/false
               true/false, each managed hosts needs to have one primary interface.
 primary
               true/false
 provision
             true/false
 virtual
 For virtual=true:
              VLAN tag, this attribute has precedence over the subnet VLAN ID. Only for virtual
  tag
interfaces.
                  Identifier of the interface to which this interface belongs, e.g. eth1.
  attached_to
 For type=bond:
  mode
                Possible values: balance-rr, active-backup, balance-xor, broadcast, 802.3ad,
balance-tlb, balance-alb
  bond_options
 For type=bmc:
  provider
                always IPMI
  username
  password
Provider specific options:
 ec2:
  --volume:
  --interface:
  --compute-attributes:
   flavor_id
   image_id
   availability zone
   security group ids
   managed_ip
 gce:
  --volume:
  --interface:
```

```
--compute-attributes:
  machine_type
  image id
  network
  external ip
libvirt:
 --volume:
  pool_name
                    One of available storage pools
                 String value, eg. 10G
  capacity
                   Possible values: raw, qcow2
  format_type
 --interface:
                    Possible values: bridge, network
  compute_type
  compute_bridge
                     Name of interface according to type
  compute_model
                      Possible values: virtio, rtl8139, ne2k_pci, pcnet, e1000
               Boolean (expressed as 0 or 1), whether to start the machine or not
  start
 --compute-attributes:
                Number of CPUs
  cpus
                  String, amount of memory, value in bytes
  memory
               Boolean (expressed as 0 or 1), whether to start the machine or not
  start
openstack:
 --volume:
 --interface:
 --compute-attributes:
  flavor_ref
  image ref
  tenant id
  security_groups
  network
ovirt:
 --volume:
  size_gb
                 Volume size in GB, integer value
  storage_domain
                     ID of storage domain
  bootable
                  Boolean, only one volume can be bootable
 --interface:
                      Compute name, e.g. eth0
  compute_name
  compute network
                      Select one of available networks for a cluster, must be an ID
  compute interface Interface type
  start
               Boolean (expressed as 0 or 1), whether to start the machine or not
 --compute-attributes:
  cluster
               ID of cluster to use
                Hardware profile to use
  template
```

Integer value, number of cores

Amount of memory, integer value in bytes

cores

rackspace:

memory

_

--volume:

--interface:

--compute-attributes:

flavor_id image_id

vmware:

--volume:

storage_pod Storage Pod ID from VMware datastore Datastore ID from VMware

size_gb Integer number, volume size in GB

thin true/false eager_zero true/false

mode persistent/independent_persistent/independent_nonpersistent

--interface:

compute_type Type of the network adapter, for example one of:

VirtualVmxnet3, VirtualE1000

See documentation center for your version of vSphere to find more details about available adapter types:

https://www.vmware.com/support/pubs/

start Must be a 1 or 0, whether to start the machine or not

--compute-attributes:

cpus CPU count

corespersocket Number of cores per socket (applicable to hardware versions < 10 only)

memory mb Integer number, amount of memory in MB

firmware automatic/bios/efi cluster Cluster ID from VMware

resource_pool Resource Pool ID from VMware

path Path to folder

guest id Guest OS ID form VMware

scsi_controller_type ID of the controller from VMware hardware_version Hardware version ID from VMware

add_cdrom Must be a 1 or 0, Add a CD-ROM drive to the virtual machine

cpuHotAddEnabled Must be a 1 or 0, lets you add memory resources while the machine is on memoryHotAddEnabled Must be a 1 or 0, lets you add CPU resources while the machine is on

annotation Annotation Notes

2.33. HAMMER HOST-COLLECTION

Manipulate host collections

Usage:

hammer host-collection [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand

[ARG] ... Subcommand arguments

Subcommands:

add-host Add host to the host collection

copy Copy a host collection create Create a host collection delete Destroy a host collection

erratum Manipulate errata for a host collection

hosts List all hosts

info Show a host collection list List host collections

package Manipulate packages for a host collection

package-group Manipulate package-groups for a host collection

remove-host Remove hosts from the host collection

update Update a host collection

Options:

-h, --help Print help

2.33.1. hammer host-collection add-host

Add host to the host collection

Usage:

hammer host-collection add-host [OPTIONS]

Options:

--host-ids HOST_IDS Array of host ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.33.2. hammer host-collection copy

Copy a host collection

Usage:

hammer host-collection copy [OPTIONS]

Options:

--id ID ID of the host collection

--name NAME Host collection name to search by --new-name NEW_NAME New host collection name

- --organization-label ORGANIZATION_LABEL Organization label to search by
- -h, --help Print help

2.33.3. hammer host-collection create

Create a host collection

Usage:

hammer host-collection create [OPTIONS]

Options:

--description DESCRIPTION

--host-ids HOST_IDS List of host ids to replace the hosts in host collection

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--max-hosts MAX_HOSTS Maximum number of hosts in the host collection
--name NAME Host Collection name

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have unlimited hosts

One of true/false, yes/no, 1/0.

-h, --help Print help

2.33.4. hammer host-collection delete

Destroy a host collection

Usage:

hammer host-collection delete [OPTIONS]

Options:

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.33.5. hammer host-collection erratum

Manipulate errata for a host collection

Usage:

hammer host-collection erratum [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

install Install errata on content hosts contained within a host collection

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.33.5.1. hammer host-collection erratum install

Install errata on content hosts contained within a host collection

Usage:

hammer host-collection erratum install [OPTIONS]

Options:

--errata ERRATA List of Errata to install

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id HOST_COLLECTION_ID Host Collection ID

--name HOST COLLECTION NAME Host Collection Name

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help Print help

2.33.6. hammer host-collection hosts

List all hosts

Usage:

hammer host-collection hosts [OPTIONS]

Options:

--environment ENVIRONMENT NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--id HOST COLLECTION ID Host Collection ID

--include INCLUDE Array of extra information types to include

Possible value(s): 'parameters', 'all_parameters'

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name HOST_COLLECTION_NAME Host Collection Name --order ORDER Sort field and order, eg. 'id DESC'

--organization-label ORGANIZATION_LABEL Organization label to search by

```
--page PAGE
                               Paginate results
--per-page PER_PAGE
                                    Number of entries per request
--search SEARCH
                                 Filter results
--thin THIN
                            Only list ID and name of hosts
                         One of true/false, yes/no, 1/0.
-h, --help
                           Print help
Search / Order fields:
 activation key
                      string
 activation key id
                       string
 addon
                   text
 addons_status
                       Values: mismatched, matched, not_specified
 ansible_role
                     string
 applicable_errata
                       string
 applicable_rpms
                       string
 architecture
                    string
 autoheal
                    boolean
                  Values: true, false
 build
 class
                  string
 comment
                     text
                         string
 compute resource
 compute_resource_id
                          integer
 config_group
                      string
 content source
                       string
 content_view
                      string
 content_view_id
                       integer
 domain
                    string
 domain id
                     integer
 environment
                      string
                     Values: security_needed, errata_needed, updated, unknown
 errata status
 execution_status
                       Values: ok, error
 facts
                  string
 global status
                      Values: ok, warning, error
 has ip
                   string
                     string
 has_mac
 hostgroup
                     string
 hostgroup fullname
                         string
 hostgroup_id
                      integer
 hostgroup_name
                         string
 hostgroup_title
                      string
 hypervisor
                    Values: true, false
 hypervisor_host
                       string
 image
                    string
 installable_errata
                      string
 installed_at
                    datetime
                 string
 ip
 job invocation.id
                      string
 job invocation.result Values: cancelled, failed, pending, success
 last_checkin
                     datetime
 last report
                    datetime
 lifecycle environment string
 lifecycle_environment_id integer
 location
                   string
 location_id
                    integer
 mac
                   string
 managed
                     Values: true, false
```

```
model
                   string
name
                   string
organization
                    string
organization_id
                     integer
origin
                 string
                 string
os
os description
                     string
os id
                  integer
os major
                    string
os minor
                    string
os title
                  string
owner
                   string
owner_id
                    integer
owner_type
                     string
params
                   string
                       string
params_name
parent_hostgroup
                       string
                     string
puppet_ca
puppet_proxy_id
                       integer
puppetmaster
                      string
                      Values: mismatched, matched, not specified
purpose_status
realm
                  string
realm id
                   integer
registered at
                     datetime
registered_through
                       string
release_version
                      string
                 text
role
                    Values: mismatched, matched, not_specified
role_status
service level
                    Values: mismatched, matched, not_specified
sla_status
smart_proxy
                     string
status.applied
                     integer
                      Values: true, false
status.enabled
status.failed
                    integer
status.failed restarts
                      integer
status.interesting
                     Values: true, false
status.pending
                     integer
                     integer
status.restarted
status.skipped
                     integer
subnet
                   string
subnet.name
                      text
subnet6
                   strina
subnet6.name
                      text
subscription_id
                     string
subscription_name
                        string
subscription status
                       Values: valid, partial, invalid, unknown, unsubscribed hypervisor
subscription uuid
trace status
                     Values: reboot needed, process restart needed, updated
upgradable_rpms
                        string
                   text
usage
usage_status
                      Values: mismatched, matched, not specified
                     string
user.firstname
                      string
user.lastname
user.login
                   string
user.mail
                   string
```

usergroup string
usergroup.name string
uuid string

2.33.7. hammer host-collection info

Show a host collection

Usage:

hammer host-collection info [OPTIONS]

Options:

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.33.8. hammer host-collection list

List host collections

Usage:

hammer host-collection list [OPTIONS]

Options:

--activation-key ACTIVATION_KEY_NAME Activation key name to search by

--activation-key-id ACTIVATION_KEY_ID ID of the activation key

--available-for AVAILABLE_FOR Interpret specified object to return only Host Collections that

can be

Associated with specified object. The value 'host' is supported.

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST NAME Host name

--host-id HOST ID

--name NAME Host collection name to filter by
--order ORDER Sort field and order, eg. 'id DESC'

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.33.9. hammer host-collection package

Manipulate packages for a host collection

Usage:

hammer host-collection package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

install Install packages on content hosts contained within a host collection remove Packages on content hosts contained within a host collection Update packages on content hosts contained within a host collection

Options:

-h, --help Print help

Unfortunately the server does not support such operation.

2.33.9.1. hammer host-collection package install

Install packages on content hosts contained within a host collection

Usage:

hammer host-collection package install [OPTIONS]

Options:

--id HOST_COLLECTION_ID Host Collection ID

--name HOST_COLLECTION_NAME Host Collection Name

--organization-label ORGANIZATION_LABEL Organization label to search by

--packages PACKAGES Comma-separated list of packages to install

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.9.2. hammer host-collection package remove

Remove packages on content hosts contained within a host collection

Usage:

hammer host-collection package remove [OPTIONS]

Options:

--id HOST COLLECTION ID Host Collection ID

--name HOST_COLLECTION_NAME Host Collection Name

--organization-label ORGANIZATION_LABEL Organization label to search by

--packages PACKAGES Comma-separated list of packages to install

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.9.3. hammer host-collection package update

Update packages on content hosts contained within a host collection

Usage:

hammer host-collection package update [OPTIONS]

Options:

--id HOST_COLLECTION_ID Host Collection ID

--name HOST_COLLECTION_NAME Host Collection Name

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--packages PACKAGES Comma-separated list of packages to install

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.10. hammer host-collection package-group

Manipulate package-groups for a host collection

Usage:

hammer host-collection package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

install Install package-groups on content hosts contained within a host collection remove Remove package-groups on content hosts contained within a host collection update Update package-groups on content hosts contained within a host collection

Options:

Print help -h, --help

Unfortunately the server does not support such operation.

2.33.10.1. hammer host-collection package-group install

Install package-groups on content hosts contained within a host collection

Usage:

hammer host-collection package-group install [OPTIONS]

Options:

--id HOST COLLECTION ID Host Collection ID

--name HOST COLLECTION NAME Host Collection Name

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--package-groups PACKAGE-GROUPS Comma-separated list of package-groups to install Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.10.2. hammer host-collection package-group remove

Remove package-groups on content hosts contained within a host collection

Usage:

hammer host-collection package-group remove [OPTIONS]

Options:

--id HOST COLLECTION ID Host Collection ID

--name HOST_COLLECTION_NAME Host Collection Name

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--package-groups PACKAGE-GROUPS Comma-separated list of package-groups to install

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.10.3. hammer host-collection package-group update

Update package-groups on content hosts contained within a host collection

Usage:

hammer host-collection package-group update [OPTIONS]

Options:

--id HOST COLLECTION ID Host Collection ID

--name HOST_COLLECTION_NAME Host Collection Name

--organization-label ORGANIZATION_LABEL Organization label to search by

--package-groups PACKAGE-GROUPS Comma-separated list of package-groups to install

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.33.11. hammer host-collection remove-host

Remove hosts from the host collection

Usage:

hammer host-collection remove-host [OPTIONS]

Options:

--host-ids HOST IDS Array of host ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID Id of the host collection

--name NAME Host collection name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.33.12. hammer host-collection update

Update a host collection

Usage:

hammer host-collection update [OPTIONS]

Options:

--description DESCRIPTION

--host-ids HOST_IDS List of host ids to replace the hosts in host collection

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID Id of the host collection

--max-hosts MAX_HOSTS Maximum number of hosts in the host collection

--name NAME Host collection name to search by --new-name NEW_NAME Host Collection name

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--unlimited-hosts UNLIMITED_HOSTS Whether or not the host collection may have unlimited hosts

One of true/false, yes/no, 1/0.

-h, --help Print help

2.34. HAMMER HOSTGROUP

Manipulate hostgroups

Usage:

hammer hostgroup [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

ansible-roles Manage Ansible roles on a hostgroup

create Create a host group delete Delete a host group

delete-parameter Delete parameter for a hostgroup

info Show a host group list List all host groups

puppet-classes
rebuild-config
sc-params

List all Puppet classes
Rebuild orchestration config
List all smart class parameters

set-parameter Create or update parameter for a hostgroup

smart-variables List all smart variables update Update a host group

Options:

-h, --help Print help

2.34.1. hammer hostgroup ansible-roles

Manage Ansible roles on a hostgroup

Usage:

hammer hostgroup ansible-roles [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

assign Assigns Ansible roles to a hostgroup list List all Ansible roles for a hostgroup play Plays Ansible roles on a hostgroup

Options:

-h, --help Print help

2.34.1.1. hammer hostgroup ansible-roles assign

Assigns Ansible roles to a hostgroup

Usage:

hammer hostgroup ansible-roles assign [OPTIONS]

Options:

--ansible-role-ids ANSIBLE_ROLE_IDS Ansible roles to assign to a hostgroup

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Hostgroup name

--organization ORGANIZATION_NAME Organization name

 --organization-title ORGANIZATION_TITLE Organization title

--title TITLE Hostgroup title -h, --help Print help

2.34.1.2. hammer hostgroup ansible-roles list

List all Ansible roles for a hostgroup

Usage:

hammer hostgroup ansible-roles list [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Hostgroup name

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Hostgroup title -h, --help Print help

2.34.1.3. hammer hostgroup ansible-roles play

Plays Ansible roles on a hostgroup

Usage:

hammer hostgroup ansible-roles play [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Hostgroup name

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Hostgroup title

-h, --help Print help

2.34.2. hammer hostgroup create

Create a host group

Usage:

hammer hostgroup create [OPTIONS]

Options:

--ansible-role-ids ANSIBLE ROLE IDS IDs of associated ansible roles

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters --ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --architecture ARCHITECTURE NAME Architecture name --architecture-id ARCHITECTURE ID --ask-root-pass ASK ROOT PW One of true/false, yes/no, 1/0. --compute-profile COMPUTE PROFILE NAME Compute profile name --compute-profile-id COMPUTE PROFILE ID --compute-resource COMPUTE RESOURCE NAME Compute resource name --compute-resource-id COMPUTE RESOURCE ID --config-group-ids CONFIG GROUP IDS IDs of associated config groups Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --config-groups CONFIG GROUP NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --content-source CONTENT SOURCE NAME Content Source name --content-source-id CONTENT SOURCE ID Content source ID --content-view CONTENT VIEW NAME Name to search by --content-view-id CONTENT VIEW ID Content view numeric identifier --description DESCRIPTION Host group description --domain DOMAIN NAME Domain name --domain-id DOMAIN ID Numerical ID or domain name --environment ENVIRONMENT_NAME Environment name (--environment is deprecated: Use --puppet-environment instead) --environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppetenvironment-id instead) --group-parameters-attributes GROUP_PARAMETERS_ATTRIBUTES Array of parameters Comma separated list of values defined by a schema. See Option details section below. JSON is acceptable and preferred way for complex parameters --kickstart-repository REPOSITORY NAME Kickstart repository name --kickstart-repository-id KICKSTART REPOSITORY ID Kickstart repository ID --lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Name to search by --lifecycle-environment-id LIFECYCLE ENVIRONMENT ID ID of the environment --location LOCATION NAME Location name --location-id LOCATION ID --location-ids LOCATION_IDS REPLACE locations with given ids Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --location-title LOCATION TITLE Location title --location-titles LOCATION TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --locations LOCATION NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --medium MEDIUM NAME Medium name --medium-id MEDIUM ID --name NAME Name of the host group --openscap-proxy-id OPENSCAP_PROXY_ID ID of OpenSCAP Capsule --operatingsystem OPERATINGSYSTEM TITLE Operating system title --operatingsystem-id OPERATINGSYSTEM ID

Red Hat Satellite 6.6 Hammer CLI Guide --organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-ids ORGANIZATION IDS REPLACE organizations with given ids. Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --organization-title ORGANIZATION_TITLE Organization title --organization-titles ORGANIZATION TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --organizations ORGANIZATION NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Name of parent hostgroup --parent PARENT NAME --parent-id PARENT_ID Parent ID of the host group --partition-table PARTITION TABLE NAME Partition table name --partition-table-id PARTITION TABLE ID --puppet-ca-proxy PUPPET CA PROXY NAME Name of puppet CA proxy --puppet-ca-proxy-id PUPPET CA PROXY ID Puppet CA Capsule ID --puppet-class-ids PUPPETCLASS_IDS List of puppetclass ids Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name --puppet-environment-id PUPPET_ENVIRONMENT_ID --puppet-proxy PUPPET PROXY NAME Name of puppet proxy --puppet-proxy-id PUPPET PROXY ID Puppet Capsule ID --pxe-loader PXE LOADER DHCP filename option (Grub2/PXELinux by default) Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI', 'Grub UEFI', 'Grub2 BIOS', 'Grub2 ELF', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded', 'iPXE Chain BIOS', 'iPXE Chain UEFI' --query-organization ORGANIZATION NAME Organization name to search by Organization ID to search by --query-organization-id ORGANIZATION ID --query-organization-label ORGANIZATION LABEL Organization label to search by --realm REALM NAME Name to search by --realm-id REALM_ID Numerical ID or realm name --root-pass ROOT_PASSWORD Root password --subnet SUBNET NAME Subnet name --subnet-id SUBNET ID

--subnet6 SUBNET6 NAME Subnet IPv6 name --subnet6-id SUBNET6 ID Subnet IPv6 ID

-h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--group-parameters-attributes "name=string\,value=string, ... "

2.34.3. hammer hostgroup delete

Delete a host group

Usage:

hammer hostgroup delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Hostgroup name
- --organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --title TITLE Hostgroup title -h, --help Print help

2.34.4. hammer hostgroup delete-parameter

Delete parameter for a hostgroup

Usage:

hammer hostgroup delete-parameter [OPTIONS]

Options:

- --hostgroup HOSTGROUP_NAME Hostgroup name
- --hostgroup-id HOSTGROUP_ID
- --hostgroup-title HOSTGROUP_TITLE Hostgroup title
- --name NAME Parameter name
- -h, --help Print help

2.34.5. hammer hostgroup info

Show a host group

Usage:

hammer hostgroup info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
 --name NAME Hostgroup name
- --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
 --organization-title ORGANIZATION TITLE Organization title
- --show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values

One of true/false, yes/no, 1/0.

--title TITLE Hostgroup title -h, --help Print help

2.34.6. hammer hostgroup list

List all host groups

Usage:

hammer hostgroup list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

architecture string class string config_group string environment string host string id integer label string location string location id integer medium string name string organization string organization id integer string os_description string os_id integer os_major string os minor string os_title string params text template string

2.34.7. hammer hostgroup puppet-classes

List all Puppet classes

Usage:

title

hammer hostgroup puppet-classes [OPTIONS]

Options:

- --hostgroup HOSTGROUP_NAME Hostgroup name
- --hostgroup-id HOSTGROUP ID

string

- --hostgroup-title HOSTGROUP_TITLE Hostgroup title
- --location-id LOCATION ID Scope by locations
- --order ORDER Sort field and order, eg. 'id DESC'

--organization-id ORGANIZATION_ID Scope by organizations

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

config_group string environment string host string hostgroup string key string location string string name organization string

2.34.8. hammer hostgroup rebuild-config

Rebuild orchestration config

Usage:

hammer hostgroup rebuild-config [OPTIONS]

Options:

--children-hosts CHILDREN_HOSTS Operate on child hostgroup hosts

One of true/false, yes/no, 1/0.

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Hostgroup name

--only ONLY Limit rebuild steps, valid steps are DHCP, DNS, TFTP

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME--organization-id ORGANIZATION_ID--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Hostgroup title -h, --help Print help

2.34.9. hammer hostgroup sc-params

List all smart class parameters

Usage:

hammer hostgroup sc-params [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE
--search SEARCH Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge_default Values: true, false merge_overrides Values: true, false

override Values: true, false

string parameter puppetclass string puppetclass_name string

2.34.10. hammer hostgroup set-parameter

Create or update parameter for a hostgroup

Usage:

hammer hostgroup set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--name NAME Parameter name

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

Parameter value --value VALUE

-h, --help Print help

2.34.11. hammer hostgroup smart-variables

List all smart variables

Usage:

hammer hostgroup smart-variables [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title --location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid duplicates Values: true, false

key string

merge_default Values: true, false merge_overrides Values: true, false override Values: true, false

parameter string puppetclass string

2.34.12. hammer hostgroup update

Update a host group

Usage:

hammer hostgroup update [OPTIONS]

Options:

--ansible-role-ids ANSIBLE ROLE IDS IDs of associated ansible roles

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ansible-roles ANSIBLE_ROLE_NAMES Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--architecture ARCHITECTURE_NAME Architecture name

--architecture-id ARCHITECTURE_ID

--ask-root-pass ASK_ROOT_PW One of true/false, yes/no, 1/0. --compute-profile COMPUTE PROFILE NAME Compute profile name

--compute-profile-id COMPUTE_PROFILE_ID

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE RESOURCE ID

--config-group-ids CONFIG GROUP IDS IDs of associated config groups

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-groups CONFIG_GROUP_NAMES Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--content-source CONTENT_SOURCE_NAME Content Source name
--content-source-id CONTENT_SOURCE_ID Content source ID
--content-view CONTENT_VIEW_NAME Name to search by

--content-view-id CONTENT_VIEW_ID Content view numeric identifier --description DESCRIPTION Host group description --domain DOMAIN NAME Domain name --domain-id DOMAIN ID Numerical ID or domain name --environment ENVIRONMENT NAME Environment name (--environment is deprecated: Use --puppet-environment instead) --environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --puppetenvironment-id instead) --group-parameters-attributes GROUP PARAMETERS ATTRIBUTES Array of parameters Comma separated list of values defined by a schema. See Option details section below. JSON is acceptable and preferred way for complex parameters --id ID --kickstart-repository REPOSITORY NAME Kickstart repository name --kickstart-repository-id KICKSTART_REPOSITORY_ID Kickstart repository ID --lifecycle-environment LIFECYCLE ENVIRONMENT NAME Name to search by --lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID ID of the environment --location LOCATION NAME Location name --location-id LOCATION ID --location-ids LOCATION IDS REPLACE locations with given ids Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --location-title LOCATION_TITLE Location title --location-titles LOCATION TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --locations LOCATION NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --medium MEDIUM NAME Medium name --medium-id MEDIUM_ID --name NAME Hostgroup name --new-name NEW NAME Name of the host group --openscap-proxy-id OPENSCAP_PROXY_ID ID of OpenSCAP Capsule --operatingsystem OPERATINGSYSTEM_TITLE Operating system title --operatingsystem-id OPERATINGSYSTEM ID --organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids. Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --organization-title ORGANIZATION_TITLE Organization title --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Comma separated list of values. Values --organizations ORGANIZATION NAMES containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Name of parent hostgroup --parent PARENT NAME --parent-id PARENT ID Parent ID of the host group --partition-table PARTITION_TABLE_NAME Partition table name --partition-table-id PARTITION_TABLE_ID --puppet-ca-proxy PUPPET_CA_PROXY_NAME Name of puppet CA proxy --puppet-ca-proxy-id PUPPET_CA_PROXY_ID Puppet CA Capsule ID

--puppet-class-ids PUPPETCLASS_IDS List of puppetclass ids

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-classes PUPPET_CLASS_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-environment PUPPET_ENVIRONMENT_NAME

Puppet environment name

--puppet-environment-id PUPPET ENVIRONMENT ID

--puppet-proxy PUPPET_PROXY_NAME Name of puppet proxy --puppet-proxy-id PUPPET_PROXY_ID Puppet Capsule ID

--pxe-loader PXE_LOADER DHCP filename option (Grub2/PXELinux by

default)

Possible value(s): 'None', 'PXELinux BIOS', 'PXELinux UEFI',

'Grub UEFI', 'Grub2 BIOS', 'Grub2 ELF', 'Grub2 UEFI', 'Grub2 UEFI SecureBoot', 'iPXE Embedded',

'iPXE Chain BIOS', 'iPXE Chain UEFI'

--query-organization ORGANIZATION_NAME Organization name to search by --query-organization-id ORGANIZATION_ID Organization ID to search by --query-organization-label ORGANIZATION LABEL

--realm REALM_NAME Name to search by
--realm-id REALM_ID Numerical ID or realm name
--root-pass ROOT_PASSWORD Root password
--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID
--subnet6 SUBNET6_NAME

--subnet6 SUBNET6_NAME Subnet IPv6 name
--subnet6-id SUBNET6_ID Subnet IPv6 ID

--title TITLE Hostgroup title -h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--group-parameters-attributes "name=string\,value=string, ... "

2.35. HAMMER IMPORT-TEMPLATES

Import templates from a git repo or a directory on the server

Usage:

hammer import-templates [OPTIONS]

Options:

--associate ASSOCIATE Associate to OS's, Locations & Organizations. Options are: always,

New or never.

Possible value(s): 'always', 'new', 'never'

--branch BRANCH Branch in Git repo.

--dirname DIRNAME The directory within Git repo containing the templates

--filter FILTER Export templates with names matching this regex (case-insensitive;

snippets

Are not filtered).

--force FORCE Update templates that are locked

One of true/false, yes/no, 1/0.

--location LOCATION_NAME

Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--lock LOCK Lock imported templates

One of true/false, yes/no, 1/0.

--negate NEGATE Negate the prefix (for purging).

One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--prefix PREFIX The string all imported templates should begin with.

--repo REPO Override the default repo from settings.
--verbose VERBOSE Show template diff in response

One of true/false, yes/no, 1/0.

-h, --help Print help

2.36. HAMMER JOB-INVOCATION

Manage job invocations

Usage:

hammer job-invocation [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

cancel Cancel the job

create Create a job invocation info Show job invocation list List job invocations

output View the output for a host

rerun Rerun the job

Options:

-h, --help Print help

2.36.1. hammer job-invocation cancel

Cancel the job

Usage:

hammer job-invocation cancel [OPTIONS]

Options:

--force FORCE One of true/false, yes/no, 1/0.

--id ID

--location-id LOCATION_ID Scope by locations

--organization-id ORGANIZATION_ID Scope by organizations

-h, --help Print help

2.36.2. hammer job-invocation create

Create a job invocation

Usage:

hammer job-invocation create [OPTIONS]

Options:

--async Do not wait for the task

--bookmark BOOKMARK_NAME Name to search by

--bookmark-id BOOKMARK_ID

--concurrency-level CONCURRENCY_LEVEL Run at most N tasks at a time

--cron-line CRONLINE Create a recurring execution

Cron line format 'a b c d e', where:

a. is minute (range: 0-59) b. is hour (range: 0-23)

c. is day of month (range: 1-31)

d. is month (range: 1-12) e. is day of week (range: 0-6)

--description-format DESCRIPTION_FORMAT Override the description format from the

template for this invocation only --dynamic

Dynamic search queries are evaluated at run time

--effective-user EFFECTIVE_USER What user should be used to run the script (using sudo-like mechanisms).

Defaults to a template parameter or global setting.

--end-time DATETIME Perform no more executions after this time, used with -

-cron-line

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

--execution-timeout-interval EXECUTION_TIMEOUT_INTERVAL Override the timeout interval from

the template for this invocation only

--feature FEATURE Remote execution feature label that should be triggered,

job template

Assigned to this feature will be used

--input-files INPUT FILES Read input values from files

Comma-separated list of key=file, where file is a path to a text file

to be read

--inputs INPUTS Specify inputs from command line

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--job-template-id JOB_TEMPLATE_ID

--location LOCATION_NAME

--location-id LOCATION_ID

--location-title LOCATION TITLE

--max-iteration MAX ITERATION

--organization ORGANIZATION NAME

--organization-id ORGANIZATION_ID

--organization-title ORGANIZATION TITLE

--search-query SEARCH_QUERY

--start-at DATETIME Schedule the execution for a later time

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

Repeat a maximum of N times

Organization name

Organization ID Organization title

Execution should be cancelled if it cannot be started

before --start-at

--start-before DATETIME

--time-span TIME_SPAN

belole --start-at

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

Distribute tasks over N seconds

Location name

Location title

-h, --help Print help

2.36.3. hammer job-invocation info

Show job invocation

Usage:

hammer job-invocation info [OPTIONS]

Options:

--id ID

--location-id LOCATION_ID Scope by locations

--organization-id ORGANIZATION_ID Scope by organizations

-h, --help Print help

2.36.4. hammer job-invocation list

List job invocations

Usage:

hammer job-invocation list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

2.36.5. hammer job-invocation output

View the output for a host

Usage:

hammer job-invocation output [OPTIONS]

Options:

--async Do not wait for job to complete, shows current output only

Host name --host HOST_NAME

--host-id HOST_ID

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title --name NAME Name to search by

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.36.6. hammer job-invocation rerun

Rerun the job

Usage:

hammer job-invocation rerun [OPTIONS]

Options:

--failed-only FAILED ONLY One of true/false, yes/no, 1/0.

--id ID

--location-id LOCATION_ID Scope by locations

--organization-id ORGANIZATION_ID Scope by organizations

-h, --help Print help

2.37. HAMMER JOB-TEMPLATE

Manage job templates

Usage:

hammer job-template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a job template delete Delete a job template View job template content dump

Export a template including all metadata export

Import a job template from ERB import

Show job template details info

List job templates list

update Update a job template

Options:

-h, --help Print help

2.37.1. hammer job-template create

Create a job template

Usage:

hammer job-template create [OPTIONS]

Options:

--audit-comment AUDIT COMMENT

--current-user CURRENT_USER Whether the current user login should be used as the effective user

One of true/false, yes/no, 1/0.

--description-format DESCRIPTION_FORMAT This template is used to generate the description. Input values can be used

Using the syntax %{package}. You may also include the job category and Template name using %{job_category} and %{template_name}.

--file TEMPLATE Path to a file that contains the template

--job-category JOB_CATEGORY Job category --location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Template name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--overridable OVERRIDABLE Whether it should be allowed to override the effective user from the

Invocation form.

One of true/false, yes/no, 1/0.

--provider-type PROVIDER TYPE Provider type

Possible value(s): 'SSH', 'Ansible'

--snippet SNIPPET One of true/false, yes/no, 1/0.

--value VALUE What user should be used to run the script (using sudo-like mechanisms)

-h, --help Print help

2.37.2. hammer job-template delete

Delete a job template

Usage:

hammer job-template delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.37.3. hammer job-template dump

View job template content

Usage:

hammer job-template dump [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.37.4. hammer job-template export

Export a template including all metadata

Usage:

hammer job-template export [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.37.5. hammer job-template import

Import a job template from ERB

Usage:

hammer job-template import [OPTIONS]

Options:

--file TEMPLATE Path to a file that contains the template - must include ERB

metadata

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--overwrite OVERWRITE Overwrite template if it already exists

One of true/false, yes/no, 1/0.

-h, --help Print help

2.37.6. hammer job-template info

Show job template details

Usage:

hammer job-template info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.37.7. hammer job-template list

List job templates

Usage:

hammer job-template list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

2.37.8. hammer job-template update

Update a job template

Usage:

hammer job-template update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--current-user CURRENT_USER Whether the current user login should be used as the

effective user

One of true/false, yes/no, 1/0.

--description-format DESCRIPTION_FORMAT This template is used to generate the description.

Input values can be used

Using the syntax %{package}. You may also include the job category and

Template name using %{job_category} and %{template_name}.

--file TEMPLATE Path to a file that contains the template

--id ID

--job-category JOB_CATEGORY Job category --location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by
--new-name NEW NAME Template name

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--overridable OVERRIDABLE Whether it should be allowed to override the effective user

from the

Invocation form.

One of true/false, yes/no, 1/0.

--provider-type PROVIDER_TYPE Provider type

Possible value(s): 'SSH', 'Ansible'

--snippet SNIPPET One of true/false, yes/no, 1/0.

--value VALUE What user should be used to run the script (using sudo-like

mechanisms)

-h, --help Print help

2.38. HAMMER LIFECYCLE-ENVIRONMENT

Manipulate lifecycle_environments on the server

Usage:

hammer lifecycle-environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an environment delete Destroy an environment info Show an environment

list List environments in an organization

paths List environment paths update Update an environment

Options:

-h, --help Print help

2.38.1. hammer lifecycle-environment create

Create an environment

Usage:

hammer lifecycle-environment create [OPTIONS]

Options:

--description DESCRIPTION Description of the environment

--label LABEL
--name NAME
Label of the environment
Name of the environment

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--prior PRIOR Name of the prior environment

--prior-id PRIOR_ID ID of an environment that is prior to the new

environment in the chain. It

Has to be either the ID of Library or the ID of an environment

at the end

Of a chain.

--registry-name-pattern REGISTRY_NAME_PATTERN Pattern for container image names

--registry-unauthenticated-pull REGISTRY_UNAUTHENTICATED_PULL Allow unauthenticed pull of container images

One of true/false, yes/no, 1/0.

-h, --help Print help

2.38.2. hammer lifecycle-environment delete

Destroy an environment

Usage:

hammer lifecycle-environment delete [OPTIONS]

Options:

--id ID ID of the environment

--name NAME Lifecycle environment name to search by --organization ORGANIZATION_NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.38.3. hammer lifecycle-environment info

Show an environment

Usage:

hammer lifecycle-environment info [OPTIONS]

Options:

--id ID ID of the environment

--name NAME Lifecycle environment name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.38.4. hammer lifecycle-environment list

List environments in an organization

Usage:

hammer lifecycle-environment list [OPTIONS]

Options:

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--library LIBRARY Set true if you want to see only library environments

Possible value(s): 'true', 'false'

--name NAME Filter only environments containing this name

--order ORDER Sort field and order, eg. 'id DESC'

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.38.5. hammer lifecycle-environment paths

List environment paths

Usage:

hammer lifecycle-environment paths [OPTIONS]

Options:

--organization-label ORGANIZATION_LABEL Organization label to search by

promotable) Default:

Readable

-h, --help Print help

2.38.6. hammer lifecycle-environment update

Update an environment

Usage:

hammer lifecycle-environment update [OPTIONS]

Options:

--async ASYNC Do not wait for the update action to finish. Default: true

One of true/false, yes/no, 1/0.

--description DESCRIPTION Description of the environment

--id ID ID of the environment

--name NAME Lifecycle environment name to search by

--new-name NEW_NAME New name to be given to the environment Organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--registry-name-pattern REGISTRY_NAME_PATTERN Pattern for container image names

--registry-unauthenticated-pull REGISTRY_UNAUTHENTICATED_PULL Allow unauthenticed pull of

container images

One of true/false, yes/no, 1/0.

-h, --help Print help

2.39. HAMMER LOCATION

Manipulate locations

Usage:

hammer location [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-compute-resource Associate a compute resource add-config-template Associate a configuration template

add-domain Associate a domain

add-environment Associate a Puppet environment

add-hostgroup Associate a hostgroup
add-medium Associate a medium
add-organization Associate an organization
add-smart-proxy Associate a smart proxy

add-subnet Associate a subnet add-user Associate an user create Create a location delete Delete a location

delete-parameter Delete parameter for a location

info Show a location list List all locations

remove-compute-resource Disassociate a compute resource remove-config-template Disassociate a configuration template

remove-domain Disassociate a domain

remove-environment Disassociate a Puppet environment

remove-hostgroup
remove-medium
Disassociate a hostgroup
Disassociate a medium
Disassociate an organization
Disassociate a smart proxy

remove-subnet Disassociate a subnet Disassociate an user

set-parameter Create or update parameter for a location

update Update a location

Options:

-h, --help Print help

2.39.1. hammer location add-compute-resource

Associate a compute resource

Usage:

hammer location add-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE RESOURCE NAME Compute resource name

--compute-resource-id COMPUTE RESOURCE ID

--id ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.2. hammer location add-config-template

Associate a configuration template

Usage:

hammer location add-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID

--id ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.3. hammer location add-domain

Associate a domain

Usage:

hammer location add-domain [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--id ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.4. hammer location add-environment

Associate a Puppet environment

Usage:

hammer location add-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--id ID

--name NAME Location name

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

--title TITLE Location title -h, --help Print help

2.39.5. hammer location add-hostgroup

Associate a hostgroup

Usage:

hammer location add-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.6. hammer location add-medium

Associate a medium

Usage:

hammer location add-medium [OPTIONS]

Options:

--id ID

--medium-id MEDIUM_ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.7. hammer location add-organization

Associate an organization

Usage:

hammer location add-organization [OPTIONS]

Options:

--id ID

--name NAME Location name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Location title -h, --help Print help

2.39.8. hammer location add-smart-proxy

Associate a smart proxy

Usage:

hammer location add-smart-proxy [OPTIONS]

Options:

--id ID

--name NAME Location name

--smart-proxy SMART_PROXY_NAME Name to search by

--smart-proxy-id SMART_PROXY_ID
--title TITLE Location title
-h, --help Print help

2.39.9. hammer location add-subnet

Associate a subnet

Usage:

hammer location add-subnet [OPTIONS]

Options:

--id ID

--name NAME Location name
--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET_ID

--title TITLE Location title -h, --help Print help

2.39.10, hammer location add-user

Associate an user

Usage:

hammer location add-user [OPTIONS]

Options:

--id ID

--name NAME Location name
--title TITLE Location title

--user USER LOGIN User's login to search by

--user-id USER ID

-h, --help Print help

2.39.11, hammer location create

Create a location

Usage:

hammer location create [OPTIONS]

Options:

--compute-resource-ids COMPUTE RESOURCE IDS Compute resource IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--compute-resources COMPUTE_RESOURCE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --description DESCRIPTION --domain-ids DOMAIN IDS Domain IDs Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --domains DOMAIN NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --environment-ids ENVIRONMENT IDS Environment IDs (--environment-ids is deprecated: Use --puppet-environment-ids instead) Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --environments ENVIRONMENT NAMES (--environments is deprecated: Use --puppetenvironments instead) --hostgroup-ids HOSTGROUP IDS Host group IDs Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --hostgroup-titles HOSTGROUP TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --ignore-types IGNORE TYPES List of resources types that will be automatically associated Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Location name --location LOCATION NAME --location-id LOCATION ID --location-title LOCATION TITLE Location title --media MEDIUM NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --medium-ids MEDIUM_IDS Medium IDs Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --name NAME --organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--parent-id PARENT ID Parent ID

--partition-table-ids PARTITION_TABLE_IDS Partition template IDs

Comma separated list of values. Values containing comma should

be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-templates PROVISIONING TEMPLATE NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-environment-ids PUPPET ENVIRONMENT IDS **Environment IDs**

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-environments PUPPET ENVIRONMENT NAMES Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-ids REALM IDS Realm IDs

Comma separated list of values. Values containing comma should

be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realms REALM NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxies SMART PROXY NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxy-ids SMART PROXY IDS Capsule IDs

Comma separated list of values. Values containing comma should

be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Subnet IDs --subnet-ids SUBNET_IDS

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnets SUBNET NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

User IDs --user-ids USER IDS

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.39.12. hammer location delete

Delete a location

hammer location delete [OPTIONS]

Options:

--id ID Location numeric id to search by

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title --name NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Organization title

-h, --help Print help

2.39.13. hammer location delete-parameter

Delete parameter for a location

Usage:

hammer location delete-parameter [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Parameter name

-h, --help Print help

2.39.14. hammer location info

Show a location

Usage:

hammer location info [OPTIONS]

Options:

--id ID Location numeric id to search by --location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Organization name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values

One of true/false, yes/no, 1/0.

--title TITLE Organization title

-h, --help Print help

2.39.15. hammer location list

List all locations

Usage:

hammer location list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE
--search SEARCH Number of entries per request

Filter results

-h, --help Print help

2.39.16. hammer location remove-compute-resource

Disassociate a compute resource

Usage:

hammer location remove-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE RESOURCE ID

--id ID

--name NAME Location name --title TITLE Location title -h, --help Print help

2.39.17. hammer location remove-config-template

Disassociate a configuration template

Usage:

hammer location remove-config-template [OPTIONS]

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID

--name NAME Location name --title TITLE Location title -h, --help Print help

2.39.18, hammer location remove-domain

Disassociate a domain

Usage:

hammer location remove-domain [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID
--name NAME Location title Location name -h, --help Print help

2.39.19. hammer location remove-environment

Disassociate a Puppet environment

Usage:

hammer location remove-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--id ID

--name NAME Location name

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

--title TITLE Location title -h, --help Print help

2.39.20. hammer location remove-hostgroup

Disassociate a hostgroup

Usage:

hammer location remove-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.21. hammer location remove-medium

Disassociate a medium

Usage:

hammer location remove-medium [OPTIONS]

Options:

--id ID

--medium-id MEDIUM ID

--name NAME Location name
--title TITLE Location title
-h, --help Print help

2.39.22. hammer location remove-organization

Disassociate an organization

Usage:

hammer location remove-organization [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION TITLE Organization title
- --title TITLE Location title -h, --help Print help

2.39.23. hammer location remove-smart-proxy

Disassociate a smart proxy

Usage:

hammer location remove-smart-proxy [OPTIONS]

Options:

- --id ID
- --name NAME Location name
- --smart-proxy SMART_PROXY_NAME Name to search by
- --smart-proxy-id SMART_PROXY_ID
- --title TITLE Location title -h, --help Print help

2.39.24. hammer location remove-subnet

Disassociate a subnet

Usage:

hammer location remove-subnet [OPTIONS]

Options:

- --id ID
- --name NAME Location name
 --subnet SUBNET NAME Subnet name
- --subnet-id SUBNET ID
- --title TITLE Location title -h, --help Print help

2.39.25. hammer location remove-user

Disassociate an user

Usage:

hammer location remove-user [OPTIONS]

Options:

- --id ID
- --name NAME Location name
 --title TITLE Location title

--user-id USER_ID

-h, --help Print help

2.39.26. hammer location set-parameter

Create or update parameter for a location

Usage:

hammer location set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN_VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Parameter name

--parameter-type PARAMETER TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.39.27. hammer location update

Update a location

Usage:

hammer location update [OPTIONS]

Options:

--compute-resource-ids COMPUTE RESOURCE IDS Compute resource IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--compute-resources COMPUTE_RESOURCE_NAMES Comma separated list of values.

Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION

--domain-ids DOMAIN IDS Domain IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environment-ids ENVIRONMENT_IDS Environment IDs (--environment-ids is deprecated: Use --puppet-environment-ids instead) Comma separated list of values. Values containing comma should be guoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --environments ENVIRONMENT NAMES (--environments is deprecated: Use --puppetenvironments instead) --hostgroup-ids HOSTGROUP IDS Host group IDs Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --hostgroup-titles HOSTGROUP TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Location numeric id to search by --id ID --ignore-types IGNORE TYPES List of resources types that will be automatically associated Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Location name --location LOCATION NAME --location-id LOCATION ID --location-title LOCATION TITLE Location title --media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters Medium IDs --medium-ids MEDIUM_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --name NAME Location name --new-name NEW NAME Organization name --organization ORGANIZATION_NAME --organization-id ORGANIZATION ID Organization ID --organization-title ORGANIZATION TITLE Organization title Parent ID --parent-id PARENT ID --partition-table-ids PARTITION_TABLE_IDS Partition template IDs Comma separated list of values. Values containing comma should be guoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --provisioning-template-ids PROVISIONING TEMPLATE IDS Provisioning template IDs Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --provisioning-templates PROVISIONING TEMPLATE NAMES Comma separated list of values. Values containing comma should be guoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --puppet-environment-ids PUPPET_ENVIRONMENT_IDS **Environment IDs** Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-environments PUPPET_ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-ids REALM_IDS Realm IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxy-ids SMART_PROXY_IDS Capsule IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnet-ids SUBNET_IDS Subnet IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnets SUBNET_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--title TITLE Location title
--user-ids USER_IDS User IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER_LOGINS Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.40. HAMMER MEDIUM

Manipulate installation media

Usage:

hammer medium [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

create Create a medium delete Delete a medium info Show a medium

list List all installation media

remove-operatingsystem Disassociate an operating system

update Update a medium

Options:

-h, --help Print help

2.40.1. hammer medium add-operatingsystem

Associate an operating system

Usage:

hammer medium add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Medium name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help Print help

2.40.2. hammer medium create

Create a medium

Usage:

hammer medium create [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Name of media

--operatingsystem-ids OPERATINGSYSTEM_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing

comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--os-family OS_FAMILY

Operating system family, available values: AIX, Altlinux,

Archlinux,

Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Rancheros, Redhat,

Solaris,

Suse, VRP, Windows, Xenserver

--path PATH (exclusive of

The path to the medium, can be a URL or a valid NFS server

The architecture).

For example mirror.centos.org/centos/\$version/os/\$arch

Where \$arch will be substituted for the host's actual OS architecture And \$version, \$major and \$minor will be substituted for the version of the

Operating system.

Solaris and Debian media may also use \$release.

-h, --help Print help

2.40.3. hammer medium delete

Delete a medium

Usage:

hammer medium delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Medium name
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.40.4. hammer medium info

Show a medium

Usage:

hammer medium info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Medium name
- --organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.40.5. hammer medium list

List all installation media

Usage:

hammer medium list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE
--search SEARCH Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

family string location string location_id integer name string organization string organization id integer path string

2.40.6. hammer medium remove-operatingsystem

Disassociate an operating system

Usage:

hammer medium remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Medium name

--operatingsystem OPERATINGSYSTEM TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help Print help

2.40.7. hammer medium update

Update a medium

Usage:

hammer medium update [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Medium name

--new-name NEW_NAME Name of media

--operatingsystem-ids OPERATINGSYSTEM_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--os-family OS FAMILY Op

Operating system family, available values: AIX, Altlinux,

Archlinux,

Coreos, Debian, Freebsd, Gentoo, Junos, NXOS, Rancheros, Redhat,

Solaris,

Suse, VRP, Windows, Xenserver

--path PATH (exclusive of

The path to the medium, can be a URL or a valid NFS server

The architecture).

For example mirror.centos.org/centos/\$version/os/\$arch

Where \$arch will be substituted for the host's actual OS architecture And \$version, \$major and \$minor will be substituted for the version of the

Operating system.

Solaris and Debian media may also use \$release.

-h, --help Print help

2.41. HAMMER MODEL

Manipulate hardware models

Usage:

hammer model [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a hardware model
delete Delete a hardware model
info Show a hardware model
list List all hardware models
update Update a hardware model

Options:

-h, --help Print help

2.41.1. hammer model create

Create a hardware model

Usage:

hammer model create [OPTIONS]

Options:

--hardware-model HARDWARE_MODEL

--info INFO

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME

--organization-title ORGANIZATION TITLE Organization title

--vendor-class VENDOR CLASS

-h, --help Print help

2.41.2. hammer model delete

Delete a hardware model

Usage:

hammer model delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Model name

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title -h, --help Print help

2.41.3. hammer model info

Show a hardware model

Usage:

hammer model info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Model name
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.41.4. hammer model list

List all hardware models

Usage:

hammer model list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'

- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

hardware model string

info text
name string
vendor class string

2.41.5. hammer model update

Update a hardware model

Usage:

hammer model update [OPTIONS]

Options:

- --hardware-model HARDWARE MODEL
- --id ID
- --info INFO
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Model name
- --new-name NEW NAME

- --organization-title ORGANIZATION TITLE Organization title
- --vendor-class VENDOR_CLASS
- -h, --help Print help

2.42. HAMMER MODULE-STREAM

View Module Streams

Usage:

hammer module-stream [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a module stream list List module streams

Options:

-h, --help Print help

2.42.1. hammer module-stream info

Show a module stream

Usage:

hammer module-stream info [OPTIONS]

Options:

--id ID A module stream identifier

--name NAME Module stream name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.42.2. hammer module-stream list

List module streams

Usage:

hammer module-stream list [OPTIONS]

Options:

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT_ID

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host-ids HOST_IDS List of host id to list available module streams for

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ids IDS Ids to filter content by

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name-stream-only NAME STREAM ONLY Return name and stream information only)

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID
--search SEARCH Search string

-h, --help Print help

2.43. HAMMER ORGANIZATION

Manipulate organizations

Usage:

hammer organization [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-compute-resource Associate a compute resource add-config-template Associate a configuration template

add-domain Associate a domain

add-environment Associate a Puppet environment

add-hostgroup
add-location
add-medium
add-smart-proxy

Associate a hostgroup
Associate a location
Associate a medium
Associate a smart proxy

add-subnet Associate a subnet add-user Associate an user create Create organization delete Delete an organization

delete-parameter Delete parameter for an organization

info Show organization list List all organizations

remove-compute-resource Disassociate a compute resource remove-config-template Disassociate a configuration template

remove-domain Disassociate a domain

remove-environment Disassociate a Puppet environment

remove-hostgroup
remove-location
remove-medium
remove-smart-proxy

Disassociate a hostgroup
Disassociate a location
Disassociate a medium
Disassociate a smart proxy

remove-subnet Disassociate a subnet Pisassociate an user

set-parameter Create or update parameter for an organization

update Update organization

Options:

-h, --help Print help

2.43.1. hammer organization add-compute-resource

Associate a compute resource

Usage:

hammer organization add-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE RESOURCE ID

--id ID Organization ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.2. hammer organization add-config-template

Associate a configuration template

Usage:

hammer organization add-config-template [OPTIONS]

Options:

--config-template CONFIG_TEMPLATE_NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID
--id ID Organization ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.3. hammer organization add-domain

Associate a domain

Usage:

hammer organization add-domain [OPTIONS]

Options:

--domain DOMAIN NAME Domain name

--domain-id DOMAIN_ID
Numerical ID or domain name

--id ID Organization ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.4. hammer organization add-environment

Associate a Puppet environment

Usage:

hammer organization add-environment [OPTIONS]

Options:

--environment ENVIRONMENT NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--id ID Organization ID

--name NAME Organization name

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID
--title TITLE Organization title

-h, --help Print help

2.43.5. hammer organization add-hostgroup

Associate a hostgroup

Usage:

hammer organization add-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID Organization ID

--name NAME Organization name

--title TITLE Organization title

-h, --help Print help

2.43.6. hammer organization add-location

Associate a location

Usage:

hammer organization add-location [OPTIONS]

Options:

--id ID Organization ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.7. hammer organization add-medium

Associate a medium

Usage:

hammer organization add-medium [OPTIONS]

Options:

--id ID Organization ID

--medium MEDIUM NAME Medium name

--medium-id MEDIUM ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.8. hammer organization add-smart-proxy

Associate a smart proxy

Usage:

hammer organization add-smart-proxy [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name

--smart-proxy SMART_PROXY_NAME Name to search by

--smart-proxy-id SMART_PROXY_ID

--title TITLE Organization title

-h, --help Print help

2.43.9. hammer organization add-subnet

Associate a subnet

Usage:

hammer organization add-subnet [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name
--subnet SUBNET NAME Subnet name

--subnet-id SUBNET ID

--title TITLE Organization title

-h, --help Print help

2.43.10. hammer organization add-user

Associate an user

Usage:

hammer organization add-user [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name

--title TITLE Organization title

--user-id USER ID

-h, --help Print help

2.43.11. hammer organization create

Create organization

Usage:

hammer organization create [OPTIONS]

Options:

--compute-resource-ids COMPUTE_RESOURCE_IDS Compute resource IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--compute-resources COMPUTE_RESOURCE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-template-ids CONFIG_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION Description
--domain-ids DOMAIN IDS Domain IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environment-ids ENVIRONMENT_IDS Environment IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environments ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-ids HOSTGROUP_IDS Host group IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--label LABEL Unique label

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--medium-ids MEDIUM_IDS Medium IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Name

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--provisioning-template-ids PROVISIONING_TEMPLATE IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ptable-ids PTABLE_IDS Partition template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ptables PTABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-ids REALM_IDS Realm IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxy-ids SMART_PROXY_IDS Capsule IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnet-ids SUBNET_IDS Subnet IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnets SUBNET_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-ids USER IDS User IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER_LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.43.12. hammer organization delete

Delete an organization

Usage:

hammer organization delete [OPTIONS]

Options:

--async Do not wait for the task

--id ID

--label LABEL Organization label to search by

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Organization name

--organization-label ORGANIZATION LABEL Organization label to search by

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Organization title

-h, --help Print help

2.43.13. hammer organization delete-parameter

Delete parameter for an organization

Usage:

hammer organization delete-parameter [OPTIONS]

Options:

--name NAME Parameter name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.43.14. hammer organization info

Show organization

Usage:

hammer organization info [OPTIONS]

Options:

--id ID

--label LABEL Organization label to search by

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--organization-title ORGANIZATION_TITLE Organization title

--title TITLE Organization title

-h, --help Print help

2.43.15. hammer organization list

List all organizations

Usage:

hammer organization list [OPTIONS]

Options:

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name

--organization-label ORGANIZATION LABEL Organization label to search by

--organization-title ORGANIZATION_TITLE Organization title --page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--sort-by SORT_BY Field to sort the results on

--sort-order SORT_ORDER How to order the sorted results (e.g. ASC for ascending)

-h, --help Print help

2.43.16. hammer organization remove-compute-resource

Disassociate a compute resource

Usage:

hammer organization remove-compute-resource [OPTIONS]

Options:

--compute-resource COMPUTE_RESOURCE_NAME Compute resource name

--compute-resource-id COMPUTE_RESOURCE_ID

--id ID Organization ID

--name NAME Organization name --title TITLE Organization title

Print help -h, --help

2.43.17. hammer organization remove-config-template

Disassociate a configuration template

Usage:

hammer organization remove-config-template [OPTIONS]

--config-template CONFIG TEMPLATE NAME Name to search by

--config-template-id CONFIG_TEMPLATE_ID --id ID Organization ID

--name NAME Organization name --title TITLE Organization title

Print help -h, --help

2.43.18. hammer organization remove-domain

Disassociate a domain

Usage:

hammer organization remove-domain [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--id ID Organization ID

--name NAME --title TITLE Organization name Organization title

-h, --help Print help

2.43.19. hammer organization remove-environment

Disassociate a Puppet environment

Usage:

hammer organization remove-environment [OPTIONS]

Options:

--environment ENVIRONMENT NAME Use --puppet-environment instead)

Environment name (--environment is deprecated:

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--id ID Organization ID

--name NAME Organization name

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID
--title TITLE Organization title

-h, --help Print help

2.43.20. hammer organization remove-hostgroup

Disassociate a hostgroup

Usage:

hammer organization remove-hostgroup [OPTIONS]

Options:

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID Organization ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.21. hammer organization remove-location

Disassociate a location

Usage:

hammer organization remove-location [OPTIONS]

Options:

--id ID Organization ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.22. hammer organization remove-medium

Disassociate a medium

Usage:

hammer organization remove-medium [OPTIONS]

Options:

--id ID Organization ID

--medium-id MEDIUM_ID

--name NAME Organization name
--title TITLE Organization title

-h, --help Print help

2.43.23. hammer organization remove-smart-proxy

Disassociate a smart proxy

Usage:

hammer organization remove-smart-proxy [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name

--smart-proxy SMART_PROXY_NAME Name to search by

--smart-proxy-id SMART_PROXY_ID
--title TITLE Organization title

-h, --help Print help

2.43.24. hammer organization remove-subnet

Disassociate a subnet

Usage:

hammer organization remove-subnet [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name
--subnet SUBNET NAME Subnet name

--subnet-id SUBNET ID

--title TITLE Organization title

-h, --help Print help

2.43.25. hammer organization remove-user

Disassociate an user

Usage:

hammer organization remove-user [OPTIONS]

Options:

--id ID Organization ID

--name NAME Organization name

--title TITLE Organization title

--user-id USER ID

-h, --help Print help

2.43.26. hammer organization set-parameter

Create or update parameter for an organization

_

Usage:

hammer organization set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN_VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--name NAME Parameter name

--organization-title ORGANIZATION TITLE Organization title

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.43.27. hammer organization update

Update organization

Usage:

hammer organization update [OPTIONS]

Options:

--compute-resource-ids COMPUTE_RESOURCE_IDS Compute resource IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--compute-resources COMPUTE_RESOURCE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-template-ids CONFIG TEMPLATE IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION

--domain-ids DOMAIN_IDS Domain IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environment-ids ENVIRONMENT_IDS Environment IDs (--environment-ids is deprecated: Use --puppet-environment-ids instead)

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--environments ENVIRONMENT_NAMES (--environments is deprecated: Use --puppet-

environments instead)

--hostgroup-ids HOSTGROUP_IDS Host group IDs

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID

--ignore-types IGNORE_TYPES List of resources types that will be automatically associated

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--label LABEL Organization label to search by

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--medium-ids MEDIUM_IDS Medium IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Organization name

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--parent-id PARENT_ID Parent ID

--partition-table-ids PARTITION_TABLE_IDS Partition template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS Provisioning template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ptable-ids PTABLE_IDS Partition template IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ptables PTABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-environments PUPPET_ENVIRONMENT_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-ids REALM IDS Realm IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realms REALM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--redhat-repository-url REDHAT_REPOSITORY_URL Red Hat CDN URL

--smart-proxies SMART_PROXY_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--smart-proxy-ids SMART_PROXY_IDS Capsule IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnet-ids SUBNET_IDS Subnet IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--subnets SUBNET_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--title TITLE Organization title
--user-ids USER_IDS User IDs

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER_LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.44. HAMMER OS

Manipulate operating system

Usage:

hammer os [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-architecture Associate an architecture

add-config-template Associate a configuration template

add-ptable Associate a partition table create Create an operating system delete Delete an operating system

delete-default-template

delete-parameter Delete parameter for an operating system

info Show an operating system list List all operating systems

remove-architecture Disassociate an architecture

remove-config-template Disassociate a configuration template

remove-ptable Disassociate a partition table

set-default-template

set-parameter Create or update parameter for an operating system

update Update an operating system

Options:

-h, --help Print help

2.44.1. hammer os add-architecture

Associate an architecture

Usage:

hammer os add-architecture [OPTIONS]

Options:

- --architecture ARCHITECTURE_NAME Architecture name
- --architecture-id ARCHITECTURE_ID
- --id ID

--title TITLE Operating system title

-h, --help Print help

2.44.2. hammer os add-config-template

Associate a configuration template

Usage:

hammer os add-config-template [OPTIONS]

Options:

- --config-template CONFIG TEMPLATE NAME Name to search by
- --config-template-id CONFIG_TEMPLATE_ID
- --id ID

--title TITLE Operating system title

-h, --help Print help

2.44.3. hammer os add-ptable

Associate a partition table

Usage:

hammer os add-ptable [OPTIONS]

Options:

- --id ID
- --partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--title TITLE Operating system title

-h, --help Print help

2.44.4. hammer os create

Create an operating system

Usage:

hammer os create [OPTIONS]

Options:

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--architectures ARCHITECTURE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION

--family FAMILY

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--major MAJOR

--media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--medium-ids MEDIUM IDS IDs of associated media

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --minor MINOR
- --name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--os-parameters-attributes OS PARAMETERS ATTRIBUTES Array of parameters

Comma separated list of values defined by a schema. See Option

details section below.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--password-hash PASSWORD_HASH MD5, SHA256, SHA512, Base64

Root password hash function to use, one of

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning templates

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--release-name RELEASE NAME

-h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--os-parameters-attributes "name=string\,value=string, ... "

2.44.5. hammer os delete

Delete an operating system

Usage:

hammer os delete [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization ORGANIZATION_NAME Organization name

 $\hbox{--organization-title ORGANIZATION_TITLE Organization title}\\$

--title TITLE Operating system title

-h, --help Print help

2.44.6. hammer os delete-default-template

Usage:

hammer os delete-default-template [OPTIONS]

Options:

--id OS ID Operatingsystem id

--type TPL TYPE Type of the config template

-h, --help Print help

2.44.7. hammer os delete-parameter

Delete parameter for an operating system

Usage:

hammer os delete-parameter [OPTIONS]

Options:

--name NAME Parameter name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM ID

-h, --help Print help

2.44.8. hammer os info

Show an operating system

Usage:

hammer os info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--show-hidden-parameters SHOW HIDDEN PARAMETERS Display hidden parameter values

One of true/false, yes/no, 1/0.

--title TITLE Operating system title

-h, --help Print help

2.44.9. hammer os list

List all operating systems

Usage:

hammer os list [OPTIONS]

Options:

--architecture ARCHITECTURE NAME Architecture name

--architecture-id ARCHITECTURE ID

--config-template-id CONFIG_TEMPLATE_ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--medium MEDIUM_NAME Medium name

--medium-id MEDIUM_ID

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--os-parameters-attributes OS PARAMETERS ATTRIBUTES Array of parameters

Comma separated list of values defined by a schema. See Option

details section below.

JSON is acceptable and preferred way for complex parameters

--page PAGE Paginate results

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION_TABLE_ID

--per-page PER_PAGE

Number of entries per request

- --provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by
- --provisioning-template-id PROVISIONING_TEMPLATE_ID
- --search SEARCH Filter results

-h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--os-parameters-attributes "name=string\,value=string, ... "

Search / Order fields:

architecture string description string family string major string medium string minor string name string params text template string title string

2.44.10. hammer os remove-architecture

Disassociate an architecture

Usage:

hammer os remove-architecture [OPTIONS]

Options

- --architecture ARCHITECTURE NAME Architecture name
- --architecture-id ARCHITECTURE ID
- --id ID
- --title TITLE Operating system title

-h, --help Print help

2.44.11. hammer os remove-config-template

Disassociate a configuration template

Usage:

hammer os remove-config-template [OPTIONS]

Options:

- --config-template CONFIG TEMPLATE NAME Name to search by
- --config-template-id CONFIG_TEMPLATE_ID
- --id ID

--title TITLE Operating system title

-h, --help Print help

2.44.12. hammer os remove-ptable

Disassociate a partition table

Usage:

hammer os remove-ptable [OPTIONS]

Options:

--id ID

--partition-table PARTITION_TABLE_NAME Partition table name

--partition-table-id PARTITION TABLE ID

--title TITLE Operating system title

-h, --help Print help

2.44.13. hammer os set-default-template

Usage:

hammer os set-default-template [OPTIONS]

Options:

--config-template-id TPL ID Config template id to be set

--id OS ID Operatingsystem id

-h, --help Print help

2.44.14. hammer os set-parameter

Create or update parameter for an operating system

Usage:

hammer os set-parameter [OPTIONS]

Options:

--hidden-value HIDDEN_VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--name NAME Parameter name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

Default: "string"

--value VALUE Parameter value

-h, --help Print help

2.44.15. hammer os update

Update an operating system

Usage:

hammer os update [OPTIONS]

Options:

--architecture-ids ARCHITECTURE IDS IDs of associated architectures

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--architectures ARCHITECTURE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--config-templates CONFIG_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--description DESCRIPTION

--family FAMILY

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--major MAJOR

--media MEDIUM_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--minor MINOR

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION TITLE Organization title

--os-parameters-attributes OS_PARAMETERS_ATTRIBUTES Array of parameters

Comma separated list of values defined by a schema. See Option

details section below.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--partition-tables PARTITION_TABLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--password-hash PASSWORD_HASH Root password hash function to use, one of MD5, SHA256, SHA512, Base64

--provisioning-template-ids PROVISIONING_TEMPLATE_IDS IDs of associated provisioning

templates

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--provisioning-templates PROVISIONING_TEMPLATE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--release-name RELEASE NAME

--title TITLE Operating system title

-h, --help Print help

Option details:

Following parameters accept format defined by its schema (bold are required):

--os-parameters-attributes "name=string\,value=string, ... "

2.45. HAMMER OSTREE-BRANCH

Manipulate ostree branches

Usage:

hammer ostree-branch [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show an ostree branch list List ostree branches

Options:

-h, --help Print help

2.45.1, hammer ostree-branch info

Show an ostree branch

Usage:

hammer ostree-branch info [OPTIONS]

Options:

--id ID An ostree branch identifier
--name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.45.2. hammer ostree-branch list

List ostree_branches

Usage:

hammer ostree-branch list [OPTIONS]

Options

--content-view CONTENT VIEW NAME Content view name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT VIEW ID Content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--content-view-version-id CONTENT_VIEW_VERSION_ID Content view version identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT ID

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS Ids to filter content by

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID
--search SEARCH Search string

-h, --help Print help

2.46. HAMMER PACKAGE

Manipulate packages

Usage:

hammer package [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a package list List packages

Options:

-h, --help Print help

2.46.1. hammer package info

Show a package

Usage:

hammer package info [OPTIONS]

Options:

--id ID A package identifier
--name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.46.2. hammer package list

List packages

Usage: hammer package list [OPTIONS] Options: --available-for AVAILABLE FOR Return packages that can be added to the specified object. Only the value 'content_view_version' is supported. --content-view CONTENT_VIEW_NAME Content view name to search by --content-view-filter CONTENT_VIEW_FILTER_NAME Name to search by --content-view-filter-id CONTENT VIEW FILTER ID Filter identifier --content-view-id CONTENT VIEW ID Content view numeric identifier --content-view-version CONTENT VIEW VERSION VERSION Content view version number --content-view-version-id CONTENT VIEW VERSION ID Content view version identifier --environment ENVIRONMENT NAME Lifecycle environment name to search by --environment-id ENVIRONMENT ID --full-result FULL_RESULT Whether or not to show all results One of true/false, yes/no, 1/0. Host name --host HOST NAME --host-id HOST ID --ids IDS Package identifiers to filter content by Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID --organization-label ORGANIZATION LABEL Organization label to search by --packages-restrict-applicable PACKAGES RESTRICT APPLICABLE Return packages that are applicable to one or more hosts (defaults to true If host_id is specified) One of true/false, yes/no, 1/0. --packages-restrict-latest PACKAGES RESTRICT LATEST Return only the latest version of each package One of true/false, yes/no, 1/0. --packages-restrict-upgradable PACKAGES_RESTRICT_UPGRADABLE Return packages that are upgradable on one or more hosts One of true/false, yes/no, 1/0. --page PAGE Page number, starting at 1 --per-page PER_PAGE Number of results per page to return --product PRODUCT NAME

--repository-id REPOSITORY_ID

--repository REPOSITORY NAME

--search SEARCH

--product-id PRODUCT ID

-h, --help

Product name to search by Product numeric identifier

Repository name to search by

Repository ID

Search string

Print help

2.47. HAMMER PACKAGE-GROUP

Manipulate package groups

hammer package-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a package group list List package_groups

Options:

-h, --help Print help

2.47.1. hammer package-group info

Show a package group

Usage:

hammer package-group info [OPTIONS]

Options:

--id ID A package group identifier --name NAME Name to search by

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.47.2. hammer package-group list

List package_groups

Usage:

hammer package-group list [OPTIONS]

Options:

--content-view CONTENT VIEW NAME Content view name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT VIEW ID Content view numeric identifier

 $\hbox{--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number} \\$

--content-view-version-id CONTENT_VIEW_VERSION_ID
Content view version identifier

--environment ENVIRONMENT_NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT_ID

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS Ids to filter content by

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID
--search SEARCH Search string

-h, --help Print help

2.48. HAMMER PARTITION-TABLE

Manipulate partition tables

Usage:

hammer partition-table [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

create Create a partition table
delete Delete a partition table
dump View partition table content

info Show a partition table list List all partition tables

remove-operatingsystem Disassociate an operating system

update Update a partition table

Options:

-h, --help Print help

2.48.1. hammer partition-table add-operatingsystem

Associate an operating system

Usage:

hammer partition-table add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Partition table name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help Print help

2.48.2. hammer partition-table create

Create a partition table

Usage:

hammer partition-table create [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file LAYOUT Path to a file that contains the partition layout

--host-ids HOST_IDS Array of host IDs to associate with the partition table

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location LOCATION NAME

Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED

Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the partition table

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--os-family OS_FAMILY

--snippet SNIPPET One of true/false, yes/no, 1/0.

-h, --help Print help

2.48.3. hammer partition-table delete

Delete a partition table

Usage:

hammer partition-table delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Partition table name

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.48.4. hammer partition-table dump

View partition table content

Usage:

hammer partition-table dump [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Partition table name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.48.5. hammer partition-table info

Show a partition table

Usage:

hammer partition-table info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Partition table name

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title -h, --help Print help

2.48.6. hammer partition-table list

List all partition tables

Usage:

hammer partition-table list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

default Values: true, false

family string
layout text
location string
location id integer

locked Values: true, false

name string organization string organization_id integer

snippet Values: true, false

template text vendor string

2.48.7. hammer partition-table remove-operatingsystem

Disassociate an operating system

Usage:

hammer partition-table remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Partition table name

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM_ID

-h, --help Print help

2.48.8. hammer partition-table update

Update a partition table

Usage:

hammer partition-table update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file LAYOUT Path to a file that contains the partition layout

--host-ids HOST_IDS Array of host IDs to associate with the partition table

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-titles HOSTGROUP_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Partition table name

--new-name NEW NAME

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the partition table

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

 --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--os-family OS_FAMILY

--snippet SNIPPET One of true/false, yes/no, 1/0.

-h, --help Print help

2.49. HAMMER PING

Get the status of the server

Usage:

hammer ping [OPTIONS]

Options:

-h, --help Print help

2.50. HAMMER POLICY

Manipulate policies

Usage:

hammer policy [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a Policy
delete Delete a Policy
info Show a Policy
list List Policies

update Update a Policy

Options:

-h, --help Print help

2.50.1. hammer policy create

Create a Policy

Usage:

hammer policy create [OPTIONS]

Options:

--cron-line CRON_LINE Policy schedule cron line (only if period == "custom")

--day-of-month DAY_OF_MONTH Policy schedule day of month (only if period ==

"monthly")

--deploy-by DEPLOY_BY

How the policy should be deployed

Possible value(s): 'puppet', 'ansible', 'manual'

--description DESCRIPTION Policy description
--host-ids HOST IDS Apply policy to hosts

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-ids HOSTGROUP_IDS Apply policy to host groups

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location LOCATION_NAME Name to search by

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Policy name

--organization ORGANIZATION_NAME Name to search by --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--period PERIOD Policy schedule period (weekly, monthly, custom)
--scap-content SCAP CONTENT TITLE SCAP content title

--scap-content-id SCAP CONTENT ID

--scap-content-profile-id SCAP_CONTENT_PROFILE_ID Policy SCAP content profile ID

--tailoring-file TAILORING_FILE_NAME Tailoring file name

--tailoring-file-id TAILORING FILE ID

--tailoring-file-profile-id TAILORING_FILE_PROFILE ID Tailoring file profile ID

--weekday WEEKDAY Policy schedule weekday (only if period == "weekly")

-h, --help Print help

2.50.2. hammer policy delete

Delete a Policy

Usage:

hammer policy delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.50.3. hammer policy info

Show a Policy

Usage:

hammer policy info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.50.4. hammer policy list

List Policies

Usage:

hammer policy list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'

- $\hbox{--organization-title ORGANIZATION_TITLE\ Organization\ title}$
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

content string location string

location_id integer
name string
organization organization_id integer
profile string
tailoring_file_profile string

2.50.5. hammer policy update

Update a Policy

Usage:

hammer policy update [OPTIONS]

Options:

--cron-line CRON_LINE Policy schedule cron line (only if period == "custom")
--day-of-month DAY_OF_MONTH Policy schedule day of month (only if period ==

"monthly")

--deploy-by DEPLOY_BY

How the policy should be deployed Possible value(s): 'puppet', 'ansible', 'manual'

--description DESCRIPTION Policy description
--host-ids HOST_IDS Apply policy to hosts

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroup-ids HOSTGROUP_IDS

OS Apply policy to host groups
Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hostgroups HOSTGROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--hosts HOST_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--id ID

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Policy name

--new-name NEW_NAME Policy name

--organization ORGANIZATION_NAME Name to search by --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION NAMES Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters Policy schedule period (weekly, monthly, custom)

--period PERIOD Policy schedule period (weekly

--scap-content SCAP_CONTENT_TITLE SCAP content title

--scap-content-id SCAP_CONTENT_ID

--scap-content-profile-id SCAP_CONTENT_PROFILE_ID Policy SCAP content profile ID

--tailoring-file TAILORING FILE NAME Tailoring file name

--tailoring-file-id TAILORING FILE ID

--tailoring-file-profile-id TAILORING FILE PROFILE ID Tailoring file profile ID

--weekday WEEKDAY Policy schedule weekday (only if period == "weekly")

-h, --help Print help

2.51. HAMMER PRODUCT

Manipulate products

Usage:

hammer product [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a product
delete Destroy a product
info Show a product
list List products

remove-sync-plan Delete assignment sync plan and product

set-sync-plan Assign sync plan to product synchronize Sync all repositories for a product

update Updates a product

Options:

-h, --help Print help

2.51.1. hammer product create

Create a product

Usage:

hammer product create [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID Gpg key numeric identifier

--label LABEL

--name NAME Product name

--organization-label ORGANIZATION_LABEL Organization label to search by

--ssl-ca-cert-id SSL_CA_CERT_ID Idenifier of the SSL CA Cert

--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert

--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key

--sync-plan SYNC_PLAN_NAME Sync plan name to search by

--sync-plan-id SYNC_PLAN_ID Sync plan numeric identifier

-h, --help Print help

2.51.2. hammer product delete

Destroy a product

Usage:

hammer product delete [OPTIONS]

Options:

--id ID Product numeric identifier

--name NAME Product name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.51.3. hammer product info

Show a product

Usage:

hammer product info [OPTIONS]

Options:

--id ID Product numeric identifier

--name NAME Product name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.51.4. hammer product list

List products

Usage:

hammer product list [OPTIONS]

Options:

--available-for AVAILABLE FOR

Interpret specified object to return only Products that

can be associated

With specified object. Only 'sync_plan' is supported.

--custom CUSTOM Return custom products only

One of true/false, yes/no, 1/0.

--enabled ENABLED Return enabled products only

One of true/false, yes/no, 1/0.

--full-result FULL_RESULT

Whether or not to show all results

One of true/false, yes/no, 1/0.

--include-available-content INCLUDE_AVAILABLE_CONTENT Whether to include available content

attribute in results

One of true/false, yes/no, 1/0.

--name NAME Filter products by name

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--redhat-only REDHAT_ONLY Return Red Hat (non-custom) products only

One of true/false, yes/no, 1/0.

--search SEARCH Search string

--subscription SUBSCRIPTION_NAME Subscription name to search by

--subscription-id SUBSCRIPTION_ID Subscription identifier

--sync-plan SYNC_PLAN_NAME Sync plan name to search by --sync-plan-id SYNC_PLAN_ID Sync plan numeric identifier

-h, --help Print help

2.51.5. hammer product remove-sync-plan

Delete assignment sync plan and product

Usage:

hammer product remove-sync-plan [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID Gpg key numeric identifier

--id ID Product numeric identifier

--name NAME Product name to search by
--new-name NEW NAME Product name

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--ssl-ca-cert-id SSL CA CERT ID Idenifier of the SSL CA Cert

--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert

--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key

-h, --help Print help

2.51.6. hammer product set-sync-plan

Assign sync plan to product

Usage:

hammer product set-sync-plan [OPTIONS]

Options:

--gpg-key GPG_KEY_NAME Name to search by --gpg-key-id GPG_KEY_ID Gpg key numeric identifier

--id ID Product numeric identifier

--name NAME Product name to search by

--new-name NEW_NAME Product name

- --organization-label ORGANIZATION_LABEL Organization label to search by
- --ssl-ca-cert-id SSL CA CERT ID Idenifier of the SSL CA Cert
- --ssl-client-cert-id SSL CLIENT CERT ID Identifier of the SSL Client Cert
- --ssl-client-key-id SSL_CLIENT_KEY_ID $\,$ Identifier of the SSL Client Key
- --sync-plan SYNC PLAN NAME Sync plan name to search by
- --sync-plan-id SYNC PLAN ID Sync plan numeric identifier
- -h, --help Print help

2.51.7. hammer product synchronize

Sync all repositories for a product

Usage:

hammer product synchronize [OPTIONS]

Options:

--async Do not wait for the task

--id ID Product ID

--name NAME Product name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.51.8. hammer product update

Updates a product

Usage:

hammer product update [OPTIONS]

Options:

--description DESCRIPTION Product description
--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID Gpg key numeric identifier

--id ID Product numeric identifier

--name NAME Product name to search by

--new-name NEW_NAME Product name

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--ssl-ca-cert-id SSL_CA_CERT_ID Idenifier of the SSL CA Cert

--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert

 $\hbox{--ssl-client-key-id SSL_CLIENT_KEY_ID} \quad \hbox{Identifier of the SSL Client Key}$

--sync-plan SYNC_PLAN_NAME Sync plan name to search by

--sync-plan-id SYNC PLAN ID Sync plan numeric identifier

-h, --help Print help

2.52. HAMMER PROXY

Manipulate smart proxies

Usage:

hammer proxy [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

content Manage the capsule content

create Create a capsule delete Delete a capsule

import-classes Import puppet classes from puppet Capsule

info Show a capsule list List all capsules

refresh-features Refresh capsule features

update Update a capsule

Options:

-h, --help Print help

2.52.1. hammer proxy content

Manage the capsule content

Usage:

hammer proxy content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-lifecycle-environment Add lifecycle environments to the capsule

available-lifecycle-environments List the lifecycle environments not attached to the capsule

cancel-synchronization Cancel running capsule synchronization info Get current capsule synchronization status

lifecycle-environments List the lifecycle environments attached to the capsule remove-lifecycle-environment Remove lifecycle environments from the capsule

synchronization-status Get current capsule synchronization status

synchronize Synchronize the content to the capsule

Options:

-h, --help Print help

2.52.1.1. hammer proxy content add-lifecycle-environment

Add lifecycle environments to the capsule

Usage:

hammer proxy content add-lifecycle-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--id ID Id of the capsule

 $\hbox{--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME\ Lifecycle\ environment\ name\ to\ search}$

by ..

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

-h, --help Print help

2.52.1.2. hammer proxy content available-lifecycle-environments

List the lifecycle environments not attached to the capsule

Usage:

hammer proxy content available-lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.52.1.3. hammer proxy content cancel-synchronization

Cancel running capsule synchronization

Usage:

hammer proxy content cancel-synchronization [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

-h, --help Print help

2.52.1.4. hammer proxy content info

Get current capsule synchronization status

Usage:

hammer proxy content info [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.52.1.5. hammer proxy content lifecycle-environments

List the lifecycle environments attached to the capsule

Usage:

hammer proxy content lifecycle-environments [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.52.1.6. hammer proxy content remove-lifecycle-environment

Remove lifecycle environments from the capsule

Usage:

hammer proxy content remove-lifecycle-environment [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--id ID Id of the capsule

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

-h, --help Print help

2.52.1.7. hammer proxy content synchronization-status

Get current capsule synchronization status

Usage:

hammer proxy content synchronization-status [OPTIONS]

Options:

--id ID Id of the capsule

--name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.52.1.8. hammer proxy content synchronize

Synchronize the content to the capsule

Usage:

hammer proxy content synchronize [OPTIONS]

Options:

--async Do not wait for the task

--environment ENVIRONMENT_NAME Lifecycle environment name to search by (--environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --lifecycle-environment-id instead)

--id ID Id of the capsule

--lifecycle-environment LIFECYCLE_ENVIRONMENT_NAME Lifecycle environment name to search by

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID
--name NAME Name to search by
--organization NAME Organization name
--organization-id ID Organization ID

--skip-metadata-check SKIP_METADATA_CHECK Skip metadata check on each repository on the capsule

One of true/false, yes/no, 1/0.

-h, --help Print help

2.52.2. hammer proxy create

Create a capsule

Usage:

hammer proxy create [OPTIONS]

Options

--download-policy DOWNLOAD_POLICY Download Policy of the capsule, must be one of immediate, on_demand,

Background, inherit

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--url URL

-h, --help Print help

2.52.3. hammer proxy delete

Delete a capsule

Usage:

hammer proxy delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.52.4. hammer proxy import-classes

Import puppet classes from puppet Capsule

Usage:

hammer proxy import-classes [OPTIONS]

Options:

--dryrun Do not run the import

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--except EXCEPT Optional comma-delimited string containing either 'new',

'updated', or 'obsolete' that is used to limit the imported

Puppet classes

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by

--organization ORGANIZATION_NAME
--organization-id ORGANIZATION_ID
--organization-title ORGANIZATION_TITLE
Organization title
Organization title

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

-h, --help Print help

2.52.5. hammer proxy info

Show a capsule

Usage:

hammer proxy info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.52.6. hammer proxy list

List all capsules

Usage:

hammer proxy list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

feature string
location string
location_id integer
name string
organization string
organization_id integer
url string

Search / Order fields:

feature string
location string
location_id integer
name string
organization string
organization_id integer
url string

2.52.7. hammer proxy refresh-features

Refresh capsule features

Usage:

hammer proxy refresh-features [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.52.8. hammer proxy update

Update a capsule

Usage:

hammer proxy update [OPTIONS]

Options:

--download-policy DOWNLOAD_POLICY Download Policy of the capsule, must be one of immediate, on_demand,

Background, inherit

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --location-title LOCATION_TITLE Location title
- --location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --name NAME Name to search by
- --new-name NEW NAME
- --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION_ID Organization ID
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--url URL

-h, --help Print help

2.53. HAMMER PUPPET-CLASS

Search puppet modules

Usage:

hammer puppet-class [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a Puppet class list List all Puppet classes

sc-params List all smart class parameters

smart-variables List all smart variables

Options:

-h, --help Print help

2.53.1. hammer puppet-class info

Show a Puppet class

Usage:

hammer puppet-class info [OPTIONS]

Options:

--environment ENVIRONMENT NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--host HOST NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--id ID ID of Puppet class

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Puppet class name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

-h, --help Print help

2.53.2. hammer puppet-class list

List all Puppet classes

Usage:

hammer puppet-class list [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--host HOST_NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--puppet-environment PUPPET ENVIRONMENT NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID
--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

config_group string environment string host string hostgroup string key string location string name string organization string

2.53.3. hammer puppet-class sc-params

List all smart class parameters

Usage:

hammer puppet-class sc-params [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid duplicates Values: true, false

environment string key string

merge_default Values: true, false merge_overrides Values: true, false override Values: true, false

parameter string puppetclass string puppetclass_name string

2.53.4. hammer puppet-class smart-variables

List all smart variables

Usage:

hammer puppet-class smart-variables [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

key string

merge_default Values: true, false Values: true, false

override Values: true, false

parameter string puppetclass string

2.54. HAMMER PUPPET-ENVIRONMENT

Manipulate Puppet environments

Usage:

hammer puppet-environment [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an environment
delete Delete an environment
info Show an environment
list List all environments

sc-params List all smart class parameters

update Update an environment

Options:

-h, --help Print help

2.54.1. hammer puppet-environment create

Create an environment

Usage:

hammer puppet-environment create [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing

comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.54.2. hammer puppet-environment delete

Delete an environment

Usage:

hammer puppet-environment delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Puppet environment name
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.54.3. hammer puppet-environment info

Show an environment

Usage:

hammer puppet-environment info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME Puppet environment name
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.54.4. hammer puppet-environment list

List all environments

Usage:

hammer puppet-environment list [OPTIONS]

Options:

--location LOCATION NAME Location name

- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request --puppet-class PUPPET CLASS NAME Puppet class name

--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

content_view string lifecycle_environment string location string

location string
location_id integer
name string
organization string
organization_id integer

Search / Order fields:

content_view string lifecycle_environment string

location string location_id integer name string organization organization_id integer

2.54.5. hammer puppet-environment sc-params

List all smart class parameters

Usage:

hammer puppet-environment sc-params [OPTIONS]

Options:

--environment ENVIRONMENT NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER PAGE Number of entries per request

--puppet-environment PUPPET ENVIRONMENT NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID
--search SEARCH Filter results

--show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge_default Values: true, false values: true, false

override Values: true, false

parameter string puppetclass string puppetclass_name string

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge_default Values: true, false merge_overrides Values: true, false override Values: true, false

parameter string puppetclass string puppetclass_name string

2.54.6. hammer puppet-environment update

Update an environment

Usage:

hammer puppet-environment update [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Puppet environment name

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.55. HAMMER PUPPET-MODULE

View Puppet Module details

Usage:

hammer puppet-module [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show a puppet module list List puppet_modules

Options:

-h, --help Print help

2.55.1. hammer puppet-module info

Show a puppet module

Usage:

hammer puppet-module info [OPTIONS]

Options:

--id ID A puppet module identifier --name NAME Name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by --repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID

-h, --help Print help

2.55.2. hammer puppet-module list

List puppet_modules

Usage:

hammer puppet-module list [OPTIONS]

Options:

--content-view CONTENT_VIEW_NAME Content view name to search by

--content-view-filter-id CONTENT_VIEW_FILTER_ID Filter identifier

--content-view-id CONTENT_VIEW_ID Content view numeric identifier

--content-view-version CONTENT_VIEW_VERSION_VERSION Content view version number

--environment ENVIRONMENT NAME Lifecycle environment name to search by

--environment-id ENVIRONMENT ID

--full-result FULL RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--ids IDS Ids to filter content by

Comma separated list of values. Values containing comma should

be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION_ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--repository REPOSITORY_NAME Repository name to search by

--repository-id REPOSITORY_ID Repository ID
--search SEARCH Search string

-h, --help Print help

2.56. HAMMER REALM

Manipulate realms

Usage:

hammer realm [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a realm
delete Delete a realm
info Show a realm
list List of realms
update Update a realm

Options:

-h, --help Print help

2.56.1, hammer realm create

Create a realm

Usage:

hammer realm create [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME The realm name, e.g. EXAMPLE.COM

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-proxy-id REALM_PROXY_ID Capsule ID to use within this realm

--realm-type REALM_TYPE Realm type, e.g. Red Hat Identity Management or Active

Directory

-h, --help Print help

2.56.2. hammer realm delete

Delete a realm

Usage:

hammer realm delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.56.3. hammer realm info

Show a realm

Usage:

hammer realm info [OPTIONS]

Options:

--id ID Numerical ID or realm name --location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.56.4. hammer realm list

List of realms

Usage:

hammer realm list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

location string
location_id integer
name string
organization string
organization_id integer
type string

2.56.5. hammer realm update

Update a realm

Usage:

hammer realm update [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Name to search by

--new-name NEW_NAME The realm name, e.g. EXAMPLE.COM

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--realm-proxy-id REALM_PROXY_ID Capsule ID to use within this realm

--realm-type REALM_TYPE Realm type, e.g. Red Hat Identity Management or Active

Directory

-h, --help Print help

2.57. HAMMER RECURRING-LOGIC

Recurring logic related actions

Usage:

hammer recurring-logic [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

cancel Cancel recurring logic info Show recurring logic details

list List recurring logics

Options:

-h, --help Print help

2.57.1. hammer recurring-logic cancel

Cancel recurring logic

Usage:

hammer recurring-logic cancel [OPTIONS]

Options:

--id ID ID of the recurring logic

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.57.2. hammer recurring-logic info

Show recurring logic details

Usage:

hammer recurring-logic info [OPTIONS]

Options:

--id ID ID of the recurring logic

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.57.3. hammer recurring-logic list

List recurring logics

Usage:

hammer recurring-logic list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

2.58. HAMMER REMOTE-EXECUTION-FEATURE

Manage remote execution features

Usage:

hammer remote-execution-feature [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show remote execution feature list List remote execution features update Update a job template

Options:

-h, --help Print help

2.58.1. hammer remote-execution-feature info

Show remote execution feature

Usage:

hammer remote-execution-feature info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.58.2. hammer remote-execution-feature list

List remote execution features

Usage:

hammer remote-execution-feature list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.58.3. hammer remote-execution-feature update

Update a job template

Usage:

hammer remote-execution-feature update [OPTIONS]

Options:

- --id ID
- --job-template-id JOB_TEMPLATE_ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --new-name NEW NAME
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.59. HAMMER REPORT

Browse and read reports

Usage:

hammer report [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete Delete a report info Show a report list List all reports

Options:

-h, --help Print help

2.59.1. hammer report delete

Delete a report

Usage:

hammer report delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --organization ORGANIZATION NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.59.2. hammer report info

Show a report

Usage:

hammer report info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.59.3. hammer report list

List all reports

Usage:

hammer report list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

- applied integer environment string
- eventful Values: true, false
- failed integer
 failed_restarts integer
 host string
 host_id integer
 hostgroup string
 hostgroup_fullname string
 hostgroup title string
- last_report datetime
- location string
- log text
- organization string origin string
- pending integer reported datetime

resource text restarted integer skipped integer

Search / Order fields: applied integer environment string

eventful Values: true, false

failed integer failed_restarts integer host string integer host_id hostgroup string hostgroup_fullname string hostgroup_title string last_report datetime location string log text organization string origin string pending integer

2.60. HAMMER REPORT-TEMPLATE

datetime

text

integer

integer

Manipulate report templates

Usage:

hammer report-template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

reported resource

restarted

skipped

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

clone Clone a template

create Create a report template delete Delete a report template dump View report content generate Generate report info Show a report template list List all report templates

report-data Downloads a generated report schedule Schedule generating of a report

update Update a report template

Options:

-h, --help Print help

2.60.1. hammer report-template clone

Clone a template

Usage:

hammer report-template clone [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by
- --new-name NEW NAME
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION TITLE Organization title
- -h, --help Print help

2.60.2. hammer report-template create

Create a report template

Usage:

hammer report-template create [OPTIONS]

Options:

- --audit-comment AUDIT_COMMENT
- --default DEFAULT Whether or not the template is added automatically to new organizations and

Locations

One of true/false, yes/no, 1/0.

--file LAYOUT Path to a file that contains the report template content --interactive, -i Open empty template in an \$EDITOR. Upload the result

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --location-title LOCATION TITLE Location title
- --location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--snippet SNIPPET One of true/false, yes/no, 1/0.

-h, --help Print help

2.60.3. hammer report-template delete

Delete a report template

Usage:

hammer report-template delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
 --name NAME Name to search by
- --organization ORGANIZATION_NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.60.4. hammer report-template dump

View report content

Usage:

hammer report-template dump [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.60.5. hammer report-template generate

Generate report

Usage:

hammer report-template generate [OPTIONS]

Options:

--gzip GZIP Compress the report uzing gzip

One of true/false, yes/no, 1/0.

--id ID

--inputs INPUTS Specify inputs

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

 $\hbox{--organization-title ORGANIZATION_TITLE\ Organization\ title}$

--path PATH Path to directory where downloaded content will be saved

-h, --help Print help

2.60.6. hammer report-template info

Show a report template

Usage:

hammer report-template info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.60.7. hammer report-template list

List all report templates

Usage:

hammer report-template list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

default Values: true, false

location string location id integer

locked Values: true, false

name string organization string organization_id integer

snippet Values: true, false

template text

2.60.8. hammer report-template report-data

Downloads a generated report

Usage:

hammer report-template report-data [OPTIONS]

Options:

--id ID

--job-id JOB_ID ID assigned to generation job by the schedule command

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--path PATH Path to directory where downloaded content will be saved

-h, --help Print help

2.60.9. hammer report-template schedule

Schedule generating of a report

Usage:

hammer report-template schedule [OPTIONS]

Options:

--gzip GZIP Compress the report using gzip

One of true/false, yes/no, 1/0.

--id ID

--inputs INPUTS Specify inputs

Comma-separated list of key=value.

JSON is acceptable and preferred way for complex parameters

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--mail-to MAIL_TO If set, scheduled report will be delivered via e-mail. Use ',' to

Separate multiple email addresses.

--name NAME Name to search by

--organization ORGANIZATION NAME Organization name

 --organization-title ORGANIZATION_TITLE Organization title

--path PATH Path to directory where downloaded content will be saved. Only

usable if wait is specified

--wait Turns a command to be active, wait for the result and download it right

away

-h, --help Print help

2.60.10. hammer report-template update

Update a report template

Usage:

hammer report-template update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--default DEFAULT Whether or not the template is added automatically to new

organizations and

Locations

One of true/false, yes/no, 1/0.

--file REPORT Path to a file that contains the report template content

--id ID

--interactive, -i Dump existing template and open it in an \$EDITOR. Update with the

result

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

--snippet SNIPPET

JSON is acceptable and preferred way for complex parameters

One of true/false, yes/no, 1/0.

-h, --help Print help

2.61. HAMMER REPOSITORY

Manipulate repositories

Usage:

hammer repository [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a custom repository delete Destroy a custom repository

export Export content from a repository to the configured directory

info Show a repository

list List of enabled repositories

remove-content Remove content from a repository

synchronize Sync a repository update Update a repository

upload-content Upload content into the repository

Options:

-h, --help Print help

2.61.1. hammer repository create

Create a custom repository

Usage:

hammer repository create [OPTIONS]

Options:

--checksum-type CHECKSUM_TYPE Checksum of the repository, currently 'sha1'

& 'sha256'

Are supported

--content-type CONTENT_TYPE Type of repo (either 'yum', 'deb', 'puppet',

'docker', or 'ostree')

Possible value(s): 'docker', 'file', 'ostree', 'puppet', 'yum'

--deb-architectures DEB_ARCHITECTURES Comma separated list of architectures to

be synched from deb-archive

--deb-components DEB_COMPONENTS Comma separated list of repo components

to be synched from deb-archive

--deb-releases DEB_RELEASES Comma separated list of releases to be synched

from deb-archive

--docker-tags-whitelist DOCKER_TAGS_WHITELIST Comma separated list of tags to sync

for Container Image repository

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--docker-upstream-name DOCKER_UPSTREAM_NAME Name of the upstream docker repository --download-policy DOWNLOAD POLICY Download policy for yum repos (either 'immediate', 'on demand', or 'background') Possible value(s): 'immediate', 'on_demand', 'background' Name to search by --gpg-key GPG KEY NAME --gpg-key-id GPG KEY ID Gpg key numeric identifier --ignorable-content IGNORABLE CONTENT List of content units to ignore while syncing a yum repository. Must be Subset of rpm,drpm,srpm,distribution,erratum Comma separated list of values. Values containing comma should be quoted or escaped with backslash. JSON is acceptable and preferred way for complex parameters --ignore-global-proxy IGNORE_GLOBAL_PROXY If true, will ignore the globally configured Capsule when syncing One of true/false, yes/no, 1/0. --label LABEL --mirror-on-sync MIRROR ON SYNC True if this repository when synced has to be mirrored from the source and Stale rpms removed One of true/false, yes/no, 1/0. --name NAME --organization ORGANIZATION NAME Organization name to search by --organization-id ORGANIZATION ID Organization ID --organization-label ORGANIZATION_LABEL Organization label to search by

'depth' value must be provided

--ostree-upstream-sync-policy OSTREE_UPSTREAM_SYNC_POLICY Policies for syncing upstream ostree repositories

Possible value(s): 'latest', 'all', 'custom'
--product PRODUCT_NAME
--product-id PRODUCT_ID
Product numeric identifier

--publish-via-http ENABLE Publish Via HTTP

One of true/false, yes/no, 1/0.

--ssl-ca-cert-id SSL_CA_CERT_ID Identifier of the SSL CA Cert
--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert
--ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key

--upstream-password UPSTREAM_PASSWORD Password of the upstream repository

user used for authentication

user used for authentication

--url URL Repository source url

SSL certificates are

Signed by a trusted CA One of true/false, yes/no, 1/0.

-h, --help Print help

2.61.2. hammer repository delete

Destroy a custom repository

Usage:

hammer repository delete [OPTIONS]

Options:

--id ID

--name NAME Repository name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

-h, --help Print help

2.61.3. hammer repository export

Export content from a repository to the configured directory

Usage:

hammer repository export [OPTIONS]

Options:

--async Do not wait for the task

One of true/false, yes/no, 1/0.

--id ID Repository identifier

--name NAME Repository name to search by

--organization-id ORGANIZATION ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

--since SINCE Optional date of last export (ex: 2010-01-01T12:00:00Z)

-h, --help Print help

2.61.4. hammer repository info

Show a repository

Usage:

hammer repository info [OPTIONS]

Options:

--id ID Repository ID

--name NAME Repository name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier

-h, --help Print help

2.61.5. hammer repository list

List of enabled repositories

Usage:

hammer repository list [OPTIONS]

Options:

--available-for AVAILABLE FOR

Interpret specified object to return only Repositories

that can be

Associated with specified object. Only 'content view' &

'content view version' are supported.

--content-type CONTENT TYPE

Limit to only repositories of this type Possible value(s): 'docker', 'file', 'ostree', 'puppet', 'yum'

--content-view CONTENT VIEW NAME

Content view name to search by

--content-view-id CONTENT VIEW ID

Content view numeric identifier

--content-view-version CONTENT VIEW VERSION VERSION Content view version number --content-view-version-id CONTENT_VIEW_VERSION_ID
Content view version identifier

--deb DEB NAME

Name to search by A deb identifier

--deb-id DEB ID --description DESCRIPTION

Description of the repository

--environment ENVIRONMENT NAME

Lifecycle environment name to search by (--

environment is deprecated: Use --lifecycle-environment instead)

--environment-id ENVIRONMENT ID

(--environment-id is deprecated: Use --lifecycle-

environment-id instead)

--erratum-id ERRATUM ID

Id of an erratum to find repositories that contain the

erratum

--file-id FILE ID

Id of a file to find repositories that contain the file

--full-result FULL RESULT

Whether or not to show all results

One of true/false, yes/no, 1/0.

--label LABEL

Label of the repository

--library LIBRARY

Show repositories in Library and the default content view

One of true/false, yes/no, 1/0.

--lifecycle-environment LIFECYCLE ENVIRONMENT NAME Lifecycle environment name to search

--lifecycle-environment-id LIFECYCLE_ENVIRONMENT_ID

Name of the repository

--name NAME --order ORDER

Sort field and order, eq. 'id DESC'

--organization ORGANIZATION NAME

Organization name to search by

--organization-id ORGANIZATION ID

Organization ID

--organization-label ORGANIZATION LABEL

Organization label to search by

--ostree-branch OSTREE BRANCH NAME

Name to search by

--ostree-branch-id OSTREE BRANCH ID

An ostree branch identifier

--page PAGE

Page number, starting at 1

--per-page PER_PAGE --product PRODUCT NAME Number of results per page to return Product name to search by

--product-id PRODUCT ID

Product numeric identifier

--rpm-id RPM ID

ld of a rpm package to find repositories that contain the rpm

Search string --search SEARCH

-h, --help

Print help

2.61.6. hammer repository remove-content

Remove content from a repository

Usage:

hammer repository remove-content [OPTIONS]

Options:

--id ID Repository ID

--ids IDS Array of content ids to remove

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Repository name to search by

--organization ORGANIZATION_NAME Organization name to search by --organization-id ORGANIZATION_ID Organization ID to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by Product-id PRODUCT_ID Product numeric identifier

--sync-capsule SYNC_CAPSULE Whether or not to sync an external capsule after upload.

Default: true

One of true/false, yes/no, 1/0.

-h, --help Print help

2.61.7. hammer repository synchronize

Sync a repository

Usage:

hammer repository synchronize [OPTIONS]

Options:

--async Do not wait for the task

--id ID Repository ID

--incremental INCREMENTAL Perform an incremental import

One of true/false, yes/no, 1/0.

--name NAME Repository name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT ID Product numeric identifier

--skip-metadata-check SKIP_METADATA_CHECK Force sync even if no upstream changes are detected. Only used with yum

Repositories.

One of true/false, yes/no, 1/0.

--source-url SOURCE_URL Temporarily override feed URL for sync

--validate-contents VALIDATE_CONTENTS Force a sync and validate the checksums of all content. Only used with yum

Repositories.

One of true/false, yes/no, 1/0.

-h, --help Print help

2.61.8. hammer repository update

Update a repository

Usage:

hammer repository update [OPTIONS]

Options:

--checksum-type CHECKSUM_TYPE Checksum of the repository, currently 'sha1'

& 'sha256'

Are supported

--deb-architectures DEB ARCHITECTURES Comma separated list of architectures to

be synched from deb-archive

--deb-components DEB_COMPONENTS Comma separated list of repo components

to be synched from deb-archive

--deb-releases DEB_RELEASES Comma separated list of releases to be synched

from deb-archive

--docker-digest DIGEST Container Image manifest digest

--docker-tag TAG Optional custom Container Image tag to specify the value

of the Docker digest

--docker-tags-whitelist DOCKER_TAGS_WHITELIST Comma separated list of tags to sync

for Container Image repository

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--docker-upstream-name DOCKER_UPSTREAM_NAME Name of the upstream docker repository

--download-policy DOWNLOAD_POLICY Download policy for yum repos (either

'immediate',

'on_demand', or 'background')

Possible value(s): 'immediate', 'on_demand', 'background'

--gpg-key GPG_KEY_NAME Name to search by
--gpg-key-id GPG_KEY_ID Gpg key numeric identifier

--id ID Repository ID

--ignorable-content IGNORABLE_CONTENT List of content units to ignore while syncing

a yum repository. Must be

Subset of rpm,drpm,srpm,distribution,erratum

Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--ignore-global-proxy IGNORE_GLOBAL_PROXY If true, will ignore the globally configured Capsule when syncing

One of true/false, yes/no, 1/0.

--mirror-on-sync MIRROR_ON_SYNC True if this repository when synced has to be mirrored from the source and

Stale rpms removed

One of true/false, yes/no, 1/0.

--name NAME Repository name to search by

--new-name NEW_NAME

--organization ORGANIZATION_NAME Organization name to search by
--organization-id ORGANIZATION_ID Organization ID to search by
--organization-label ORGANIZATION_LABEL Organization label to search by

'depth' value must be provided

--ostree-upstream-sync-policy OSTREE_UPSTREAM_SYNC_POLICY Policies for syncing upstream ostree repositories

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier

--publish-via-http ENABLE Publish Via HTTP
One of true/false, yes/no, 1/0.

--ssl-ca-cert-id SSL_CA_CERT_ID Idenifier of the SSL CA Cert

--ssl-client-cert-id SSL_CLIENT_CERT_ID Identifier of the SSL Client Cert --ssl-client-key-id SSL_CLIENT_KEY_ID Identifier of the SSL Client Key

--upstream-password UPSTREAM_PASSWORD Password of the upstream repository

user used for authentication

user used for authentication

--url URL Repository source url

SSL certifcates are

Signed by a trusted CA One of true/false, yes/no, 1/0.

-h, --help Print help

2.61.9. hammer repository upload-content

Upload content into the repository

Usage:

hammer repository upload-content [OPTIONS]

Options:

--id ID Repository ID

--name NAME Repository name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--path PATH Upload file, directory of files, or glob of files as content for a

repository.

Globs must be escaped by single or double quotes

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier

-h, --help Print help

2.62. HAMMER REPOSITORY-SET

Manipulate repository sets on the server

Usage:

hammer repository-set [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

available-repositories Get list of available repositories for the repository set

disable Disable a repository from the set enable Enable a repository from the set info Get info about a repository set

list List repository sets.

Options:

-h, --help Print help

2.62.1. hammer repository-set available-repositories

Get list of available repositories for the repository set

Usage:

hammer repository-set available-repositories [OPTIONS]

Options:

--id ID ID of the repository set

--name NAME Repository set name to search by

--organization ORGANIZATION NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by Product-id PRODUCT_ID Product numeric identifier

-h, --help Print help

2.62.2. hammer repository-set disable

Disable a repository from the set

Usage:

hammer repository-set disable [OPTIONS]

Options:

--basearch BASEARCH
--id ID

ID of the repository set to disable

--name NAME Repository set name to search by

--organization-label ORGANIZATION LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier
--releasever RELEASEVER Releasever to disable

-h, --help Print help

2.62.3. hammer repository-set enable

Enable a repository from the set

Usage:

hammer repository-set enable [OPTIONS]

Options:

--basearch BASEARCH Basearch to enable
--id ID ID of the repository set to enable

--name NAME Repository set name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by
--product-id PRODUCT_ID Product numeric identifier
--releasever RELEASEVER Releasever to enable

-h, --help Print help

2.62.4. hammer repository-set info

Get info about a repository set

Usage:

hammer repository-set info [OPTIONS]

Options:

--id ID ID of the repository set

--name NAME Repository set name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--product PRODUCT_NAME Product name to search by --product-id PRODUCT_ID Product numeric identifier

-h, --help Print help

2.62.5. hammer repository-set list

List repository sets.

Usage:

hammer repository-set list [OPTIONS]

Options:

--enabled ENABLED If true, only return repository sets that have been enabled.

Defaults to

False

One of true/false, yes/no, 1/0.

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--name NAME Repository set name to search on --order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE
--product PRODUCT_NAME
--product-id PRODUCT_ID

Number of results per page to return
Product name to search by
Product numeric identifier

--search SEARCH Search string

--with-active-subscription WITH_ACTIVE_SUBSCRIPTION If true, only return repository sets that are

associated with an active

Subscriptions

One of true/false, yes/no, 1/0.

-h, --help Print help

2.63. HAMMER ROLE

Manage user roles

Usage:

hammer role [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

clone Clone a role
create Create a role
delete Delete a role
filters List all filters
info Show a role
list List all roles
update Update a role

Options:

-h, --help Print help

2.63.1. hammer role clone

Clone a role

Usage:

hammer role clone [OPTIONS]

Options:

--description DESCRIPTION Role description

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME User role name

--new-name NEW_NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.63.2. hammer role create

Create a role

Usage:

hammer role create [OPTIONS]

Options:

--description DESCRIPTION Role description
--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --name NAME
- --organization ORGANIZATION_NAME Organization name
 --organization-id ORGANIZATION ID Organization ID
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.63.3. hammer role delete

Delete a role

Usage:

hammer role delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
 --name NAME User role name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.63.4. hammer role filters

List all filters

Usage:

hammer role filters [OPTIONS]

Options:

--id ID User role id

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title --name NAME User role name

--order ORDER Sort field and order, eg. 'id DESC' --organization ORGANIZATION NAME Organization name Organization ID --organization-id ORGANIZATION_ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

Number of entries per request --per-page PER_PAGE

-h, --help Print help

2.63.5. hammer role info

Show a role

Usage:

hammer role info [OPTIONS]

Options:

- --description DESCRIPTION
- --id ID
- --location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title --name NAME User role name

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.63.6. hammer role list

List all roles

hammer role list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

Sort field and order, eg. 'id DESC' --order ORDER --organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

builtin Values: true, false

description text name string permission string

2.63.7. hammer role update

Update a role

Usage:

hammer role update [OPTIONS]

Options:

--description DESCRIPTION Role description

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME User role name

--new-name NEW NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.64. HAMMER SC-PARAM

Manipulate smart class parameters

Usage:

hammer sc-param [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-matcher Create an override value for a specific smart variable

info Show a smart class parameter list List all smart class parameters

remove-matcher Delete an override value for a specific smart variable

update Update a smart class parameter

Options:

-h, --help Print help

2.64.1. hammer sc-param add-matcher

Create an override value for a specific smart variable

Usage:

hammer sc-param add-matcher [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --match MATCH Override match

--omit OMIT Satellite will not send this parameter in classification output,

replaces

Use_puppet_default

One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME
--organization-id ORGANIZATION_ID
--organization-title ORGANIZATION_TITLE
--puppet-class PUPPET_CLASS_NAME
--puppet-class-id PUPPET CLASS_ID

Organization name
Organization name
Organization name
Organization name
Organization name
ID of puppet class

--smart-class-parameter SMART CLASS PARAMETER NAME Smart class parameter name

--smart-class-parameter-id SMART_CLASS_PARAMETER_ID

--use-puppet-default USE_PUPPET_DEFAULT Deprecated, please use omit

One of true/false, yes/no, 1/0.

--value VALUE Override value, required if omit is false

-h, --help Print help

2.64.2. hammer sc-param info

Show a smart class parameter

Usage:

hammer sc-param info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Smart class parameter name --organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

2.64.3. hammer sc-param list

List all smart class parameters

Usage:

hammer sc-param list [OPTIONS]

Options:

--environment ENVIRONMENT NAME Environment name (--environment is deprecated:

Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--host HOST NAME Host name

--host-id HOST_ID

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title
--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

environment string key string

merge default Values: true, false

merge_overrides Values: true, false override Values: true, false parameter string puppetclass string puppetclass_name string

2.64.4. hammer sc-param remove-matcher

Delete an override value for a specific smart variable

Usage:

hammer sc-param remove-matcher [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--puppet-class PUPPET_CLASS_NAME Puppet class name
--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--smart-class-parameter SMART_CLASS_PARAMETER_NAME Smart class parameter name

--smart-class-parameter-id SMART_CLASS_PARAMETER_ID

-h, --help Print help

2.64.5. hammer sc-param update

Update a smart class parameter

Usage:

hammer sc-param update [OPTIONS]

Options:

--avoid-duplicates AVOID_DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value VALUE Value to use when there is no match

--description DESCRIPTION Description of smart class

--hidden-value HIDDEN_VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--merge-default MERGE_DEFAULT Include default value when merging all matching values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash type)

One of true/false, yes/no, 1/0.

--name NAME Smart class parameter name

--omit OMIT Satellite will not send this parameter in classification output. Puppet

Will use the value defined in the Puppet manifest for this parameter

One of true/false, yes/no, 1/0.

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

--override OVERRIDE Override this parameter

One of true/false, yes/no, 1/0.

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--parameter-type PARAMETER_TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

--path PATH The order in which values are resolved --puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--required REQUIRED This parameter is required

One of true/false, yes/no, 1/0.

--use-puppet-default USE_PUPPET_DEFAULT Deprecated, please use omit

One of true/false, yes/no, 1/0.

Possible value(s): 'regexp', 'list', "

-h, --help Print help

2.65. HAMMER SCAP-CONTENT

Manipulate SCAP contents

Usage:

hammer scap-content [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create SCAP content delete Deletes an SCAP content

download Download an SCAP content as XML

info Show an SCAP content list List SCAP contents

update Update an SCAP content

Options:

-h, --help Print help

2.65.1. hammer scap-content create

Create SCAP content

Usage:

hammer scap-content create [OPTIONS]

Options:

--location LOCATION_NAME Name to search by

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted

or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--original-filename ORIGINAL FILENAME Original file name of the XML file

--scap-file SCAP_FILE SCAP content file --title TITLE SCAP content name

-h, --help Print help

2.65.2. hammer scap-content delete

Deletes an SCAP content

Usage:

hammer scap-content delete [OPTIONS]

Options:

--id ID

--location LOCATION NAME Name to search by

--location-id LOCATION ID

--organization ORGANIZATION NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--title TITLE SCAP content title

-h, --help Print help

2.65.3. hammer scap-content download

Download an SCAP content as XML

Usage:

hammer scap-content download [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Name to search by

--location-id LOCATION ID

--organization ORGANIZATION_NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--path PATH Path to directory where downloaded file will be saved

--title TITLE SCAP content title

-h, --help Print help

2.65.4. hammer scap-content info

Show an SCAP content

Usage:

hammer scap-content info [OPTIONS]

Options:

- --id ID
- --location-id LOCATION ID
- --organization ORGANIZATION_NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID
- --title TITLE SCAP content title
- -h, --help Print help

2.65.5. hammer scap-content list

List SCAP contents

Usage:

hammer scap-content list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'

- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

created_at datetime filename string location string location_id integer organization_id integer

title string

2.65.6. hammer scap-content update

Update an SCAP content

Usage:

hammer scap-content update [OPTIONS]

Options:

--id ID

--location-id LOCATION_ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--new-title NEW TITLE SCAP content name

--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--original-filename ORIGINAL FILENAME Original file name of the XML file

--scap-file SCAP_FILE SCAP content file --title TITLE SCAP content title

-h, --help Print help

2.66. HAMMER SETTINGS

Change server settings

Usage:

hammer settings [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

list List all settings set Update a setting

Options:

-h, --help Print help

2.66.1. hammer settings list

List all settings

Usage:

hammer settings list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization-id $ORGANIZATION_ID$ Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields: description text name string

2.66.2. hammer settings set

Update a setting

Usage:

hammer settings set [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Setting name

--organization-title ORGANIZATION_TITLE Organization title

--value VALUE

-h, --help Print help

2.67. HAMMER SHELL

Interactive shell

Usage:

hammer shell [OPTIONS]

Options:

-h, --help Print help

2.68. HAMMER SMART-VARIABLE

Manipulate smart variables

Usage:

hammer smart-variable [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-matcher Create an override value for a specific smart variable

create Create a smart variable delete Delete a smart variable info Show a smart variable list List all smart variables

remove-matcher Delete an override value for a specific smart variable

update Update a smart variable

Options:

-h, --help Print help

2.68.1. hammer smart-variable add-matcher

Create an override value for a specific smart variable

Usage:

hammer smart-variable add-matcher [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --match MATCH Override match

--omit OMIT Satellite will not send this parameter in classification output, replaces

Use_puppet_default

One of true/false, yes/no, 1/0.

--organization ORGANIZATION_NAME
 --organization-id ORGANIZATION_ID
 --organization-title ORGANIZATION_TITLE
 Organization title

--smart-variable SMART_VARIABLE_VARIABLE Smart variable name

--smart-variable-id SMART VARIABLE ID

--use-puppet-default USE PUPPET DEFAULT Deprecated, please use omit

One of true/false, yes/no, 1/0.

--value VALUE Override value, required if omit is false

-h, --help Print help

2.68.2. hammer smart-variable create

Create a smart variable

Usage:

hammer smart-variable create [OPTIONS]

Options:

--avoid-duplicates AVOID DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value VALUE Value to use when there is no match

--description DESCRIPTION Description of variable

--hidden-value HIDDEN VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--merge-default MERGE_DEFAULT Include default value when merging all matching values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash type)

One of true/false, yes/no, 1/0.

--organization ORGANIZATION NAME Organization name

--override-value-order OVERRIDE_VALUE_ORDER The order in which values are resolved

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-class PUPPET_CLASS_NAME Puppet class name --puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--validator-type VALIDATOR_TYPE Type of the validator

Possible value(s): 'regexp', 'list', "

--variable VARIABLE Name of variable

--variable-type VARIABLE_TYPE Type of the variable

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

-h, --help Print help

2.68.3. hammer smart-variable delete

Delete a smart variable

Usage:

hammer smart-variable delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Smart variable name (Deprecated: Use --variable instead)

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--variable VARIABLE Smart variable name

-h, --help Print help

2.68.4. hammer smart-variable info

Show a smart variable

Usage:

hammer smart-variable info [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Smart variable name (Deprecated: Use --variable instead)

--organization ORGANIZATION NAME Organization name

- --organization-id ORGANIZATION_ID Organization ID
- --organization-title ORGANIZATION_TITLE Organization title
- --show-hidden SHOW_HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

Smart variable name --variable VARIABLE

-h, --help Print help

2.68.5. hammer smart-variable list

List all smart variables

Usage:

hammer smart-variable list [OPTIONS]

Options:

--host HOST_NAME Host name

--host-id HOST ID

--hostgroup HOSTGROUP NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title --location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--puppet-class PUPPET_CLASS_NAME Puppet class name

--puppet-class-id PUPPET_CLASS_ID ID of Puppet class

--search SEARCH Filter results

--show-hidden SHOW HIDDEN Display hidden values

One of true/false, yes/no, 1/0.

-h, --help Print help

Search / Order fields:

avoid_duplicates Values: true, false

string

Values: true, false merge_default merge overrides Values: true, false override Values: true, false

string parameter

puppetclass string

2.68.6. hammer smart-variable remove-matcher

Delete an override value for a specific smart variable

Usage:

hammer smart-variable remove-matcher [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization-title ORGANIZATION_TITLE Organization title

--smart-variable SMART_VARIABLE_VARIABLE Smart variable name

--smart-variable-id SMART_VARIABLE_ID
-h, --help Print help

2.68.7. hammer smart-variable update

Update a smart variable

Usage:

hammer smart-variable update [OPTIONS]

Options:

--avoid-duplicates AVOID_DUPLICATES Remove duplicate values (only array type)

One of true/false, yes/no, 1/0.

--default-value VALUE Value to use when there is no match

--description DESCRIPTION Description of variable

--hidden-value HIDDEN_VALUE When enabled the parameter is hidden in the UI

One of true/false, yes/no, 1/0.

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--merge-default MERGE_DEFAULT Include default value when merging all matching values

One of true/false, yes/no, 1/0.

--merge-overrides MERGE_OVERRIDES Merge all matching values (only array/hash type)

One of true/false, yes/no, 1/0.

--new-variable NEW VARIABLE Name of variable

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

--override-value-order OVERRIDE VALUE ORDER The order in which values are resolved

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--puppet-class PUPPET_CLASS_NAME Puppet class name

--validator-type VALIDATOR_TYPE Type of the validator

Possible value(s): 'regexp', 'list', "

--variable VARIABLE Smart variable name

--variable-type VARIABLE TYPE Type of the variable

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml',

'json'

-h, --help Print help

2.69. HAMMER SUBNET

Manipulate subnets

Usage:

hammer subnet [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a subnet delete Delete a subnet

delete-parameter Delete parameter for a subnet

info Show a subnet list List of subnets

set-parameter Create or update parameter for a subnet

update Update a subnet

Options:

-h, --help Print help

2.69.1. hammer subnet create

Create a subnet

Usage:

hammer subnet create [OPTIONS]

Options:

--boot-mode BOOT_MODE Default boot mode for interfaces assigned to this subnet,

valid values are

"Static", "DHCP"

--description DESCRIPTION Subnet description

--dhcp DHCP_NAME DHCP Proxy to use within this subnet DHCP-ID DHCP Capsule ID to use within this subnet

--discovery-id DISCOVERY_ID ID of Discovery Capsule to use within this subnet for

managing connection

To discovered hosts

--dns DNS_NAME DNS Proxy to use within this subnet
--dns-id DNS_ID DNS Capsule ID to use within this subnet
--dns-primary DNS_PRIMARY Primary DNS for this subnet

--dns-secondary DNS_SECONDARY Secondary DNS for this subnet --domain-ids DOMAIN IDS Domains in which this subnet is part

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--from FROM Starting IP Address for IP auto suggestion

--gateway GATEWAY Subnet gateway

--httpboot-id HTTPBOOT ID HTTPBoot Capsule ID to use within this subnet

--ipam IPAM IP Address auto suggestion mode for this subnet, valid values are

"DHCP",

"Internal DB", "None"

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--mask MASK
--mtu MTU
--name NAME
--network NETWORK

Netmask for this subnet
MTU for this subnet
Subnet name
Subnet network

--network-type NETWORK_TYPE Type or protocol, IPv4 or IPv6, defaults to IPv4

Possible value(s): 'IPv4', 'IPv6'

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--template-id TEMPLATE_ID Template HTTP(S) Capsule ID to use within this subnet

--tftp TFTP_NAME TFTP Proxy to use within this subnet
--tftp-id TFTP_ID TFTP Capsule ID to use within this subnet
--to TO Ending IP Address for IP auto suggestion

--vlanid VLANID VLAN ID for this subnet

-h, --help Print help

2.69.2. hammer subnet delete

Delete a subnet

Usage:

hammer subnet delete [OPTIONS]

Options:

--id ID Subnet numeric identifier --location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Subnet name

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.69.3. hammer subnet delete-parameter

Delete parameter for a subnet

Usage:

hammer subnet delete-parameter [OPTIONS]

Options:

--name NAME Parameter name
--subnet SUBNET NAME Subnet name

--subnet-id SUBNET ID

-h, --help Print help

2.69.4. hammer subnet info

Show a subnet

Usage:

hammer subnet info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Subnet name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--show-hidden-parameters SHOW_HIDDEN_PARAMETERS Display hidden parameter values

One of true/false, yes/no, 1/0.

-h, --help Print help

2.69.5. hammer subnet list

List of subnets

Usage:

hammer subnet list [OPTIONS]

Options:

--domain DOMAIN_NAME Domain name

--domain-id DOMAIN ID Numerical ID or domain name

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields: boot mode string dns primary string dns secondary string domain string gateway string string ipam location string location id integer mask string mtu integer name text network string organization string organization_id integer params text type string vlanid integer

2.69.6. hammer subnet set-parameter

Create or update parameter for a subnet

Usage:

hammer subnet set-parameter [OPTIONS]

Options

--hidden-value HIDDEN_VALUE Should the value be hidden

One of true/false, yes/no, 1/0.

--name NAME Parameter name

--parameter-type PARAMETER TYPE Type of the parameter

Possible value(s): 'string', 'boolean', 'integer', 'real', 'array', 'hash', 'yaml', 'json'

Default: "string"

--subnet SUBNET_NAME Subnet name

--subnet-id SUBNET ID

--value VALUE Parameter value

-h, --help Print help

2.69.7. hammer subnet update

Update a subnet

Usage:

hammer subnet update [OPTIONS]

Options:

--boot-mode BOOT_MODE Default boot mode for interfaces assigned to this subnet,

valid values are

"Static", "DHCP"

--description DESCRIPTION Subnet description

--dhcp DHCP_NAME DHCP Proxy to use within this subnet of the control of the contr

managing connection

To discovered hosts

--dns DNS_NAME DNS Proxy to use within this subnet
--dns-id DNS_ID DNS Capsule ID to use within this subnet
--dns-primary DNS PRIMARY Primary DNS for this subnet

--dns-secondary DNS_SECONDARY Secondary DNS for this subnet --domain-ids DOMAIN IDS Domains in which this subnet is part

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--domains DOMAIN_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--from FROM Starting IP Address for IP auto suggestion

--gateway GATEWAY Subnet gateway

--httpboot-id HTTPBOOT_ID HTTPBoot Capsule ID to use within this subnet

--id ID Subnet numeric identifier

--ipam IPAM IP Address auto suggestion mode for this subnet, valid values are

"DHCP",

"Internal DB", "None"

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--mask MASK
--mtu MTU
--name NAME
--network NETWORK

Netmask for this subnet
MTU for this subnet
Subnet name
Subnet network

--network-type NETWORK TYPE Type or protocol, IPv4 or IPv6, defaults to IPv4

Possible value(s): 'IPv4', 'IPv6'

--new-name NEW_NAME Subnet name

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--template-id TEMPLATE_ID Template HTTP(S) Capsule ID to use within this subnet

--tftp TFTP_NAME TFTP Proxy to use within this subnet
--tftp-id TFTP ID TFTP Capsule ID to use within this subnet

--to TO Ending IP Address for IP auto suggestion

--vlanid VLANID VLAN ID for this subnet

-h, --help Print help

2.70. HAMMER SUBSCRIPTION

Manipulate subscriptions

Usage:

hammer subscription [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

delete-manifest Delete manifest from Red Hat provider

list List organization subscriptions

manifest-history Obtain manifest history for subscriptions

refresh-manifest Refresh previously imported manifest for Red Hat provider

upload Upload a subscription manifest

Options:

-h, --help Print help

2.70.1. hammer subscription delete-manifest

Delete manifest from Red Hat provider

Usage:

hammer subscription delete-manifest [OPTIONS]

Options:

--async Do not wait for the task

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.70.2. hammer subscription list

List organization subscriptions

Usage:

hammer subscription list [OPTIONS]

Options:

--activation-key ACTIVATION_KEY_NAME Activation key name to search by

--activation-key-id ACTIVATION_KEY_ID ID of the activation key

--available-for AVAILABLE_FOR Object to show subscriptions available for, either 'host' or

'activation_key'

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--host HOST_NAME Host name

--host-id HOST_ID

--match-host MATCH_HOST Ignore subscriptions that are unavailable to the specified host

One of true/false, yes/no, 1/0.

--match-installed MATCH_INSTALLED Return subscriptions that match installed products of the

specified host

One of true/false, yes/no, 1/0.

--no-overlap NO_OVERLAP Return subscriptions which do not overlap with a currently-

attached

Subscription

One of true/false, yes/no, 1/0.

--order ORDER Sort field and order, eg. 'id DESC'

--organization-label ORGANIZATION_LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.70.3. hammer subscription manifest-history

obtain manifest history for subscriptions

Usage:

hammer subscription manifest-history [OPTIONS]

Options:

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.70.4. hammer subscription refresh-manifest

Refresh previously imported manifest for Red Hat provider

Usage:

hammer subscription refresh-manifest [OPTIONS]

Options:

--async Do not wait for the task

--organization-label ORGANIZATION LABEL Organization label to search by

-h, --help Print help

2.70.5. hammer subscription upload

Upload a subscription manifest

Usage:

hammer subscription upload [OPTIONS]

Options:

--async Do not wait for the task
--file MANIFEST Subscription manifest file

--organization-label ORGANIZATION LABEL Organization label to search by

--repository-url REPOSITORY_URL Repository url

-h, --help Print help

2.71. HAMMER SYNC-PLAN

Manipulate sync plans

Usage:

hammer sync-plan [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a sync plan
delete Destroy a sync plan
info Show a sync plan
list List sync plans

update Update a sync plan

Options:

-h, --help Print help

2.71.1. hammer sync-plan create

Create a sync plan

Usage:

hammer sync-plan create [OPTIONS]

Options:

--cron-expression CRON EXPRESSION Set this when interval is custom cron

--description DESCRIPTION Sync plan description

--enabled ENABLED Enables or disables synchronization

One of true/false, yes/no, 1/0.

--interval INTERVAL How often synchronization should run

--name NAME Sync plan name

--organization ORGANIZATION NAME Organization name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

--sync-date SYNC_DATE Start date and time for the sync plan. Time is optional, if kept

blank current system time will be considered

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

-h, --help Print help

2.71.2. hammer sync-plan delete

Destroy a sync plan

Usage:

hammer sync-plan delete [OPTIONS]

Options:

--id ID Sync plan numeric identifier

--name NAME Sync plan name to search by

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.71.3. hammer sync-plan info

Show a sync plan

Usage:

hammer sync-plan info [OPTIONS]

Options:

--id ID Sync plan numeric identifier

--name NAME Sync plan name to search by

--organization-label ORGANIZATION_LABEL Organization label to search by

-h, --help Print help

2.71.4. hammer sync-plan list

List sync plans

Usage:

hammer sync-plan list [OPTIONS]

Options:

--full-result FULL_RESULT Whether or not to show all results

One of true/false, yes/no, 1/0.

--interval INTERVAL Filter by interval

Possible value(s): 'hourly', 'daily', 'weekly', 'custom cron'

--name NAME Filter by name

--order ORDER Sort field and order, eg. 'id DESC'

--organization-id ORGANIZATION ID Organization ID

--organization-label ORGANIZATION LABEL Organization label to search by

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

--sync-date SYNC_DATE Filter by sync date

-h, --help Print help

2.71.5. hammer sync-plan update

Update a sync plan

Usage:

hammer sync-plan update [OPTIONS]

Options:

--cron-expression CRON_EXPRESSION Add custom cron logic for sync plan

--description DESCRIPTION Sync plan description

--enabled ENABLED Enables or disables synchronization

One of true/false, yes/no, 1/0.

--id ID Sync plan numeric identifier

--interval INTERVAL How often synchronization should run

--name NAME Sync plan name to search by --new-name NEW NAME Sync plan name

--organization-label ORGANIZATION_LABEL Organization label to search by --sync-date SYNC DATE Start date and time of the synchronization

Date and time in YYYY-MM-DD HH:MM:SS or ISO 8601 format

-h, --help Print help

2.72. HAMMER TAILORING-FILE

Manipulate Tailoring files

Usage:

hammer tailoring-file [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a Tailoring file delete Deletes a Tailoring file

download Download a Tailoring file as XML

info Show a Tailoring file list List Tailoring files

update Update a Tailoring file

Options:

-h, --help Print help

2.72.1. hammer tailoring-file create

Create a Tailoring file

Usage:

hammer tailoring-file create [OPTIONS]

Options:

- --location-id LOCATION_ID
- --location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --name NAME Tailoring file name
- --organization ORGANIZATION NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --original-filename ORIGINAL_FILENAME Original file name of the XML file
- --scap-file SCAP FILE Tailoring file content
- -h, --help Print help

2.72.2. hammer tailoring-file delete

Deletes a Tailoring file

Usage:

hammer tailoring-file delete [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.72.3. hammer tailoring-file download

Download a Tailoring file as XML

Usage:

hammer tailoring-file download [OPTIONS]

Options:

- --id ID
- --location-id LOCATION_ID
- --name NAME Tailoring file name
- --organization ORGANIZATION_NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

--path PATH Path to directory where downloaded file will be saved

-h, --help Print help

2.72.4. hammer tailoring-file info

Show a Tailoring file

Usage:

hammer tailoring-file info [OPTIONS]

Options:

--id ID

--location-id LOCATION ID

--name NAME Tailoring file name

--organization ORGANIZATION_NAME Name to search by

--organization-id ORGANIZATION_ID Organization ID

-h, --help Print help

2.72.5. hammer tailoring-file list

List Tailoring files

Usage:

hammer tailoring-file list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

created_at datetime
filename string
location string
location_id integer
name string
organization string
organization id integer

2.72.6. hammer tailoring-file update

Update a Tailoring file

Usage:

hammer tailoring-file update [OPTIONS]

Options:

--id ID

--location LOCATION NAME Name to search by

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--name NAME Tailoring file name

--new-name NEW_NAME Tailoring file name

--organization-id ORGANIZATION ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted

or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--original-filename ORIGINAL_FILENAME Original file name of the XML file

--scap-file SCAP_FILE Tailoring file content

-h, --help Print help

2.73. HAMMER TASK

Tasks related actions.

Usage:

hammer task [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

info Show task details

list List tasks

progress Show the progress of the task

resume Resume all tasks paused in error state

Options:

-h, --help Print help

2.73.1. hammer task info

Show task details

Usage:

hammer task info [OPTIONS]

Options:

--id ID UUID of the task

--organization-id ORGANIZATION_ID Scope by organizations

-h, --help Print help

2.73.2. hammer task list

List tasks

Usage:

hammer task list [OPTIONS]

Options:

--by BY Field to sort the results on --location-id LOCATION ID Scope by locations

--order ORDER Sort field and order, e.g. 'name DESC' --organization-id ORGANIZATION ID Scope by organizations

--page PAGE Page number, starting at 1

--per-page PER_PAGE Number of results per page to return

--search SEARCH Search string

-h, --help Print help

2.73.3. hammer task progress

Show the progress of the task

Usage:

hammer task progress [OPTIONS]

Options:

--id ID UUID of the task

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.73.4. hammer task resume

Resume all tasks paused in error state

Usage:

hammer task resume [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--search SEARCH Resume tasks matching search string

--task-ids TASK_IDS Resume specific tasks by ID

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--tasks TASK_NAMES Comma separated list of values. Values containing comma

should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.74. HAMMER TEMPLATE

Manipulate config templates

Usage:

hammer template [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-operatingsystem Associate an operating system

build-pxe-default Update the default PXE menu on all configured TFTP servers

clone Clone a provision template

combination Manage template combinations
create Create a provisioning template
delete Delete a provisioning template
dump View provisioning template content
info Show provisioning template details

kinds List available provisioning template kinds

list List provisioning templates

remove-operatingsystem Disassociate an operating system

update Update a provisioning template

Options:

-h, --help Print help

2.74.1. hammer template add-operatingsystem

Associate an operating system

Usage:

hammer template add-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Name to search by

- --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
- --operatingsystem-id OPERATINGSYSTEM_ID
- -h, --help Print help

2.74.2. hammer template build-pxe-default

Update the default PXE menu on all configured TFTP servers

Usage:

hammer template build-pxe-default [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.74.3. hammer template clone

Clone a provision template

Usage:

hammer template clone [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title
--name NAME Name to search by
--new-name NEW_NAME Template name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.74.4. hammer template combination

Manage template combinations

Usage:

hammer template combination [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Add a template combination delete Delete a template combination

info Show template combination list List template combination

Update template combination update

Options:

-h, --help Print help

2.74.4.1. hammer template combination create

Add a template combination

Usage:

hammer template combination create [OPTIONS]

Options:

--environment ENVIRONMENT NAME Environment name (--environment is

deprecated: Use --puppet-environment instead)

--environment-id ENVIRONMENT ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title --location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION NAME Organization name --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--provisioning-template PROVISIONING TEMPLATE NAME Name to search by

--provisioning-template-id PROVISIONING TEMPLATE ID

--puppet-environment PUPPET ENVIRONMENT NAME Puppet environment name

--puppet-environment-id PUPPET ENVIRONMENT ID

-h, --help Print help

2.74.4.2. hammer template combination delete

Delete a template combination

hammer template combination delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

Print help -h, --help

2.74.4.3. hammer template combination info

Show template combination

Usage:

hammer template combination info [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is

deprecated: Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP ID

--hostgroup-title HOSTGROUP_TITLE Hostgroup title

--id ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION TITLE Organization title

--provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by

--provisioning-template-id PROVISIONING_TEMPLATE_ID

--puppet-environment-id PUPPET_ENVIRONMENT_ID

-h, --help Print help

2.74.4.4. hammer template combination list

List template combination

Usage:

hammer template combination list [OPTIONS]

Options:

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME
--organization-id ORGANIZATION_ID
--organization-title ORGANIZATION_TITLE
Organization title

--provisioning-template PROVISIONING_TEMPLATE_NAME Name to search by

--provisioning-template-id PROVISIONING_TEMPLATE_ID

-h, --help Print help

2.74.4.5. hammer template combination update

Update template combination

Usage:

hammer template combination update [OPTIONS]

Options:

--environment ENVIRONMENT_NAME Environment name (--environment is

deprecated: Use --puppet-environment instead)

--environment-id ENVIRONMENT_ID (--environment-id is deprecated: Use --puppet-

environment-id instead)

--hostgroup HOSTGROUP_NAME Hostgroup name

--hostgroup-id HOSTGROUP_ID

--hostgroup-title HOSTGROUP TITLE Hostgroup title

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title

--provisioning-template PROVISIONING TEMPLATE NAME Name to search by

--provisioning-template-id PROVISIONING_TEMPLATE_ID

--puppet-environment PUPPET_ENVIRONMENT_NAME Puppet environment name

--puppet-environment-id PUPPET_ENVIRONMENT_ID

-h, --help Print help

2.74.5. hammer template create

Create a provisioning template

Usage:

hammer template create [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file TEMPLATE Path to a file that contains the template

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Template name

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the template

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --organization-title ORGANIZATION_TITLE Organization title
- --organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--type TYPE Template type. Eg. snippet, script, provision

-h, --help Print help

2.74.6. hammer template delete

Delete a provisioning template

Usage:

hammer template delete [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.74.7. hammer template dump

View provisioning template content

Usage:

hammer template dump [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by --organization ORGANIZATION_NAME Organiz
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title

Organization name

-h, --help Print help

2.74.8. hammer template info

Show provisioning template details

Usage:

hammer template info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.74.9. hammer template kinds

List available provisioning template kinds

Usage:

hammer template kinds [OPTIONS]

Options:

-h, --help Print help

2.74.10. hammer template list

List provisioning templates

Usage:

hammer template list [OPTIONS]

Options:

- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --operatingsystem OPERATINGSYSTEM_TITLE Operating system title
- --operatingsystem-id OPERATINGSYSTEM ID
- --order ORDER Sort field and order, eg. 'id DESC'

- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

Search / Order fields:

default template Values: true, false

environment string
hostgroup string
kind string
location string
location_id integer

locked Values: true, false

name string operatingsystem string

organization string organization_id integer

snippet Values: true, false

template text vendor string

2.74.11. hammer template remove-operatingsystem

Disassociate an operating system

Usage:

hammer template remove-operatingsystem [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--operatingsystem OPERATINGSYSTEM_TITLE Operating system title

--operatingsystem-id OPERATINGSYSTEM ID

-h, --help Print help

2.74.12. hammer template update

Update a provisioning template

Usage:

hammer template update [OPTIONS]

Options:

--audit-comment AUDIT_COMMENT

--file TEMPLATE Path to a file that contains the template

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locked LOCKED Whether or not the template is locked for editing

One of true/false, yes/no, 1/0.

--name NAME Name to search by --new-name NEW NAME Template name

--operatingsystem-ids OPERATINGSYSTEM_IDS Array of operating system IDs to associate with the template

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--operatingsystems OPERATINGSYSTEM_TITLES Comma separated list of values. Values

containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-title ORGANIZATION_TITLE Organization title

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--type TYPE Template type. Eg. snippet, script, provision

-h, --help Print help

2.75. HAMMER TEMPLATE-INPUT

Manage template inputs

Usage:

hammer template-input [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a template input
delete Delete a template input
info Show template input details

list List template inputs

Options:

-h, --help Print help

2.75.1. hammer template-input create

Create a template input

Usage:

hammer template-input create [OPTIONS]

Options:

--advanced ADVANCED Input is advanced

One of true/false, yes/no, 1/0.

--description DESCRIPTION Input description

--fact-name FACT_NAME Fact name, used when input type is fact

--input-type INPUT_TYPE Input type

Possible value(s): 'user', 'fact', 'variable', 'puppet_parameter'

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Input name

--options OPTIONS Selectable values for user inputs

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title
--puppet-class-name PUPPET CLASS NAME Puppet class na

--puppet-class-name PUPPET_CLASS_NAME Puppet class name, used when input type is puppet parameter

--puppet-parameter-name PUPPET_PARAMETER_NAME Puppet parameter name, used when input type is puppet_parameter

--required REQUIRED Input is required

One of true/false, yes/no, 1/0.

--resource-type RESOURCE_TYPE For values of type search, this is the resource the value searches in

Possible value(s): 'AnsibleRole', 'AnsibleVariable', 'Architecture', 'Audit',

'AuthSource', 'Bookmark', 'ComputeProfile', 'ComputeResource', 'ConfigGroup', 'ConfigReport',

'DiscoveryRule', 'Domain', 'Environment', 'ExternalUsergroup', 'FactValue', 'Filter',

'ForemanOpenscap::ArfReport', 'ForemanOpenscap::Policy', 'ForemanOpenscap::ScapContent',

'ForemanOpenscap::TailoringFile', 'ForemanTasks::RecurringLogic', 'ForemanTasks::Task',

'ForemanVirtWhoConfigure::Config', 'Host', 'HostClass', 'Hostgroup', 'HttpProxy', 'Image',

'JobInvocation', 'JobTemplate', 'Katello::ActivationKey', 'Katello::ContentView', 'Katello::GpgKey',

'Katello::HostCollection', 'Katello::KTEnvironment', 'Katello::Product', 'Katello::Subscription',

'Katello::SyncPlan', 'KeyPair', 'Location', 'MailNotification', 'Medium', 'Model', 'Operatingsystem',

'Organization', 'Parameter', 'PersonalAccessToken', 'ProvisioningTemplate', 'Ptable', 'Puppetclass',

'PuppetclassLookupKey', 'Realm', 'RemoteExecutionFeature', 'Report', 'ReportTemplate', 'Role',

'Setting', 'SmartProxy', 'SshKey', 'Subnet', 'Template', 'TemplateInvocation', 'Trend', 'User',

'Usergroup', 'VariableLookupKey'

--template-id TEMPLATE_ID

--value-type VALUE_TYPE Value type, defaults to plain

Possible value(s): 'plain', 'search', 'date'

--variable-name VARIABLE NAME Variable name, used when input type is variable

-h, --help Print help

2.75.2. hammer template-input delete

Delete a template input

Usage:

hammer template-input delete [OPTIONS]

Options:

--id ID

--location LOCATION NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--name NAME Name to search by

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--template-id TEMPLATE_ID

-h, --help Print help

2.75.3. hammer template-input info

Show template input details

Usage:

hammer template-input info [OPTIONS]

Options:

- --id ID
- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- --template-id TEMPLATE_ID
- -h, --help Print help

2.75.4. hammer template-input list

List template inputs

Usage:

hammer template-input list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION_TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- --template-id TEMPLATE_ID
- -h, --help Print help

2.76. HAMMER USER

Manipulate users

Usage:

hammer user [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

access-token Managing personal access tokens

add-role Assign a user role

create Create a user
delete Delete a user
info Show a user
list List all users

remove-role Remove a user role ssh-keys Managing User SSH Keys.

update Update a user

Options:

-h, --help Print help

2.76.1. hammer user access-token

Managing personal access tokens

Usage:

hammer user access-token [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a Personal Access Token for a user info Show a Personal Access Token for a user list List all Personal Access Tokens for a user revoke Revoke a Personal Access Token for a user

Options:

-h, --help Print help

2.76.1.1. hammer user access-token create

Create a Personal Access Token for a user

Usage:

hammer user access-token create [OPTIONS]

Options:

--expires-at EXPIRES_AT Expiry Date
--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID
--organization-title ORGANIZATION_TITLE Organization title
--user USER_LOGIN User's login to search by

--user-id USER ID

-h, --help Print help

2.76.1.2. hammer user access-token info

Show a Personal Access Token for a user

Usage:

hammer user access-token info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- --user-id USER_ID
- -h, --help Print help

2.76.1.3. hammer user access-token list

List all Personal Access Tokens for a user

Usage:

hammer user access-token list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
- --organization ORGANIZATION NAME Organization name
- --organization-title ORGANIZATION TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- --user USER LOGIN User's login to search by
- --user-id USER ID
- -h, --help Print help

2.76.1.4. hammer user access-token revoke

Revoke a Personal Access Token for a user

Usage:

hammer user access-token revoke [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title

--user-id USER_ID

-h, --help Print help

2.76.2. hammer user add-role

Assign a user role

Usage:

hammer user add-role [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by --role ROLE NAME User role name

--role-id ROLE_ID

-h, --help Print help

2.76.3. hammer user create

Create a user

Usage:

hammer user create [OPTIONS]

Options:

--admin ADMIN Is an admin account

One of true/false, yes/no, 1/0.

--ask-password ASK_PW One of true/false, yes/no, 1/0.

--auth-source AUTH_SOURCE_NAME Name to search by

--auth-source-id AUTH SOURCE ID

--default-location DEFAULT LOCATION NAME Default location name

--default-location-id DEFAULT LOCATION ID

--default-organization DEFAULT_ORGANIZATION_NAME Default organization name

--default-organization-id DEFAULT ORGANIZATION ID

--description DESCRIPTION

--firstname FIRSTNAME

--lastname LASTNAME

--locale LOCALE User's preferred locale

Possible value(s): 'ca', 'cs_CZ', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja',

'ko', 'nl_NL', 'pl', 'pt_BR', 'ru', 'sv_SE', 'zh_CN', 'zh_TW'

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-ids LOCATION IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be

quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

- --login LOGIN
- --mail MAIL
- --organization ORGANIZATION_NAME Organization name
- --organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be guoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--password PASSWORD source

Required unless user is in an external authentication

--role-ids ROLE_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--roles ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--timezone TIMEZONE User's timezone

Possible value(s): 'International Date Line West', 'American Samoa', 'Midway Island', 'Hawaii', 'Alaska', 'Pacific Time (US & Samp; Canada)', 'Tijuana', 'Arizona', 'Chihuahua', 'Mazatlan', 'Mountain Time (US & Description of the Control of the Canada)', 'Guadalajara', 'Mexico City', 'Monterrey', 'Saskatchewan', 'Bogota', 'Eastern Time (US & amp; Canada)', 'Indiana (East)', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'Georgetown', 'La Paz', 'Puerto Rico', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Greenland', 'Montevideo', 'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Casablanca', 'Dublin', 'Edinburgh', 'Lisbon', 'London', 'Monrovia', 'UTC', 'Amsterdam', 'Belgrade', 'Berlin', 'Bern', 'Bratislava', 'Brussels', 'Budapest', 'Copenhagen', 'Ljubljana', 'Madrid', 'Paris', 'Prague', 'Rome', 'Sarajevo', 'Skopje', 'Stockholm', 'Vienna', 'Warsaw', 'West Central Africa', 'Zagreb', 'Zurich', 'Athens', 'Bucharest', 'Cairo', 'Harare', 'Helsinki', 'Jerusalem', 'Kaliningrad', 'Kyiv', 'Pretoria', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Baghdad', 'Istanbul', 'Kuwait', 'Minsk', 'Moscow', 'Nairobi', 'Riyadh', 'St. Petersburg', 'Tehran', 'Abu Dhabi', 'Baku', 'Muscat', 'Samara', 'Tbilisi', 'Volgograd', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent', 'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Sri Jayawardenepura', 'Kathmandu', 'Almaty', 'Astana', 'Dhaka', 'Urumqi', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Novosibirsk', 'Beijing', 'Chongqing', 'Hong Kong', 'Irkutsk', 'Kuala Lumpur', 'Perth', 'Singapore', 'Taipei', 'Ulaanbaatar', 'Osaka', 'Sapporo', 'Seoul', 'Tokyo', 'Yakutsk', 'Adelaide', 'Darwin', 'Brisbane', 'Canberra', 'Guam',

'Hobart', 'Melbourne', 'Port Moresby', 'Sydney', 'Vladivostok', 'Magadan', 'New Caledonia', 'Solomon

Is.', 'Srednekolymsk', 'Auckland', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Wellington', 'Chatham Is.',

-h, --help Print help

'Nuku'alofa', 'Samoa', 'Tokelau Is.'

2.76.4. hammer user delete

Delete a user

Usage:

hammer user delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--login LOGIN User's login to search by

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.76.5. hammer user info

Show a user

Usage:

hammer user info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title
--login LOGIN User's login to search by

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.76.6. hammer user list

List all users

Usage:

hammer user list [OPTIONS]

Options:

--auth-source-Idap AUTH SOURCE LDAP NAME Name to search by

--auth-source-ldap-id AUTH_SOURCE_LDAP_ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--role ROLE NAME User role name

--role-id ROLE ID

--search SEARCH Filter results

--user-group USER GROUP NAME Name to search by

--user-group-id USER_GROUP_ID -h, --help Print help

Search / Order fields:

admin Values: true, false

description text firstname string last_login_on datetime lastname string location string location id integer login string mail string string organization organization_id integer role string role_id integer usergroup string

2.76.7. hammer user remove-role

Remove a user role

Usage:

hammer user remove-role [OPTIONS]

Options:

--id ID

--login LOGIN User's login to search by --role ROLE_NAME User role name

--role-id ROLE_ID

-h, --help Print help

2.76.8. hammer user ssh-keys

Managing User SSH Keys.

Usage:

hammer user ssh-keys [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add Add an SSH key for a user
delete Delete an SSH key for a user
info Show an SSH key from a user
list List all SSH keys for a user

Options:

-h, --help Print help

2.76.8.1. hammer user ssh-keys add

Add an SSH key for a user

Usage:

hammer user ssh-keys add [OPTIONS]

Options:

--key KEY Public SSH key

--key-file KEY_FILE Path to a SSH public key --location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title --user USER_LOGIN User's login to search by

--user-id USER_ID

-h, --help Print help

2.76.8.2. hammer user ssh-keys delete

Delete an SSH key for a user

Usage:

hammer user ssh-keys delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title --user USER LOGIN User's login to search by

--user-id USER ID

-h, --help Print help

2.76.8.3. hammer user ssh-keys info

Show an SSH key from a user

Usage:

hammer user ssh-keys info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

--user USER_LOGIN

User's login to search by

--user-id USER_ID

-h, --help Print help

2.76.8.4. hammer user ssh-keys list

List all SSH keys for a user

Usage:

hammer user ssh-keys list [OPTIONS]

Options:

--location LOCATION NAME

Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

--user USER_LOGIN User's login to search by

--user-id USER_ID

-h, --help Print help

Search / Order fields: name string user id integer

2.76.9. hammer user update

Update a user

Usage:

hammer user update [OPTIONS]

Options:

--admin ADMIN Is an admin account

One of true/false, yes/no, 1/0.

--ask-password ASK_PW One of true/false, yes/no, 1/0.
--auth-source AUTH_SOURCE_NAME Name to search by

--auth-source-id AUTH SOURCE ID

--current-password CURRENT_PASSWORD Required when user want to change own

password

--default-location-id DEFAULT LOCATION ID

--default-organization DEFAULT_ORGANIZATION_NAME Default organization name

--default-organization-id DEFAULT_ORGANIZATION_ID

--description DESCRIPTION

--firstname FIRSTNAME

--id ID

--lastname LASTNAME

--locale LOCALE User's preferred locale

Possible value(s): 'ca', 'cs_CZ', 'de', 'en', 'en_GB', 'es', 'fr', 'gl', 'it', 'ja',

'ko', 'nl_NL', 'pl', 'pt_BR', 'ru', 'sv_SE', 'zh_CN', 'zh_TW'

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-ids LOCATION_IDS REPLACE locations with given ids

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--location-title LOCATION_TITLE Location title

--location-titles LOCATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--locations LOCATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--login LOGIN User's login to search by

--mail MAIL

--new-login NEW LOGIN

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--organization-ids ORGANIZATION_IDS REPLACE organizations with given ids.

Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organization-titles ORGANIZATION_TITLES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--organizations ORGANIZATION_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--password PASSWORD Required unless user is in an external authentication source

--role-ids ROLE_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--roles ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--timezone TIMEZONE User's timezone

Possible value(s): 'International Date Line West', 'American Samoa',

'Midway Island', 'Hawaii', 'Alaska', 'Pacific Time (US & Eamp; Canada)', 'Tijuana', 'Arizona', 'Chihuahua', 'Mazatlan', 'Mountain Time (US & Eamp; Canada)', 'Central America', 'Central Time (US & Eamp; Canada)', 'Guadalajara', 'Mexico City', 'Monterrey', 'Saskatchewan', 'Bogota', 'Eastern Time (US & Eamp; Canada)', 'Indiana (East)', 'Lima', 'Quito', 'Atlantic Time (Canada)', 'Caracas', 'Georgetown', 'La Paz', 'Puerto Rico', 'Santiago', 'Newfoundland', 'Brasilia', 'Buenos Aires', 'Greenland', 'Montevideo', 'Mid-Atlantic', 'Azores', 'Cape Verde Is.', 'Casablanca', 'Dublin', 'Edinburgh', 'Lisbon', 'London', 'Monrovia', 'UTC', 'Amsterdam', 'Belgrade', 'Berlin', 'Bern', 'Bratislava', 'Brussels', 'Budapest', 'Copenhagen', 'Ljubljana', 'Madrid', 'Paris', 'Prague', 'Rome', 'Sarajevo', 'Skopje', 'Stockholm', 'Vienna', 'Warsaw', 'West Central Africa', 'Zagreb', 'Zurich', 'Athens', 'Bucharest', 'Cairo', 'Harare', 'Helsinki', 'Jerusalem', 'Kaliningrad', 'Kyiv', 'Pretoria', 'Riga', 'Sofia', 'Tallinn', 'Vilnius', 'Baghdad', 'Istanbul', 'Kuwait', 'Minsk', 'Moscow', 'Nairobi', 'Riyadh', 'St. Petersburg', 'Tehran', 'Abu Dhabi', 'Baku', 'Muscat', 'Samara', 'Tbilisi', 'Volgograd', 'Yerevan', 'Kabul', 'Ekaterinburg', 'Islamabad', 'Karachi', 'Tashkent', 'Chennai', 'Kolkata', 'Mumbai', 'New Delhi', 'Sri Jayawardenepura', 'Kathmandu', 'Almaty', 'Astana', 'Dhaka', 'Urumqi', 'Rangoon', 'Bangkok', 'Hanoi', 'Jakarta', 'Krasnoyarsk', 'Novosibirsk', 'Beijing', 'Chongqing', 'Hong Kong', 'Irkutsk', 'Kuala Lumpur', 'Perth', 'Singapore', 'Taipei', 'Ulaanbaatar',

'Osaka', 'Sapporo', 'Seoul', 'Tokyo', 'Yakutsk', 'Adelaide', 'Darwin', 'Brisbane', 'Canberra', 'Guam', 'Hobart', 'Melbourne', 'Port Moresby', 'Sydney', 'Vladivostok', 'Magadan', 'New Caledonia', 'Solomon Is.', 'Srednekolymsk', 'Auckland', 'Fiji', 'Kamchatka', 'Marshall Is.', 'Wellington', 'Chatham Is.', 'Nuku'alofa', 'Samoa', 'Tokelau Is.'

-h, --help Print help

2.77. HAMMER USER-GROUP

Manage user groups

Usage:

hammer user-group [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

add-role Assign a user role add-user Associate an user

add-user-group Associate an user group

create Create a user group delete Delete a user group

external View and manage user group's external user groups

info Show a user group
list List all user groups
remove-role Remove a user role
remove-user Disassociate an user

remove-user-group Disassociate an user group

update Update a user group

Options:

-h, --help Print help

2.77.1. hammer user-group add-role

Assign a user role

Usage:

hammer user-group add-role [OPTIONS]

Options:

--id ID

--name NAME Name to search by --role ROLE_NAME User role name

--role-id ROLE ID

-h, --help Print help

2.77.2. hammer user-group add-user

Associate an user

Usage:

hammer user-group add-user [OPTIONS]

Options:

- --id ID
- --name NAME Name to search by
- --user-id USER ID
- -h, --help Print help

2.77.3. hammer user-group add-user-group

Associate an user group

Usage:

hammer user-group add-user-group [OPTIONS]

Options:

- --id ID
- --name NAME Name to search by
- --user-group USER_GROUP_NAME Name to search by
- --user-group-id USER_GROUP_ID -h, --help Print help

2.77.4. hammer user-group create

Create a user group

Usage:

hammer user-group create [OPTIONS]

Options:

--admin ADMIN Is an admin user group

One of true/false, yes/no, 1/0.

- --location LOCATION_NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION TITLE Location title
- --name NAME

- --organization-title ORGANIZATION_TITLE Organization title
- --role-ids ROLE_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--roles ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-group-ids USER_GROUP_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-groups USER_GROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-ids USER_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER_LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.77.5. hammer user-group delete

Delete a user group

Usage:

hammer user-group delete [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.77.6. hammer user-group external

View and manage user group's external user groups

Usage:

hammer user-group external [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create an external user group linked to a user group

delete Delete an external user group

info Show an external user group for user group list List all external user groups for user group

refresh Refresh external user group update Update external user group

Options:

-h, --help Print help

2.77.6.1. hammer user-group external create

Create an external user group linked to a user group

Usage:

hammer user-group external create [OPTIONS]

Options:

--auth-source-id AUTH_SOURCE_ID

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title

--name NAME External user group name

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--user-group-id USER_GROUP_ID

-h, --help Print help

2.77.6.2. hammer user-group external delete

Delete an external user group

Usage:

hammer user-group external delete [OPTIONS]

Options:

--id ID ID or name external user group

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION TITLE Organization title

--user-group USER GROUP NAME Name to search by

--user-group-id USER_GROUP_ID

-h, --help Print help

2.77.6.3. hammer user-group external info

Show an external user group for user group

Usage:

hammer user-group external info [OPTIONS]

Options:

--id ID ID or name of external user group

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION TITLE Organization title

--user-group USER GROUP NAME Name to search by

--user-group-id USER GROUP ID

-h, --help Print help

2.77.6.4. hammer user-group external list

List all external user groups for user group

Usage:

hammer user-group external list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

--user-group USER GROUP NAME Name to search by

--user-group-id USER_GROUP_ID

-h, --help Print help

2.77.6.5. hammer user-group external refresh

Refresh external user group

Usage:

hammer user-group external refresh [OPTIONS]

Options:

--id ID ID or name of external user group

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION_TITLE Organization title

--user-group-id USER GROUP ID

-h, --help Print help

2.77.6.6. hammer user-group external update

Update external user group

Usage:

hammer user-group external update [OPTIONS]

Options:

--auth-source AUTH SOURCE NAME Name to search by

--auth-source-id AUTH SOURCE ID

--id ID ID or name of external user group

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--new-name NEW_NAME External user group name

--organization ORGANIZATION_NAME Organization name --organization-id ORGANIZATION_ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--user-group USER_GROUP_NAME Name to search by

--user-group-id USER_GROUP_ID

-h, --help Print help

2.77.7. hammer user-group info

Show a user group

Usage:

hammer user-group info [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.77.8. hammer user-group list

List all user groups

Usage:

hammer user-group list [OPTIONS]

Options:

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION TITLE Location title

--order ORDER Sort field and order, eg. 'id DESC'
--organization ORGANIZATION_NAME Organization name

--organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title

--page PAGE Paginate results

--per-page PER_PAGE Number of entries per request

--search SEARCH Filter results

-h, --help Print help

Search / Order fields:

name string role string role id integer

2.77.9. hammer user-group remove-role

Remove a user role

_

Usage:

hammer user-group remove-role [OPTIONS]

Options:

--id ID

--name NAME Name to search by --role ROLE_NAME User role name

--role-id ROLE_ID

-h, --help Print help

2.77.10. hammer user-group remove-user

Disassociate an user

Usage:

hammer user-group remove-user [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--user-id USER ID

-h, --help Print help

2.77.11. hammer user-group remove-user-group

Disassociate an user group

Usage:

hammer user-group remove-user-group [OPTIONS]

Options:

--id ID

--name NAME Name to search by

--user-group USER_GROUP_NAME Name to search by

--user-group-id USER_GROUP_ID

-h, --help Print help

2.77.12. hammer user-group update

Update a user group

Usage:

hammer user-group update [OPTIONS]

Options:

--admin ADMIN Is an admin user group

One of true/false, yes/no, 1/0.

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--new-name NEW_NAME

--organization-id ORGANIZATION ID Organization ID

--organization-title ORGANIZATION_TITLE Organization title

--role-ids ROLE_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--roles ROLE_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-group-ids USER_GROUP_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-groups USER_GROUP_NAMES Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--user-ids USER_IDS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

--users USER_LOGINS Comma separated list of values. Values containing comma should be quoted or escaped with backslash.

JSON is acceptable and preferred way for complex parameters

-h, --help Print help

2.78. HAMMER VIRT-WHO-CONFIG

Manage Virt Who configurations

Usage:

hammer virt-who-config [OPTIONS] SUBCOMMAND [ARG] ...

Parameters:

SUBCOMMAND Subcommand [ARG] ... Subcommand arguments

Subcommands:

create Create a virt-who configuration delete Delete a virt-who configuration

deploy Download and execute script for the specified virt-who configuration fetch Renders a deploy script for the specified virt-who configuration

info Show a virt-who configuration list List of virt-who configurations update Update a virt-who configuration

Options:

-h, --help Print help

2.78.1. hammer virt-who-config create

Create a virt-who configuration

Usage:

hammer virt-who-config create [OPTIONS]

Options:

--blacklist BLACKLIST Hypervisor blacklist, applicable only when filtering mode is set

to 2.

Wildcards and regular expressions are supported, multiple records must

be

Separated by comma.

Enable debugging output --debug DEBUG

One of true/false, yes/no, 1/0.

--exclude-host-parents EXCLUDE HOST PARENTS Applicable only for esx provider type. Hosts

which parent (usually

ComputeResource) name is specified in comma-separated list in this

option

Will NOT be reported. Wildcards and regular expressions

Are supported, multiple records must be separated by comma. Put the

value

Into the double-quotes if it contains special characters like comma. All New line characters will be removed in resulting configuration file, white

Spaces are removed from beginning and end.

--filter-host-parents FILTER HOST PARENTS Applicable only for exx provider type. Only hosts which parent (usually

ComputeResource) name is specified in comma-separated list in this

option

Will be reported. Wildcards and regular expressions are supported,

multiple

Records must be separated by comma. Put the value into the double-

quotes if

It contains special characters like comma. All new line characters will be Removed in resulting configuration file, white spaces are removed from Beginning and end.

Hypervisor filtering mode --filtering-mode MODE

Possible value(s): 'none', 'whitelist', 'blacklist'

Specifies how the hypervisor will be identified. --hypervisor-id HYPERVISOR ID

Possible value(s): 'hostname', 'uuid', 'hwuuid'

--hypervisor-password HYPERVISOR PASSWORD Hypervisor password, required for all hypervisor types except for libvirt

--hypervisor-server HYPERVISOR_SERVER Fully qualified host name or IP address of the hypervisor

--hypervisor-type HYPERVISOR TYPE Hypervisor type

Possible value(s): 'esx', 'rhevm', 'hyperv', 'xen', 'libvirt', 'kubevirt'

--hypervisor-username HYPERVISOR_USERNAME Account name by which virt-who is to connect to the hypervisor.

--interval INTERVAL Configuration interval in minutes

Possible value(s): '60', '120', '240', '480', '720', '1440', '2880', '4320'

--location LOCATION NAME Location name

--location-id LOCATION_ID

--location-title LOCATION TITLE Location title --name NAME Configuration name

--no-proxy NO PROXY Ignore Proxy. A comma-separated list of hostnames or

domains or ip

Addresses to ignore Capsule settings for. Optionally this may be set to * To bypass proxy settings for all hostnames domains or ip addresses.

--organization ORGANIZATION NAME Organization name

--organization-id ORGANIZATION_ID Organization ID

--proxy PROXY HTTP Proxy that should be used for communication between the

server on

Which virt-who is running and the hypervisors and virtualization

managers.

--satellite-url SATELLITE URL Satellite server FQDN

--whitelist WHITELIST Hypervisor whitelist, applicable only when filtering mode is set

to 1.

Wildcards and regular expressions are supported, multiple records must

be

Separated by comma.

-h, --help Print help

2.78.2. hammer virt-who-config delete

Delete a virt-who configuration

Usage:

hammer virt-who-config delete [OPTIONS]

Options:

--id ID Configuration numeric identifier

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title

--name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION_TITLE Organization title

-h, --help Print help

2.78.3. hammer virt-who-config deploy

Download and execute script for the specified virt-who configuration

Usage:

hammer virt-who-config deploy [OPTIONS]

Options:

--id ID

--location LOCATION_NAME Location name

--location-id LOCATION_ID

--location-title LOCATION_TITLE Location title --name NAME Name to search by

--organization ORGANIZATION_NAME Organization name

--organization-title ORGANIZATION TITLE Organization title

-h, --help Print help

2.78.4. hammer virt-who-config fetch

Renders a deploy script for the specified virt-who configuration

Usage:

hammer virt-who-config fetch [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title
- --name NAME Name to search by
- --organization-id ORGANIZATION_ID Organization ID --organization-title ORGANIZATION TITLE Organization title
- --organization-title ONGANIZATION_TITLE Organization title
- --output, -o FILE File where the script will be written.
- -h, --help Print help

2.78.5. hammer virt-who-config info

Show a virt-who configuration

Usage:

hammer virt-who-config info [OPTIONS]

Options:

- --id ID
- --location LOCATION NAME Location name
- --location-id LOCATION ID
- --location-title LOCATION_TITLE Location title --name NAME Name to search by

- --organization-title ORGANIZATION_TITLE Organization title
- -h, --help Print help

2.78.6. hammer virt-who-config list

List of virt-who configurations

Usage:

hammer virt-who-config list [OPTIONS]

Options:

- --location LOCATION_NAME Location name
- --location-id LOCATION_ID
- --location-title LOCATION TITLE Location title
- --order ORDER Sort field and order, eg. 'id DESC'
 --organization ORGANIZATION_NAME Organization name
- --organization-id ORGANIZATION ID Organization ID
- --organization-title ORGANIZATION TITLE Organization title
- --page PAGE Paginate results
- --per-page PER_PAGE Number of entries per request
- --search SEARCH Filter results
- -h, --help Print help

2.78.7. hammer virt-who-config update

Update a virt-who configuration

_

Usage:

hammer virt-who-config update [OPTIONS]

Options:

--blacklist BLACKLIST Hypervisor blacklist, applicable only when filtering mode is set

to 2.

Wildcards and regular expressions are supported, multiple records must

be

Separated by comma.

--debug DEBUG Enable debugging output

One of true/false, yes/no, 1/0.

--exclude-host-parents EXCLUDE_HOST_PARENTS Applicable only for esx provider type. Hosts

which parent (usually

ComputeResource) name is specified in comma-separated list in this

option

Will NOT be reported. Wildcards and regular expressions

Are supported, multiple records must be separated by comma. Put the

value

Into the double-quotes if it contains special characters like comma. All New line characters will be removed in resulting configuration file, white

Spaces are removed from beginning and end.

--filter-host-parents FILTER_HOST_PARENTS Applicable only for esx provider type. Only hosts

which parent (usually

ComputeResource) name is specified in comma-separated list in this

option

Will be reported. Wildcards and regular expressions are supported,

multiple

Records must be separated by comma. Put the value into the double-

quotes if

It contains special characters like comma. All new line characters will be Removed in resulting configuration file, white spaces are removed from

Beginning and end.

--filtering-mode MODE Hypervisor filtering mode

Possible value(s): 'none', 'whitelist', 'blacklist'

--hypervisor-id HYPERVISOR ID Specifies how the hypervisor will be identified.

Possible value(s): 'hostname', 'uuid', 'hwuuid'

--hypervisor-password HYPERVISOR_PASSWORD Hypervisor password, required for all hypervisor types except for libvirt

--hypervisor-server HYPERVISOR_SERVER Fully qualified host name or IP address of the hypervisor

--hypervisor-type HYPERVISOR_TYPE Hypervisor type

Possible value(s): 'esx', 'rhevm', 'hyperv', 'xen', 'libvirt', 'kubevirt'

--hypervisor-username HYPERVISOR_USERNAME Account name by which virt-who is to connect to the hypervisor.

--id ID Configuration numeric identifier

--interval INTERVAL Configuration interval in minutes

Possible value(s): '60', '120', '240', '480', '720', '1440', '2880', '4320'

--location LOCATION_NAME Location name

--location-id LOCATION ID

--location-title LOCATION_TITLE
--name NAME
--new-name NEW_NAME
Location title
Name to search by
Configuration name

--no-proxy NO_PROXY Ignore Proxy. A comma-separated list of hostnames or

domains or ip

Addresses to ignore Capsule settings for. Optionally this may be set to * To bypass proxy settings for all hostnames domains or ip addresses.

--organization ORGANIZATION_NAME Organization name
--organization-id ORGANIZATION_ID Organization ID

--proxy PROXY HTTP Proxy that should be used for communication between the

server on

Which virt-who is running and the hypervisors and virtualization

managers.

--satellite-url SATELLITE_URL Satellite server FQDN

--whitelist WHITELIST Hypervisor whitelist, applicable only when filtering mode is set

to 1.

Wildcards and regular expressions are supported, multiple records must

be

Separated by comma.

-h, --help Print help