

AVL Trees

AVL Tree is a self-balancing BST.

Balance Factor in AVL tree = height(left Subtree) - height(right Subtree) and always equal to {-1, 0, 1}

There are 4 cases of rotation in an AVL Tree:

- a. LL Case
 - Right Rotate
- b. RR Case
 - Left Rotate
- c. LR Case
 - Left Rotate
 - Right Rotate
- d. RL Case
 - Right Rotate
 - Left Rotate

AVL Tree Code (Insertion)

```
public class AVLTrees {
    static class Node {
        int data, height;
        Node left, right;

        Node(int data) {
            this.data = data;
            height = 1;
        }
    }

    public static Node root;

public static int height(Node root) {
        if (root == null)
            return 0;
    }
}
```



```
return root.height;
public static Node rightRotate(Node y) {
    Node x = y.left;
   Node T2 = x.right;
    x.right = y;
    y.left = T2;
    y.height = Math.max(height(y.left), height(y.right)) + 1;
    x.height = Math.max(height(x.left), height(x.right)) + 1;
    return x;
public static Node leftRotate(Node x) {
    Node y = x.right;
   Node T2 = y.left;
    y.left = x;
    x.right = T2;
    x.height = Math.max(height(x.left), height(x.right)) + 1;
    y.height = Math.max(height(y.left), height(y.right)) + 1;
    return y;
public static int getBalance(Node root) {
```



```
return 0;
    return height(root.left) - height(root.right);
public static Node insert(Node root, int key) {
        return new Node (key);
        root.left = insert(root.left, key);
    else if (key > root.data)
        root.right = insert(root.right, key);
    root.height = 1 + Math.max(height(root.left), height(root.right));
    int bf = getBalance(root);
    if (bf > 1 && key < root.left.data)
        return rightRotate(root);
    if (bf < -1 && key > root.right.data)
        return leftRotate(root);
    if (bf > 1 && key > root.left.data) {
        root.left = leftRotate(root.left);
        return rightRotate(root);
    if (bf < -1 && key < root.right.data) {
        root.right = rightRotate(root.right);
        return leftRotate(root);
```

```
public static void preorder(Node root) {
    if(root == null) {
    System.out.print(root.data + " ");
    preorder(root.left);
    preorder(root.right);
public static void main(String[] args) {
    root = insert(root, 10);
    root = insert(root, 20);
    root = insert(root, 30);
    root = insert(root, 40);
    root = insert(root, 50);
    root = insert(root, 25);
    preorder (root);
```



AVL Tree Deletion

BST delete is a recursive function in which, after deletion, we get pointers to all ancestors one by one in a bottom up manner. So we don't need a parent pointer to travel up. The recursive code itself travels up and visits all the ancestors of the deleted node.

- a. Perform the normal BST deletion.
- b. The current node must be one of the ancestors of the deleted node. Update the height of the current node.
- c. Get the balance factor (left subtree height right subtree height) of the current node.
- d. If the balance factor is greater than 1, then the current node is unbalanced and we are either in the Left Left case or Left Right case. To check whether it is Left Left case or Left Right case, get the balance factor of the left subtree. If the balance factor of the left subtree is greater than or equal to 0, then it is Left Left case, else Left Right case.
- e. If the balance factor is less than -1, then the current node is unbalanced and we are either in the Right Right case or Right Left case. To check whether it is a Right Right case or Right Left case, get the balance factor of the right subtree. If the balance factor of the right subtree is smaller than or equal to 0, then it is Right Right case, else Right Left case.

```
for non-empty BST, return the node with MIN data
public static Node getMinNode(Node root) {
    Node curr = root;
    while (curr.left != null)
    curr = curr.left;
    return curr;
public static Node deleteNode(Node root, int key) {
        return root;
    if (key < root.data) {
        root.left = deleteNode(root.left, key);
    else if (key > root.data) {
        root.right = deleteNode(root.right, key);
```

```
if ((root.left == null) || (root.right == null)) {
        Node temp = null;
        if (temp == root.left)
            temp = root.right;
            temp = root.left;
        if (temp == null)
            temp = root;
            root = temp; // Copy the contents of
        Node temp = getMinNode(root.right);
        root.data = temp.data;
        root.right = deleteNode(root.right, temp.data);
    return root;
root.height = Math.max(height(root.left), height(root.right)) + 1;
int bf = getBalance(root);
if (bf > 1 && getBalance(root.left) >= 0)
    return rightRotate(root);
if (bf > 1 && getBalance(root.left) < 0)
```

```
shrutikolla.2002@gm
```

```
root.left = leftRotate(root.left);
    return rightRotate(root);

}

// Right Right Case

if (bf < -1 && getBalance(root.right) <= 0)
    return leftRotate(root);

// Right Left Case

if (bf < -1 && getBalance(root.right) > 0)

{
    root.right = rightRotate(root.right);
    return leftRotate(root);
}

return root;
}
```

APNA COLLEGE