```
vsFTP: Very Secure FTP
``````````````````````
package: vsftpd
service: vsftpd
Port 21: The Control Connection
Port 20: The Data Connection
1) Install
dnf install vsftpd -y

2) Default DocumentRoot for public access
cd /var/ftp/pub
touch file{1..10}.txt

Default DocumentRoot for users is HOME DIR of user

3) Configuration File:
vim /etc/vsftpd/vsftpd.conf
anonymous_enable = YES

:wq

4) Start the service:
systemctl restart vsftpd
systemctl enable vsftpd
systemctl is-active vsftpd
systemctl is-enabled vsftpd

5) Firewall :
firewall-cmd --add-service=ftp --permanent
firewall-cmd --reload
firewall-cmdf --list-all

On Client:

1) Software [FileZilla]
2) On CLI:
Install client side tool to access ftp
dnf install ftp -y
ftp master.itiss.com
OR
ftp 192.168.37.128

=> For anonymous login, the user is `ftp` and no password
=> For regular user the username is regular user & and the password for regular user is a regular
password of a regular user.

```
```

```
Network File Share:
``````````````````
Port   : 2049/tcp
Package   : nfs-utils
Service   : nfs-server
Service Acc   : nfsnobody
Config   : /etc/exports

`````````````````````````````
ON SERVER:
``````````
1) Install
``````````
# dnf install nfs-utils -y

2)

# mkdir /data
# touch /data/file{1..10}.txt
# chmod 770 /data -R

3) Configure NFS server to share directory:

$ sudo vim /etc/exports

FULL_DIR_PATH   x.x.x.x(rw,sync,no_root_squash,no_subtree_check)

| x.x.x.x : Share the NFS DIR to an IP only
| ro      : Read Only
| rw      : Read & Write
| sync    : Sync the data between Clients & server
| no_root_squash : On client side ROOT user can also access NFS shared data
| no_subtree_check : Disable sub tree check [Do not lookup parent to child]

---------------OR--------------------
FULL_DIR_PATH   x.x.x.x(rw,sync) x.x.x.x(rw,sync,no_root_squash,no_subtree_check)
---------------OR--------------------
FULL_DIR_PATH   192.168.206.0/24(rw,sync,no_root-squash,no_subtree_check)
---------------OR--------------------
FULL_DIR_PATH   192.168.206.0/24(rw,sync,no_root-squash,no_subtree_check)
10.0.0.0/16(rw,sync,no_subtree_check)
---------------OR--------------------
FULL_DIR_PATH   *(rw,sync,no_subtree_check)

| * : Wildcard [0.0.0.0/0] ( All networks/ANY )

e) Verify the NFS Shared dir is shared or not:

- Restart NFS service

$ sudo systemctl restart nfs-server
$ sudo systemctl status nfs-server

- Verify the shared content via NFS:

$ sudo exportfs -a



_____________________________________
On Client
``````````
# dnf install nfs-utils -y  [CentOS]
```
```

```
# apt install nfs-common -y [Debian]

TEMP MOUNTING:
```````````````
# mount -t nfs 192.168.1.254:/data /mnt

-t  : type of filesystem
192.168.1.254 : NFS server IP

# df -h

# umount /mnt

Mounting permanently
````````````````````
# vim /etc/fstab

192.168.1.254:/data     /mnt    nfs   defaults   0  0

:wq

# mount -a
# df -h
```