

MAS 433: Cryptography

Lecture 4
Block Cipher (Part 1, Introduction)

Wu Hongjun

Lecture Outline

- Classical ciphers
- Symmetric key encryption
 - One-time pad & information theory
 - **Block cipher**
 - DES, Double DES, Triple DES
 - AES
 - Mode of Operations
 - Attacks
 - Stream cipher
- Hash function and Message Authentication Code
- Public key encryption
- Digital signature
- Key establishment and management
- Introduction to other cryptographic topics

Lecture Outline (contd.)

- Information theoretical security & computational security
- Practical symmetric key ciphers
- Introduction to block cipher

Recommended Reading

- CTP Section 3.1, 3.2
- HAC Section 7.1, 7.2.1
- Wikipedia:
 - Block cipher
http://en.wikipedia.org/wiki/Block_cipher

Information-Theoretical Security vs Computational Security


- Information-theoretically secure
 - Also called “unconditionally secure”
 - A cryptosystem is information-theoretically secure if it is secure even when the attacker has **unlimited computing power**
 - One case we have studied
 - One-time pad: perfect secrecy
 - But the one-time key’s length is as long as the message
 - Inconvenient to use for many applications
- Computationally secure
 - A cryptosystem is computationally secure if it cannot be broken with **the current computing technology** within a **given period of time**.

Computing power today

- Intel Core-i3, i5, i7 CPUs
 - Widely used CPUs in 2011 (notebook, desktop computers)
 - Normally each costs less than S\$400
 - Each has two or four cores, runs at the speed about 2.5GHz
 - Each core performs about 2^{32} 64-bit integer operations per second
- The most powerful supercomputer in the world in 2010
 - Jaguar (Oak Ridge National Laboratory)
 - 224,162 Opteron CPUs
 - Perform 1.76 Pflops (about 2^{51} Floating Point Operations Per Second)
- The combined computing power of top 500 supercomputers in 2010
 - Perform 32.4 Pflops (about 2^{55} Floating Point Operations Per Second)
(about 2^{80} operations per year)
- Computer is getting faster and faster (for the same price)
 - **128-bit key is needed today**

The Fastest Computers in History

<http://en.wikipedia.org/wiki/Supercomputer>



- 1938: 1 OPS Germany
1943: 5 KOPS Post Office Research Station, Bletchley Park, UK
1961: 1.2 MFLOPS; Los Alamos National Laboratory, USA
1984: 2.4 GFLOPS ; Scientific Research Institute of Computer Complexes, USSR
1997: 1.338 TFLOPS; Sandia National Laboratories, USA
2008: 1.026 PFLOPS; Los Alamos National Laboratory, USA

Ciphertext-only attack & known-plaintext attack

- Ciphertext-only attack
 - The attacker does not know the message
 - But the attacker knows the statistical information of the message (such as the distribution of letters, digrams, trigrams ...)
- Known-plaintext attack
 - The attacker
 - knows part of the plaintext
 - tries to recover the key and to decrypt other messages being encrypted using that key
 - Known-plaintext attack is practical in many applications
 - Example: NTU webmail (protected using SSL) -- a lot of contents are identical to all the users (such as the NTU logo, webpage frame, email protocol)

Kerckhoffs' principle

- Kerckhoffs' principle
 - The attacker knows the specifications of the cipher except the secret key
 - A strong cipher should remain secure in the above scenario
- Do we need to publish every cipher according to Kerckhoff's principle?
 - Making a cipher public makes sense only if we assume that all the attackers are cooperative (i.e., they will publish their attacks)

Practical Symmetric Key Ciphers

- Practical ciphers are required to be at least
 - Computationally secure
 - Strong even when the attacker knows the cipher specifications (Kerchoffs' principle)
 - Strong against known-plaintext attack
 - Convenient to use
 - A relatively short key (for example: a 128-bit key) can be used to encrypt many messages without compromising security
- Two types of practical symmetric key ciphers
 - Block cipher
 - Stream cipher

Block Cipher

- Substitution cipher
 - The size of the substitution table is small
 - 26 elements (for English)
 - Extremely weak against
 - ciphertext-only attack & known-plaintext attack
 - What will happen if we increase the size of the secret substitution table to 2^{128} elements?
 - The resulting cipher is strong!
 - What is the complexity of known-plaintext attack?
 - But the key (substitution table) size is too large to store

International Data Corporation (IDC) estimates that the amount of data generated in 2009 was 1.2 million Petabytes ($\approx 2^{70}$ bytes $\approx 10^{21}$ bytes)


The internet size is estimated to be 5 million Terabytes ($\approx 2^{62}$ bytes) of data. Google indexed roughly 200 terabytes ($\approx 2^{48}$ bytes) of that, or 0.004% of the total size (Eric Schmidt, CEO of Google, 2005).

Block Cipher

- Block cipher
 - Maybe viewed as a huge “substitution cipher”
 - DES: a “substitution table with 2^{64} elements”
 - AES: a “substitution table with 2^{128} elements”
 - But each element in the huge “table” is computed only when it is needed
 - So there is no need to store the huge table
 - How to compute each element?
 - Equivalent to: how to encrypt a message block?
 - how to design a block cipher?

Block Cipher: overall


- an n -bit plaintext block is encrypted to an n -bit ciphertext block
 - Block size: n bits
 - DES: 64 bits
 - AES: 128 bits
 - Key size
 - DES: 56 bits, (insecure today)
 - 3-DES: 112 or 168 bits
 - AES: 128, 192 or 256 bits



Block Cipher: Iterated Structure

- To simplify the design, security evaluation and implementation, a **round function** is used repeatedly in a block cipher
 - A typical block cipher consists of
 - r rounds (one **round function** for each round)
 - Normally a **round key** is used for each round
 - **key schedule**
 - round keys are generated from the secret key

Block Cipher: Iterated Structure (contd.)



Block Cipher: Round Function

- How to design the round function?
 - Design strategy
 - **Confusion** (non-linear)
 - Combine bits in a nonlinear way
 - » Small substitution table
 - » Multiplication together with XOR
 - » addition together with XOR
 - »
 - **Diffusion**
 - Let all the bits affect each other
 - » Permutation
 - » Shift, Rotation
 - »

Block Cipher: Round Function (contd.)

- Two main approaches to design round function
 - Substitution-permutation network (SPN)
 - AES ...
 - Feistel network
 - DES ...
 - To be learned soon ...


Block Cipher: Key Schedule

- How to design key schedule
 - Many different approaches
 - No perfect guideline so far
 - Basic rule:
 - Each bit of the key should affect many round key bits at **different** locations

Example: A Simple Block Cipher

http://en.wikipedia.org/wiki/Substitution-permutation_network

- **Substitution-Permutation network**
 - Confusion: substitution
 - Substitution table: secret or public
 - Diffusion: permutation
 - Permutation: normally public
- Example: A toy cipher
 - Block size: 16 bits
 - 3 rounds
 - Substitution
 - four Sboxes
 - Each Sbox: 4x4-bit
 - Permutation
 - Bit-wise permutation
 - 16 positions being permuted
 - Carefully chosen to ensure quick diffusion
 - Each plaintext bit affects all the 16 bits in the state after 2 rounds.



How to design the substitution table?

Summary

- Information-theoretical security & computational security
- Practical symmetric key ciphers
 - Computational security
 - Kerckhoffs' principle
 - Known-plaintext attack & ...
- Block Cipher
 - Iterated structure
 - Round function & round key
 - Key schedule
 - Round function
 - Design strategy: Confusion & diffusion
 - Methods:
 - Substitution-permutation network
 - Feistel network