

Mobile Hamburger Menu Fix - December 18, 2024

Issue Report

User reported that the hamburger menu was not visible on mobile devices after signing in, preventing navigation on mobile.

Root Cause Analysis

After investigating the `MainNavigation` component (`components/navigation/main-navigation.tsx`), several issues were identified:

- 1. **Overflow Clipping:** The parent flex container had `overflow-hidden` which could clip the hamburger button on small screens
- 2. **Z-index Stacking:** The button had z-index 70, but the header had z-index 9999, creating potential stacking context issues
- 3. **Extra Wrapper Div:** The button was wrapped in an extra div that might have interfered with visibility
- 4. **Implicit Visibility:** The button relied on Tailwind classes without explicit inline visibility styles

Changes Made

1. Removed Overflow Clipping

File: `components/navigation/main-navigation.tsx` (Line 144)

Before:

```
<div className="flex items-center justify-between h-16 gap-2 sm:gap-3 min-h-[64px] max-w-[100vw] overflow-hidden">
```

After:

```
<div className="flex items-center justify-between h-16 gap-2 sm:gap-3 min-h-[64px] w-full">
```

Reason: Removed `overflow-hidden` and `max-w-[100vw]` to prevent the hamburger button from being clipped on small mobile screens.

2. Simplified Button Structure

File: `components/navigation/main-navigation.tsx` (Lines 165-194)

Before:

```

<div
  className="lg:hidden ml-auto flex-shrink-0 relative z-[70]"
  style={{
    isolation: 'isolate',
    WebkitTransform: 'translateZ(0)',
    transform: 'translateZ(0)',
  }}
>
  <SheetTrigger asChild>
    <Button ... />
  </SheetTrigger>
</div>

```

After:

```

<SheetTrigger asChild>
  <Button
    className="lg:hidden ... flex-shrink-0"
    style={{
      zIndex: 9999,
      display: 'inline-flex',
      visibility: 'visible',
      opacity: 1,
      ...
    }}
    ...
  />
</SheetTrigger>

```

Reason:

- Removed extra wrapper div to simplify DOM structure
- Moved `lg:hidden` class directly to button
- Added `flex-shrink-0` to prevent button from shrinking

3. Enhanced Visibility Styles

File: `components/navigation/main-navigation.tsx` (Lines 172-183)

Added Inline Styles:

```

style={{
  WebkitTapHighlightColor: 'transparent',
  WebkitTouchCallout: 'none',
  WebkitUserSelect: 'none',
  position: 'relative',
  zIndex: 9999,                // ← Increased from 70
  minWidth: '48px',
  minHeight: '48px',
  display: 'inline-flex',      // ← Explicit display
  visibility: 'visible',      // ← Explicit visibility
  opacity: 1,                 // ← Explicit opacity
}}

```

Reason:

- Increased z-index to 9999 to match header z-index

- Added explicit `display`, `visibility`, and `opacity` to override any CSS that might hide the button
- Ensured minimum touch target size of 48x48px for accessibility

4. Improved Click Handler

File: `components/navigation/main-navigation.tsx` (Lines 184-189)

Added:

```
onClick={(e) => {  
  e.stopPropagation();  
  console.log('Mobile menu button clicked');  
  setMobileMenuOpen(true); // ← Explicit state update  
}}
```

Reason: Added explicit `setMobileMenuOpen(true)` call to ensure the menu opens even if the Sheet component's trigger doesn't fire properly.

Testing Recommendations

Manual Testing Steps:

1. Navigate to <https://mindfulchampion.com> on a mobile device (or use Chrome DevTools mobile viewport)
2. Sign in with valid credentials
3. Verify the hamburger menu button (green button with three horizontal lines) is visible in the top-right corner
4. Tap/click the hamburger menu button
5. Verify the mobile navigation menu slides in from the right
6. Test navigation links work correctly
7. Verify the menu closes when clicking outside or on a link

Test Devices:

- iPhone (Safari and Chrome)
- Android phone (Chrome)
- iPad (Safari)
- Chrome DevTools mobile viewport (various sizes: 375px, 390px, 414px widths)

Expected Behavior:

- ☒ Hamburger menu button is always visible on screens < 1024px width
- ☒ Button is positioned in the top-right corner of the header
- ☒ Button has a green background with white menu icon
- ☒ Button is easily tappable (48x48px minimum)
- ☒ Clicking button opens the mobile navigation menu
- ☒ Menu contains all navigation sections (Training, Progress, Connect, Tournaments, Account)
- ☒ Menu closes when clicking outside or selecting a link

Files Modified

1. `components/navigation/main-navigation.tsx` - Main navigation component with hamburger menu

Deployment

- **Commit:** `a712d22` - “Fix mobile hamburger menu visibility: Remove overflow-hidden, increase z-index, add explicit visibility styles”
- **Pushed to:** GitHub master branch
- **Auto-deployed to:** Vercel (<https://mindfulchampion.com>)
- **Deployment Time:** ~2-3 minutes after push

Additional Notes

Why the Issue Occurred:

The hamburger menu button was likely being:

1. Clipped by the parent container's `overflow-hidden` property
2. Hidden by z-index stacking context issues
3. Affected by CSS specificity conflicts from global mobile styles

Prevention:

- Always test mobile navigation on actual devices, not just desktop DevTools
- Use explicit inline styles for critical UI elements that must always be visible
- Avoid `overflow-hidden` on flex containers that contain important interactive elements
- Ensure z-index values are consistent across parent and child elements

Related Components:

- `components/ui/sheet.tsx` - Sheet component used for mobile menu
- `app/mobile-fixes.css` - Global mobile CSS fixes
- `components/pages/redesigned-home-dashboard.tsx` - Dashboard that includes MainNavigation

Verification

After deployment completes, the user should:

1. Clear browser cache or use incognito mode
2. Navigate to <https://mindfulchampion.com>
3. Sign in with their credentials
4. Verify the hamburger menu is now visible and functional on mobile

If the issue persists, check:

- Browser console for JavaScript errors
- Network tab to ensure latest deployment is loaded
- CSS computed styles on the button element to identify any overriding styles