

Python CLI steps

AWS CLI

1. SETUP

The customers will be provided 3 wheels files (.whl) which they will use to install the AWS CLI. AWS CLI uses python so an installation of python would also be required.

2. INSTALLATION

1. Install python version 3.7+ and python virtual environment
2. Create a virtual environment to keep the AWS CLI for SFT beta installation separate from general AWS CLI

On MacOS/Linux

```
python3 -m venv python-sdk-test
source python-sdk-test/bin/activate
```

On Windows

```
py -m venv python-sdk-test
.\python-sdk-test\Scripts\activate
```

3. Install Botocore

```
python3 -m pip install botocore-1.31.80-py3-none-any.whl
```

4. Install boto3

```
python3 -m pip install boto3-1.28.80-py3-none-any.whl
```

5. Install aws cli

```
python3 -m pip install awscli-1.29.80-py3-none-any.whl
```

6. Make sure your shell is pointing to the preview build aws binary and not a globally installed one. The aws binary found in your PATH should look something like the following:

```
$ which aws
/path/to/preview-build/virtual-env/bin/aws
```

7. If the output shows your globally installed aws (i.e., /usr/local/bin/aws), then run the following command to reset the cache that your shell is looking in for the aws executable and try again.

```
$ hash -r
```

8. Verify the right aws cli is working by running the following command in a terminal and confirming the printed name is the same as the wheels file.

```
aws --version
```

3. VALIDATION

CreateFuotaTask

```
$ aws iotwireless create-fuota-task --firmware-update-image s3://some-bucket/object \
    --firmware-update-role <some-role> --protocol-type Sidewalk \
    --name "Sidewalk_test" --fragment-size-bytes 1024

{
  "Arn": "arn:aws:iotwireless:us-east-1:<accountid>:FuotaTask/<some-id>",
  "Id": "<some-id>"
}
```

GetFuotaTask

```
aws iotwireless get-fuota-task --id <some-id>

{
  "Arn": "arn:aws:iotwireless:us-east-1:<accountid>:FuotaTask/<some-id>",
  "Id": "<some-id>",
  "Status": "Pending",
  "Name": "Sidewalk_test",
  "FirmwareUpdateImage": "s3://some-bucket/object",
  "FirmwareUpdateRole": "arn:aws:iam::<accountid>:role/<some-role>",
  "CreatedAt": 1702543097.701,
  "FragmentSizeBytes": 1024,
  "ProtocolType": "Sidewalk"
}
```

ASSOCIATEWIRELESSDEVICEWITHFUOTATASK

```
aws iotwireless associate-wireless-device-with-fuota-task --id <some-id> \
    --wireless-device-id <some-wireless-device-id>
```

START-FUOTA-TASK

```
aws iotwireless start-fuota-task --id <some-id> \
    --sidewalk StartTime="2023-12-15T00:00:00"
```