## PostgreSQL server configuration

Document author: anna.hammais@tyks.fi

Useful options to cofigure in the PostgreSQL server, according to https://wiki.postgresql.org/wiki/Tuning\_Your\_PostgreSQL\_Server:

```
select * from pg_settings
where name in
('shared_buffers',
'checkpoint_segments',
'effective_cache_size',
'checkpoint_completion_target',
'maintenance_work_mem',
'autovacuum_work_mem',
'ual_buffers',
'config_file');
```

- shared\_buffers 25% of system memory (default very small)
- checkpoint\_segments default 3, set to 20
- effective\_cache\_size 50% of system RAM (not hard allocation, just an estimate of max needs)
- checkpoint\_completion\_target set to 0.9
- maintenance\_work\_mem set to 64MB
- autovacuum\_work\_mem -1, which means to use maintenance\_work\_mem
- wal\_buffers default 1/32 of shared buffers, which is ok

These changes should be entered in the *postgresql.conf* file, located by starting psql as superuser on the ktppg server:

```
ssh ktp@ktppg.vsshp.net
sudo su -
psql
psql> show config_file;
```

The PostgreSQL server must be restarted for these changes to take effect. You can check this by re-running the above select query after the restart.

2018-01-18 Subtopic Page 1/1